

---

# **resistics**

***Release 1.0.0a3***

**Neeraj Shah**

**May 12, 2023**



**USER GUIDE:**

<b>1</b>	<b>Why?</b>	<b>3</b>
<b>2</b>	<b>What’s new?</b>	<b>5</b>
<b>3</b>	<b>What’s missing?</b>	<b>7</b>
<b>4</b>	<b>Next steps</b>	<b>9</b>
4.1	Getting started . . . . .	9
4.1.1	Installation . . . . .	9
4.1.2	Tutorials . . . . .	9
4.2	Custom processes . . . . .	90
4.3	resistics package . . . . .	90
4.3.1	Submodules . . . . .	90
4.3.2	Module contents . . . . .	408
4.4	Literature references . . . . .	408
<b>5</b>	<b>Index</b>	<b>409</b>
	<b>Bibliography</b>	<b>411</b>
	<b>Python Module Index</b>	<b>413</b>
	<b>Index</b>	<b>415</b>



Soon resistics will be upgrading to version 1.0.0. This will be a breaking change versus version 0.0.6. Currently, the newest version is available as a development release for those who are intersted in experimenting with its updated feature set.

Until version 1.0.0 is released as a stable version, the existing documentation for 0.0.6 will remain at [resistics.io](https://resistics.io).



## **WHY?**

Resistics has been re-written from the ground up to tackle several limitations of the previous version, namely

- Processing time
- Limited traceability
- Lack of extensibility
- Difficult to maintain

The new version of resistics aims to tackle all of these issues through better coding practises, putting extensibility at the heart of its design and moving to a modern deployment pipeline.





## WHAT'S NEW?

The literal answer is everything as this is a from scratch rewrite, which has taken some features of the previous version but combined them with new capabilities.

For most users, notable changes are related to configuration of processing flows and the carving out of specific data format readers into a separate package.

Advanced users will be able to take advantage of opportunities to write their own solvers or processors and a greater ability to customise and extend resistics.

Other smaller changes include:

- Moving to JSON for metadata as this is a universal format
- Moving from matplotlib to plotly for plots as they are more interactive



## WHAT'S MISSING?

The first thing to note is that time series data reader for various formats have been removed from resistics and placed in a sister package named resistics-readers. This is to remove any coupling of data format support to core resistics releases. It is hoped that resistics-readers will receive more community support as knowledge about the various data formats in the magnetotelluric world is distributed around the community.

Statistics are another capability of resistics 0.0.6 that is missing. The intention is to re-introduce these shortly and additionally, make it easier for users to write their own features to extract.

Masks are also missing and these will be re-introduced with statistics.



## NEXT STEPS

### 4.1 Getting started

The best way to get started with resistics is to install the package and begin with the examples.

#### 4.1.1 Installation

Resistics can be installed using pip. For most users, it is recommended to install both resistics and the resistics-readers package which provides support for several data formats.

```
python -m pip install resistics resistics-readers
```

For those who do not need the data support in resistics-readers, it is sufficient to install only resistics

```
python -m pip install resistics
```

#### 4.1.2 Tutorials

##### Reading data

The main resistics package supports two time data formats and two calibration data formats.

For time data:

- ASCII (including compressed ASCII, e.g. bz2)
- numpy .npy

Where possible, it is recommended to use the numpy data format for time data as this is quicker to read from. Whilst it is a binary format, it is portable and well supported by the numpy package.

For calibration data, resistics supports:

- Text file calibration data
- JSON calibration data

The structure of these two calibration data formats can be seen in the relevant examples.

---

**Note:** Support for other data formats is provided by the resistics-readers package. This includes support for Metronix ATS data, SPAM RAW data, Phoenix TS data, Lemi data and potentially more in the future.

---

## Time data ASCII

This example will show how to read time data from an ASCII file using the default ASCII data reader. To do this, a metadata file is required. The example shows how an appropriate metadata file can be created and the information required to create such a metadata file.

The dataset in this example has been provided for use by the SAMTEX consortium. For more information, please refer to [Jones2009]. Additional details about the dataset can be found at <https://www.mtnet.info/data/kap03/kap03.html>.

The dataset is KAP175. A couple of notes:

- The data has a sample every 5 seconds, meaning a 0.2 Hz sampling frequency.
- Values of 1E32 have been replaced by NaN

```
from pathlib import Path
import pandas as pd
from resistics.time import ChanMetadata, TimeMetadata, TimeReaderAscii, InterpolateNans
import plotly
```

Define the data path. This is dependent on where the data is stored. Here, the data path is being read from an environment variable.

```
time_data_path = Path("../", "..", "data", "time", "ascii")
ascii_data_path = time_data_path / "kap175as.ts"
```

The folder contains a single ascii data file. Let's have a look at the contents of the file.

```
with ascii_data_path.open("r") as f:
    for line_number, line in enumerate(f):
        print(line.strip("\n"))
        if line_number >= 130:
            break
```

```
# time series file from tssplice
# date: Mon Nov  7 05:44:13 2016
#
# Files spliced together:
# kap175a1  2003-10-31 11:00:00-2003-11-06 15:17:39
# kap175b1  2003-11-06 16:00:00-2003-11-15 09:56:39
#
# Following comment block from first file...
#
# time series file from mp2ts
# date: Mon Nov  7 05:44:07 2016
#
# input file: kap175\kap175a1.lmp
#
# Machine endian: Little
# UNIX set      : F
#
# site description: maroi
#
# Latitude      :022:11:30 S
# Longitude     :029:51:31 E
```

(continues on next page)

(continued from previous page)

```

#
# LiMS acquisition code : 10.2
# LiMS box      number   :   53
# Magnetometer number   :   53
#
# Ex line length (m):      100.00
# Ey line length (m):      94.00
#
# Azimuths relative to: MAGNETIC NORTH
# Ex azimuth;  30
# Ey azimuth; 120
# Hx azimuth;  30
# Hy azimuth; 120
#
# FIRST 20 POINTS DROPPED FROM .1mp FILE TO
# ACCOUNT FOR FILTER SETTLING
#
#F Filter block begin
#F
#F Filters applied to LiMS/LRMT data are:
#F 1: Analogue anti-alias six-pole Bessel low-pass
#F   filters on each channel with -3 dB point at nominally 5 Hz.
#F   -calibrated values given below
#F
#F 2: Digital anti-alias multi-stage Chebyshev FIR filters
#F   with final stage at 2xsampling rate
#F
#F 1: Analogue single-pole Butterworth high-pass filters on the
#F   telluric channels only with -3 dB point at nominally 30,000 s
#F   -calibrated values given below
#F
#F Chan      Calib      Low-pass      High-pass (s)
#F  1         1.00         0.00         0.00
#F  2         1.00         0.00         0.00
#F  3         1.00         0.00         0.00
#F  4         1.00         0.00         0.00
#F  5         1.00         0.00         0.00
#F
#F In the tsrestack code, these filter responses are
#F removed using bessell7.f and highl7.f
#F
#F Filter block end
>INFO_START:
>STATION      :kap175
>INSTRUMENT: 53
>WINDOW       :kap175as
>LATITUDE    : -22.1916695
>LONGITUDE   : 29.8586102
>ELEVATION   : 0.
>UTM_ORIGIN  : 27.
>UTM_NORTH   : -2456678
>UTM_EAST    : 794763

```

(continues on next page)

(continued from previous page)

```

>COORD_SYS :MAGNETIC NORTH
>DECLIN    : 0.
>FORM      :ASCII
>FORMAT    :FREE
>SEQ_REC   : 1
>NCHAN     : 5
>CHAN_1    :HX
>SENSOR_1  : 53
>AZIM_1    : 30.
>UNITS_1   :nT
>GAIN_1    : 1.
>BASELINE_1: 12618.2402
>CHAN_2    :HY
>SENSOR_2  : 53
>AZIM_2    : 120.
>UNITS_2   :nT
>GAIN_2    : 1.
>BASELINE_2: -7354.87988
>CHAN_3    :HZ
>SENSOR_3  : 53
>AZIM_3    : 0.
>UNITS_3   :nT
>GAIN_3    : 1.
>BASELINE_3: -26291.1992
>CHAN_4    :EX
>SENSOR_4  : 53
>AZIM_4    : 30.
>UNITS_4   :mV/km
>GAIN_4    : 1.
>CHAN_5    :EY
>SENSOR_5  : 53
>AZIM_5    : 120.
>UNITS_5   :mV/km
>GAIN_5    : 1.
>STARTTIME :2003-10-31 11:00:00
>ENDTIME    :2003-11-15 09:56:39
>T_UNITS    :s
>DELTA_T    : 5.
>MIS_DATA   : 1.000000003E+32
>INFO_END   :
  2.39398551  1.43499565  2.21125007 -1.55760086  0.0748437345
  2.23659754  1.09759927  2.16549993 -6.5316  1.9800632
  1.6032145  0.608650982  2.02824998 -14.0248184  3.94819808
  0.724482358 -0.00434030406  1.79949999 -22.1152382  4.54121494
 -0.170995399 -0.679827273  1.54025006 -28.7814693  4.58896542
 -1.17621446 -1.34823668  1.28100002 -33.5379982  5.47701597
 -2.31609321 -1.93590927  0.991250038 -37.1378212  6.52709579
 -3.41281223 -2.44583607  0.701499999 -38.6588211  6.6605401
 -4.29263926 -2.81293082  0.442250013 -37.8415413  6.49546909
 -4.97082424 -3.01078033  0.244000003 -35.6481323  6.60037565
 -5.44532394 -3.07342243  0.106749997 -31.5662174  6.48429155
 -5.67856073 -2.94394422  0.0305000003 -26.1866817  6.25566292

```

(continues on next page)



(continued from previous page)

```
-5.76094007 -2.70975876 0.0152500002 -22.297369 6.53417683
-5.86769009 -2.52486253 0.0152500002 -20.8914051 7.27097702
-6.06688833 -2.39334106 0. -20.4016094 7.70362616
-6.25846148 -2.27502656 -0.0305000003 -20.194458 7.71082592
-6.485569 -2.24766445 -0.0305000003 -22.052597 7.81821918
-6.84828472 -2.35142326 -0.0457499996 -26.1871376 8.14745235
```

Note that the metadata requires the number of samples. Pandas can be useful for this purpose.

```
df = pd.read_csv(ascii_data_path, header=None, skiprows=121, delim_whitespace=True)
n_samples = len(df.index)
print(df)
```

```
      0      1      2      3      4
0    -4.292639 -2.812931 0.442250 -37.841541 6.495469
1    -4.970824 -3.010780 0.244000 -35.648132 6.600376
2    -5.445324 -3.073422 0.106750 -31.566217 6.484292
3    -5.678561 -2.943944 0.030500 -26.186682 6.255663
4    -5.760940 -2.709759 0.015250 -22.297369 6.534177
...
258428 -162.422211 -738.918762 -504.817841 10.141210 -3.474090
258429 -162.422211 -738.918762 -504.817841 9.408063 -3.485243
258430 -162.422211 -738.918762 -504.817841 8.700190 -3.631670
258431 -162.422211 -738.918762 -504.817841 8.757909 -3.823143
258432 -162.422211 -738.918762 -504.817841 8.475470 -4.004943
```

[258433 rows x 5 columns]

Define other key pieces of recording information

```
fs = 0.2
chans = ["Hx", "Hy", "Hz", "Ex", "Ey"]
first_time = pd.Timestamp("2003-10-31 11:00:00")
last_time = first_time + (n_samples - 1) * pd.Timedelta(1 / fs, "s")
```

The next step is to create a TimeMetadata object. The TimeMetadata has information about the recording and channels. Let's construct the TimeMetadata and save it as a JSON along with the time series data file.

```
chans_metadata = {}
for chan in chans:
    chan_type = "electric" if chan in ["Ex", "Ey"] else "magnetic"
    chans_metadata[chan] = ChanMetadata(
        name=chan, chan_type=chan_type, data_files=[ascii_data_path.name]
    )
time_metadata = TimeMetadata(
    fs=fs,
    chans=chans,
    n_samples=n_samples,
    first_time=first_time,
    last_time=last_time,
    chans_metadata=chans_metadata,
)
```

(continues on next page)

(continued from previous page)

```
time_metadata.summary()
time_metadata.write(time_data_path / "metadata.json")
```

```
{
  'file_info': None,
  'fs': 0.2,
  'chans': ['Hx', 'Hy', 'Hz', 'Ex', 'Ey'],
  'n_chans': 5,
  'n_samples': 258433,
  'first_time': '2003-10-31 11:00:00.000000_000000_000000_000000',
  'last_time': '2003-11-15 09:56:00.000000_000000_000000_000000',
  'system': '',
  'serial': '',
  'wgs84_latitude': -999.0,
  'wgs84_longitude': -999.0,
  'easting': -999.0,
  'northing': -999.0,
  'elevation': -999.0,
  'chans_metadata': {
    'Hx': {
      'name': 'Hx',
      'data_files': ['kap175as.ts'],
      'chan_type': 'magnetic',
      'chan_source': None,
      'sensor': '',
      'serial': '',
      'gain1': 1,
      'gain2': 1,
      'scaling': 1,
      'chopper': False,
      'dipole_dist': 1,
      'sensor_calibration_file': '',
      'instrument_calibration_file': ''
    },
    'Hy': {
      'name': 'Hy',
      'data_files': ['kap175as.ts'],
      'chan_type': 'magnetic',
      'chan_source': None,
      'sensor': '',
      'serial': '',
      'gain1': 1,
      'gain2': 1,
      'scaling': 1,
      'chopper': False,
      'dipole_dist': 1,
      'sensor_calibration_file': '',
      'instrument_calibration_file': ''
    },
    'Hz': {
      'name': 'Hz',
```

(continues on next page)

(continued from previous page)

```

        'data_files': ['kap175as.ts'],
        'chan_type': 'magnetic',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1,
        'gain2': 1,
        'scaling': 1,
        'chopper': False,
        'dipole_dist': 1,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Ex': {
        'name': 'Ex',
        'data_files': ['kap175as.ts'],
        'chan_type': 'electric',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1,
        'gain2': 1,
        'scaling': 1,
        'chopper': False,
        'dipole_dist': 1,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Ey': {
        'name': 'Ey',
        'data_files': ['kap175as.ts'],
        'chan_type': 'electric',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1,
        'gain2': 1,
        'scaling': 1,
        'chopper': False,
        'dipole_dist': 1,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    }
},
'history': {'records': []}
}

```

Now the data is ready to be read in by resistics. Read it in and print the first and last sample values.

```

reader = TimeReaderAscii(extension=".ts", n_header=121)
time_data = reader.run(time_data_path)
print(time_data.data[:, 0])

```

(continues on next page)

(continued from previous page)

```
print(time_data.data[:, -1])
```

```
[ -4.2926393  -2.8129308   0.44225  -37.84154    6.495469 ]
[-162.42221  -738.91876  -504.81784    8.47547   -4.0049434]
```

There are some invalid values in the data that have been replaced by NaN values. Interpolate the NaN values.

```
time_data = InterpolateNans().run(time_data)
```

Finally plot the data. By default, the data is downsampled using the LTTB algorithm to avoid slow and large plots.

```
fig = time_data.plot(max_pts=1_000)
fig.update_layout(height=700)
plotly.io.show(fig)
```

**Total running time of the script:** ( 0 minutes 8.907 seconds)

## Time data bz2

This example will show how to read time data from a compressed ASCII file using the default ASCII data reader. In this case, the data has been compressed using bz2.

To read such a compressed ASCII data file, a metadata file is required. The example shows how an appropriate metadata file can be created and the information required to create such a metadata file.

The dataset in this example has been provided for use by the SAMTEX consortium. For more information, please refer to [Jones2009]. Additional details about the dataset can be found at <https://www.mtnet.info/data/kap03/kap03.html>.

The dataset is KAP148. A couple of notes:

- The data has a sample every 5 seconds, meaning a 0.2 Hz sampling frequency.
- Values of 1E32 have been replaced by NaN

```
from pathlib import Path
import bz2
import pandas as pd
from resisticks.time import ChanMetadata, TimeMetadata, TimeReaderAscii, InterpolateNans
import plotly
```

Define the data path. This is dependent on where the data is stored. Here, the data path is being read from an environment variable.

```
time_data_path = Path("../", "..", "data", "time", "bz2")
ascii_data_path = time_data_path / "kap148as.ts.bz2"
```

The folder contains a single ascii data file. Let's have a look at the contents of the file.

```
with bz2.open(ascii_data_path, "rt") as f:
    for line_number, line in enumerate(f):
        print(line.strip("\n"))
        if line_number >= 130:
            break
```

```

# time series file from tsssplice
# date: Mon Nov 7 05:27:46 2016
#
# Files spliced together:
# kap148a1 2003-10-25 11:30:00-2003-11-02 10:52:04
# kap148b1 2003-11-02 11:30:00-2003-11-12 11:15:34
# kap148c1 2003-11-12 11:45:00-2003-11-21 13:43:14
# kap148d1 2003-11-21 14:30:00-2003-11-29 10:14:10
#
# Following comment block from first file...
#
# time series file from mp2ts
# date: Mon Nov 7 05:27:32 2016
#
# input file: kap148\kap148a1.1mp
#
# Machine endian: Little
# UNIX set      : F
#
# site description: suikerbosrand
#
# Latitude      :025:55:40 S
# Longitude     :026:27:04 E
#
# LiMS acquisition code : 10.2
# LiMS box      number  : 26
# Magnetometer number   : 26
#
# Ex line length (m):    100.00
# Ey line length (m):    98.00
#
# Azimuths relative to: MAGNETIC NORTH
# Ex azimuth; 0
# Ey azimuth; 90
# Hx azimuth; 0
# Hy azimuth; 90
#
# FIRST 20 POINTS DROPPED FROM .1mp FILE TO
# ACCOUNT FOR FILTER SETTling
#
#F Filter block begin
#F
#F Filters applied to LiMS/LRMT data are:
#F 1: Analogue anti-alias six-pole Bessel low-pass
#F    filters on each channel with -3 dB point at nominally 5 Hz.
#F    -calibrated values given below
#F
#F 2: Digital anti-alias multi-stage Chebyshev FIR filters
#F    with final stage at 2xsampling rate
#F
#F 1: Analogue single-pole Butterworth high-pass filters on the
#F    telluric channels only with -3 dB point at nominally 30,000 s

```

(continues on next page)

(continued from previous page)

```

#F      -calibrated values given below
#F
#F Chan      Calib      Low-pass      High-pass (s)
#F  1         1.00         0.00         0.00
#F  2         1.00         0.00         0.00
#F  3         1.00         0.00         0.00
#F  4         1.00         0.00         0.00
#F  5         1.00         0.00         0.00
#F
#F In the tsrestack code, these filter responses are
#F removed using bessell7.f and highl7.f
#F
#F Filter block end
>INFO_START:
>STATION      :kap148
>INSTRUMENT: 26
>WINDOW       :kap148as
>LATITUDE    : -25.9277802
>LONGITUDE   : 26.4511108
>ELEVATION   : 1518.
>UTM_ORIGIN  : 27.
>UTM_NORTH   : -2867639
>UTM_EAST    : 445033
>COORD_SYS   :MAGNETIC NORTH

>DECLIN      : 0.
>FORM        :ASCII
>FORMAT      :FREE

>SEQ_REC     : 1
>NCHAN       : 5
>CHAN_1      :HX
>SENSOR_1    : 26
>AZIM_1      : 0.
>UNITS_1     :nT

>GAIN_1      : 1.
>BASELINE_1  : 12410.8799
>CHAN_2      :HY
>SENSOR_2    : 26
>AZIM_2      : 90.
>UNITS_2     :nT

>GAIN_2      : 1.
>BASELINE_2  : -245.759995
>CHAN_3      :HZ
>SENSOR_3    : 26
>AZIM_3      : 0.
>UNITS_3     :nT

>GAIN_3      : 1.
>BASELINE_3  : -25784.3203

```

(continues on next page)

(continued from previous page)

```

>CHAN_4      :EX
>SENSOR_4    : 26
>AZIM_4      : 0.
>UNITS_4     :mV/km

>GAIN_4      : 1.
>CHAN_5      :EY
>SENSOR_5    : 26
>AZIM_5      : 90.
>UNITS_5     :mV/km

>GAIN_5      : 1.
>STARTTIME   :2003-10-25 11:30:00
>ENDTIME     :2003-11-29 10:14:10
>T_UNITS     :s

>DELTA_T     : 5.
>MIS_DATA    : 1.000000003E+32
>INFO_END    :
  3.00425005  2.62300014 -0.381249994  2.5315001  2.44311237
  3.01950002  2.60774994 -0.457500011  2.62300014  2.34974504
  3.01950002  2.62300014 -0.488000005  2.51625013  2.33418369
  3.03474998  2.65350008 -0.442250013  2.45525002  2.48979592
  3.06524992  2.66875005 -0.427000016  2.50099993  2.58316326
  3.04999995  2.68400002 -0.488000005  2.54675007  2.55204082
  3.09575009  2.69924998 -0.564249992  2.63825011  2.38086748
  3.21775007  2.71449995 -0.610000014  2.60774994  2.28750014

```

Note that the metadata requires the number of samples. Pandas can be useful for this purpose.

```

df = pd.read_csv(ascii_data_path, header=None, skiprows=123, delim_whitespace=True)
n_samples = len(df.index)
print(df)

```

```

      0      1      2      3      4
0  3.004250  2.623000 -0.381250  2.531500  2.443112
1  3.019500  2.607750 -0.457500  2.623000  2.349745
2  3.019500  2.623000 -0.488000  2.516250  2.334184
3  3.034750  2.653500 -0.442250  2.455250  2.489796
4  3.065250  2.668750 -0.427000  2.501000  2.583163
...
603885  67.700172 -132.892487  33.821594 -33.046749  178.160461
603886  68.035675 -132.724747  33.836845 -32.955250  398.631897
603887  67.791672 -133.105988  34.294342 -32.665501  509.894653
603888  66.952919 -134.768250  34.919594 -32.345249  508.774261
603889  66.571670 -135.332489  35.102593 -32.452000  503.001038

[603890 rows x 5 columns]

```

Define other key pieces of recording information

```

fs = 0.2
chans = ["Hx", "Hy", "Hz", "Ex", "Ey"]
first_time = pd.Timestamp("2003-10-25 11:30:00")
last_time = first_time + (n_samples - 1) * pd.Timedelta(1 / fs, "s")

```

The next step is to create a TimeMetadata object. The TimeMetadata has information about the recording and channels. Let's construct the TimeMetadata and save it as a JSON along with the time series data file.

```

chans_metadata = {}
for chan in chans:
    chan_type = "electric" if chan in ["Ex", "Ey"] else "magnetic"
    chans_metadata[chan] = ChanMetadata(
        name=chan, chan_type=chan_type, data_files=[ascii_data_path.name]
    )
time_metadata = TimeMetadata(
    fs=fs,
    chans=chans,
    n_samples=n_samples,
    first_time=first_time,
    last_time=last_time,
    chans_metadata=chans_metadata,
)
time_metadata.summary()
time_metadata.write(time_data_path / "metadata.json")

```

```

{
  'file_info': None,
  'fs': 0.2,
  'chans': ['Hx', 'Hy', 'Hz', 'Ex', 'Ey'],
  'n_chans': 5,
  'n_samples': 603890,
  'first_time': '2003-10-25 11:30:00.000000_000000_000000_000000',
  'last_time': '2003-11-29 10:14:05.000000_000000_000000_000000',
  'system': '',
  'serial': '',
  'wgs84_latitude': -999.0,
  'wgs84_longitude': -999.0,
  'easting': -999.0,
  'northing': -999.0,
  'elevation': -999.0,
  'chans_metadata': {
    'Hx': {
      'name': 'Hx',
      'data_files': ['kap148as.ts.bz2'],
      'chan_type': 'magnetic',
      'chan_source': None,
      'sensor': '',
      'serial': '',
      'gain1': 1,
      'gain2': 1,
      'scaling': 1,
      'chopper': False,

```

(continues on next page)



(continued from previous page)

```

        'dipole_dist': 1,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Hy': {
        'name': 'Hy',
        'data_files': ['kap148as.ts.bz2'],
        'chan_type': 'magnetic',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1,
        'gain2': 1,
        'scaling': 1,
        'chopper': False,
        'dipole_dist': 1,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Hz': {
        'name': 'Hz',
        'data_files': ['kap148as.ts.bz2'],
        'chan_type': 'magnetic',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1,
        'gain2': 1,
        'scaling': 1,
        'chopper': False,
        'dipole_dist': 1,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Ex': {
        'name': 'Ex',
        'data_files': ['kap148as.ts.bz2'],
        'chan_type': 'electric',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1,
        'gain2': 1,
        'scaling': 1,
        'chopper': False,
        'dipole_dist': 1,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Ey': {
        'name': 'Ey',
        'data_files': ['kap148as.ts.bz2'],

```

(continues on next page)

(continued from previous page)

```

        'chan_type': 'electric',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1,
        'gain2': 1,
        'scaling': 1,
        'chopper': False,
        'dipole_dist': 1,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    }
},
    'history': {'records': []}
}

```

Now the data is ready to be read in by resistics. Read it in and print the first and last sample values.

```

reader = TimeReaderAscii(extension=".bz2", n_header=123)
time_data = reader.run(time_data_path)
print(time_data.data[:, 0])
print(time_data.data[:, -1])

```

```

[ 3.00425    2.6230001 -0.38125    2.5315    2.4431124]
[ 66.57167  -135.33249   35.102592  -32.452   503.00104 ]

```

There are some invalid values in the data that have been replaced by NaN values. Interpolate the NaN values.

```
time_data = InterpolateNans().run(time_data)
```

Finally plot the data. By default, the data is downsampled using the LTTB algorithm to avoid slow and large plots.

```

fig = time_data.plot(max_pts=1_000)
fig.update_layout(height=700)
plotly.io.show(fig)

```

**Total running time of the script:** ( 0 minutes 5.200 seconds)

## Time data binary

If a data file is available in npy binary format, this can be read in using the TimeReaderNumpy reader as long as a metadata file can be made.

Information about the recording will be required to make the metadata file. In the below example, a metadata file is made and then the data is read.

The dataset in this example has been provided for use by the SAMTEX consortium. For more information, please refer to [Jones2009]. Additional details about the dataset can be found at <https://www.mtnet.info/data/kap03/kap03.html>.

The dataset is KAP130. A couple of notes:

- The data has a sample every 5 seconds, meaning a 0.2 Hz sampling frequency.
- Values of 1E32 have been replaced by NaN

```

from pathlib import Path
import numpy as np
import pandas as pd
from resisticks.time import TimeMetadata, ChanMetadata, TimeReaderNumpy
from resisticks.time import InterpolateNans, LowPass
import plotly

```

Define the data path. This is dependent on where the data is stored. Here, the data path is being read from an environment variable.

```

time_data_path = Path("../", "..", "data", "time", "binary")
binary_data_path = time_data_path / "kap130as.npy"

```

Define key pieces of recording information. This is known.

```

fs = 0.2
chans = ["Hx", "Hy", "Hz", "Ex", "Ey"]
first_time = pd.Timestamp("2003-10-17 15:30:00")

```

Note that the metadata requires the number of samples. This can be found by loading the data in memory mapped mode. In most cases, it is likely that this be known.

```

data = np.load(binary_data_path, mmap_mode="r")
n_samples = data.shape[1]
last_time = first_time + (n_samples - 1) * pd.Timedelta(1 / fs, "s")

```

The next step is to create a TimeMetadata object. The TimeMetadata has information about the recording and channels. Let's construct the TimeMetadata and save it as a JSON along with the time series data file.

```

chans_metadata = {}
for chan in chans:
    chan_type = "electric" if chan in ["Ex", "Ey"] else "magnetic"
    chans_metadata[chan] = ChanMetadata(
        name=chan, chan_type=chan_type, data_files=[binary_data_path.name]
    )
time_metadata = TimeMetadata(
    fs=fs,
    chans=chans,
    n_samples=n_samples,
    first_time=first_time,
    last_time=last_time,
    chans_metadata=chans_metadata,
)
time_metadata.summary()
time_metadata.write(time_data_path / "metadata.json")

```

```

{
  'file_info': None,
  'fs': 0.2,
  'chans': ['Hx', 'Hy', 'Hz', 'Ex', 'Ey'],
  'n_chans': 5,
  'n_samples': 707753,
  'first_time': '2003-10-17 15:30:00.000000_000000_000000_000000',

```

(continues on next page)

(continued from previous page)

```

'last_time': '2003-11-27 14:29:20.000000_000000_000000_000000',
'system': '',
'serial': '',
'wgs84_latitude': -999.0,
'wgs84_longitude': -999.0,
'easting': -999.0,
'northing': -999.0,
'elevation': -999.0,
'chans_metadata': {
  'Hx': {
    'name': 'Hx',
    'data_files': ['kap130as.npy'],
    'chan_type': 'magnetic',
    'chan_source': None,
    'sensor': '',
    'serial': '',
    'gain1': 1,
    'gain2': 1,
    'scaling': 1,
    'chopper': False,
    'dipole_dist': 1,
    'sensor_calibration_file': '',
    'instrument_calibration_file': ''
  },
  'Hy': {
    'name': 'Hy',
    'data_files': ['kap130as.npy'],
    'chan_type': 'magnetic',
    'chan_source': None,
    'sensor': '',
    'serial': '',
    'gain1': 1,
    'gain2': 1,
    'scaling': 1,
    'chopper': False,
    'dipole_dist': 1,
    'sensor_calibration_file': '',
    'instrument_calibration_file': ''
  },
  'Hz': {
    'name': 'Hz',
    'data_files': ['kap130as.npy'],
    'chan_type': 'magnetic',
    'chan_source': None,
    'sensor': '',
    'serial': '',
    'gain1': 1,
    'gain2': 1,
    'scaling': 1,
    'chopper': False,
    'dipole_dist': 1,
    'sensor_calibration_file': '',

```

(continues on next page)

(continued from previous page)

```

        'instrument_calibration_file': ''
    },
    'Ex': {
        'name': 'Ex',
        'data_files': ['kap130as.npy'],
        'chan_type': 'electric',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1,
        'gain2': 1,
        'scaling': 1,
        'chopper': False,
        'dipole_dist': 1,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Ey': {
        'name': 'Ey',
        'data_files': ['kap130as.npy'],
        'chan_type': 'electric',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1,
        'gain2': 1,
        'scaling': 1,
        'chopper': False,
        'dipole_dist': 1,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    }
},
'history': {'records': []}
}

```

Read the numpy formatted time data using the appropriate time data reader.

```

time_data = TimeReaderNumpy().run(time_data_path)
time_data.metadata.summary()

```

```

{
    'file_info': {
        'created_on_local': '2023-05-12T14:40:14.108330',
        'created_on_utc': '2023-05-12T14:40:14.108335',
        'version': '1.0.0a3'
    },
    'fs': 0.2,
    'chans': ['Hx', 'Hy', 'Hz', 'Ex', 'Ey'],
    'n_chans': 5,
    'n_samples': 707753,
    'first_time': '2003-10-17 15:30:00.000000_000000_000000_000000',

```

(continues on next page)

(continued from previous page)

```

'last_time': '2003-11-27 14:29:20.000000_000000_000000_000000',
'system': '',
'serial': '',
'wgs84_latitude': -999.0,
'wgs84_longitude': -999.0,
'easting': -999.0,
'northing': -999.0,
'elevation': -999.0,
'chans_metadata': {
  'Hx': {
    'name': 'Hx',
    'data_files': ['kap130as.npy'],
    'chan_type': 'magnetic',
    'chan_source': None,
    'sensor': '',
    'serial': '',
    'gain1': 1.0,
    'gain2': 1.0,
    'scaling': 1.0,
    'chopper': False,
    'dipole_dist': 1.0,
    'sensor_calibration_file': '',
    'instrument_calibration_file': ''
  },
  'Hy': {
    'name': 'Hy',
    'data_files': ['kap130as.npy'],
    'chan_type': 'magnetic',
    'chan_source': None,
    'sensor': '',
    'serial': '',
    'gain1': 1.0,
    'gain2': 1.0,
    'scaling': 1.0,
    'chopper': False,
    'dipole_dist': 1.0,
    'sensor_calibration_file': '',
    'instrument_calibration_file': ''
  },
  'Hz': {
    'name': 'Hz',
    'data_files': ['kap130as.npy'],
    'chan_type': 'magnetic',
    'chan_source': None,
    'sensor': '',
    'serial': '',
    'gain1': 1.0,
    'gain2': 1.0,
    'scaling': 1.0,
    'chopper': False,
    'dipole_dist': 1.0,
    'sensor_calibration_file': '',

```

(continues on next page)

(continued from previous page)

```

        'instrument_calibration_file': ''
    },
    'Ex': {
        'name': 'Ex',
        'data_files': ['kap130as.npy'],
        'chan_type': 'electric',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Ey': {
        'name': 'Ey',
        'data_files': ['kap130as.npy'],
        'chan_type': 'electric',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    }
},
'history': {
    'records': [
        {
            'time_local': '2023-05-12T14:40:14.113421',
            'time_utc': '2023-05-12T14:40:14.113419',
            'creator': {
                'name': 'TimeReaderNumpy',
                'apply_scalings': True,
                'extension': '.npy'
            },
            'messages': [
                'Reading raw data from ../../data/time/binary',
                'Sampling frequency 0.2 Hz',
                'From sample, time: 0, 2003-10-17 15:30:00',
                'To sample, time: 707752, 2003-11-27 14:29:20'
            ],
            'record_type': 'process'
        }
    ]
}

```

(continues on next page)

(continued from previous page)

```
}
}
```

Next remove any NaN values and plot the data. By default, the data is downsampled using lttb so that it is possible to plot the full timeseries. A second plot will be added with the same data filtered with a  $(1/(24*3600))$  Hz or 1 day period low pass filter.

```
time_data = InterpolateNans().run(time_data)
fig = time_data.plot(max_pts=1_000, legend="original")
filtered_data = LowPass(cutoff=1 / (24 * 3_600)).run(time_data)
fig = filtered_data.plot(
    max_pts=1_000, fig=fig, chans=chans, legend="filtered", color="red"
)
fig.update_layout(height=700)
plotly.io.show(fig)
```

**Total running time of the script:** ( 0 minutes 2.822 seconds)

## Calibration data JSON

The preferred format for calibration data is JSON file. However, they are not always as easy to handwrite, so it is possible to use txt/ASCII calibration files too.

```
from pathlib import Path
import json
from resistics.time import ChanMetadata
from resistics.calibrate import SensorCalibrationJSON
import plotly
```

Define the calibration data path. This is dependent on where the data is stored.

```
cal_data_path = Path("../", "..", "data", "calibration", "example.json")
```

Inspect the contents of the calibration file

```
with cal_data_path.open("r") as f:
    file_contents = json.load(f)
print(json.dumps(file_contents, indent=4, sort_keys=True))
```

```
{
  "file_info": {
    "created_on_local": "2021-07-04T17:20:47.042892",
    "created_on_utc": "2021-07-04T16:20:47.042892",
    "version": "1.0.0a3"
  },
  "file_path": "calibration_ascii\\example.txt",
  "frequency": [
    0.00011,
    0.0011,
    0.011,
    0.021,
```

(continues on next page)



(continued from previous page)

0.03177,  
0.048062,  
0.072711,  
0.11,  
0.13249,  
0.15959,  
0.19222,  
0.23153,  
0.27888,  
0.3359,  
0.40459,  
0.48733,  
0.58698,  
0.70702,  
0.8516,  
1.0257,  
1.2355,  
1.4881,  
1.7925,  
2.159,  
2.6005,  
3.1323,  
3.7728,  
4.5443,  
5.4736,  
6.5929,  
7.9411,  
9.5649,  
11.521,  
13.877,  
16.715,  
20.132,  
24.249,  
29.208,  
35.181,  
42.375,  
51.041,  
61.478,  
74.05,  
89.192,  
107.43,  
129.4,  
155.86,  
187.73,  
226.12,  
272.36,  
328.06,  
395.14,  
475.95,  
573.28,  
690.5,  
831.71,

(continues on next page)

(continued from previous page)

```
1001.8
],
"magnitude": [
  0.01,
  0.1,
  1.0,
  1.903,
  2.903,
  4.339,
  6.565,
  9.935,
  12.02,
  14.2,
  17.24,
  20.82,
  24.53,
  29.38,
  34.21,
  40.3,
  47.34,
  53.8,
  61.1,
  68.05,
  75.0,
  80.45,
  85.4,
  89.25,
  92.2,
  94.4,
  96.2,
  97.3,
  98.1,
  98.65,
  99.05,
  99.35,
  99.75,
  99.75,
  99.8,
  99.95,
  99.95,
  99.95,
  100.0,
  100.0,
  100.2,
  100.0,
  100.0,
  100.0,
  99.8,
  99.8,
  99.7,
  99.6,
  99.3,
```

(continues on next page)

(continued from previous page)

```

98.8,
98.0,
96.0,
92.7,
87.55,
80.8,
74.5,
70.7
],
"magnitude_unit": "mV/nT",
"n_samples": 57,
"phase": [
1.5707963267948966,
1.5707963267948966,
1.5533430342749532,
1.546065011294137,
1.5428361521779475,
1.526971109277319,
1.505398839722669,
1.4724295701524963,
1.4491817845159316,
1.4238046971919343,
1.402913106045562,
1.3795780539463978,
1.3431181258722362,
1.2771446801468507,
1.2277693156079312,
1.1700861838295185,
1.0909355022515757,
1.0088177609452424,
0.9242216521010773,
0.827041719350033,
0.7294952674560699,
0.6388428661074844,
0.5498136209632537,
0.46968555500419407,
0.3926641751136843,
0.32766811376941546,
0.270246781378802,
0.21961477977844648,
0.17517869702267086,
0.13625436404469332,
0.10112263153129945,
0.06969099703213358,
0.04107981460419053,
0.013366778609323771,
-0.01522921945412692,
-0.04212177616763115,
-0.07138396640656808,
-0.10302329508672128,
-0.1383801750736224,
-0.1780235837034216,

```

(continues on next page)

(continued from previous page)

```

-0.21912608758788807,
-0.2792875869041326,
-0.3439869422755624,
-0.42004839107747527,
-0.5115036438819781,
-0.6197664173831864,
-0.7506312046977213,
-0.9091245540713263,
-1.1008838789879434,
-1.3337282544965068,
-1.616262153809349,
-1.9645426060448175,
-2.384294291149454,
-2.8906143071530086,
2.784672821556953,
2.030865117620602,
0.8973959414979245
],
"sensor": "lemi120",
"serial": 710,
"static_gain": 1.0
}

```

Read the data using the appropriate calibration data reader. As calibration data can be dependent on certain sensor parameters, channel metadata needs to be passed to the method.

```

chan_metadata = ChanMetadata(name="Hx", chan_type="magnetic", data_files=[])
cal_data = SensorCalibrationJSON().read_calibration_data(cal_data_path, chan_metadata)

```

Plot the calibration data.

```

fig = cal_data.plot(color="maroon")
fig.update_layout(height=700)
plotly.io.show(fig)

```

**Total running time of the script:** ( 0 minutes 0.312 seconds)

## Calibration data TXT

An alternative to JSON calibration files is to use text/ASCII calibration files.

```

from pathlib import Path
from resistics.time import ChanMetadata
from resistics.calibrate import SensorCalibrationTXT
import plotly

```

Define the calibration data path. This is dependent on where the data is stored.

```
cal_data_path = Path("../", "..", "data", "calibration", "example.txt")
```

Inspect the contents of the calibration file

```

with cal_data_path.open("r") as f:
    for line_number, line in enumerate(f):
        print(line.strip("\n"))

```

```

Serial = 710
Sensor = LEMI120
Static gain = 1
Magnitude unit = mV/nT
Phase unit = degrees
Chopper = False

CALIBRATION DATA
1.1000E-4      1.000E-2      9.0000E1
1.1000E-3      1.000E-1      9.0000E1
1.1000E-2      1.000E0 8.9000E1
2.1000E-2      1.903E0 8.8583E1
3.1770E-2      2.903E0 8.8398E1
4.8062E-2      4.339E0 8.7489E1
7.2711E-2      6.565E0 8.6253E1
1.1000E-1      9.935E0 8.4364E1
1.3249E-1      1.202E1 8.3032E1
1.5959E-1      1.420E1 8.1578E1
1.9222E-1      1.724E1 8.0381E1
2.3153E-1      2.082E1 7.9044E1
2.7888E-1      2.453E1 7.6955E1
3.3590E-1      2.938E1 7.3175E1
4.0459E-1      3.421E1 7.0346E1
4.8733E-1      4.030E1 6.7041E1
5.8698E-1      4.734E1 6.2506E1
7.0702E-1      5.380E1 5.7801E1
8.5160E-1      6.110E1 5.2954E1
1.0257E0      6.805E1 4.7386E1
1.2355E0      7.500E1 4.1797E1
1.4881E0      8.045E1 3.6603E1
1.7925E0      8.540E1 3.1502E1
2.1590E0      8.925E1 2.6911E1
2.6005E0      9.220E1 2.2498E1
3.1323E0      9.440E1 1.8774E1
3.7728E0      9.620E1 1.5484E1
4.5443E0      9.730E1 1.2583E1
5.4736E0      9.810E1 1.0037E1
6.5929E0      9.865E1 7.8068E0
7.9411E0      9.905E1 5.7939E0
9.5649E0      9.935E1 3.9930E0
1.1521E1      9.975E1 2.3537E0
1.3877E1      9.975E1 7.6586E-1
1.6715E1      9.980E1 -8.7257E-1
2.0132E1      9.995E1 -2.4134E0
2.4249E1      9.995E1 -4.0900E0
2.9208E1      9.995E1 -5.9028E0
3.5181E1      1.000E2 -7.9286E0
4.2375E1      1.000E2 -1.0200E1

```

(continues on next page)

(continued from previous page)

5.1041E1	1.002E2	-1.2555E1
6.1478E1	1.000E2	-1.6002E1
7.4050E1	1.000E2	-1.9709E1
8.9192E1	1.000E2	-2.4067E1
1.0743E2	9.980E1	-2.9307E1
1.2940E2	9.980E1	-3.5510E1
1.5586E2	9.970E1	-4.3008E1
1.8773E2	9.960E1	-5.2089E1
2.2612E2	9.930E1	-6.3076E1
2.7236E2	9.880E1	-7.6417E1
3.2806E2	9.800E1	-9.2605E1
3.9514E2	9.600E1	-1.1256E2
4.7595E2	9.270E1	-1.3661E2
5.7328E2	8.755E1	-1.6562E2
6.9050E2	8.080E1	1.5955E2
8.3171E2	7.450E1	1.1636E2
1.0018E3	7.070E1	5.1417E1

Read the data using the appropriate calibration data reader. As calibration data can be dependent on certain sensor parameters, channel metadata needs to be passed to the method.

```
chan_metadata = ChanMetadata(name="Hx", chan_type="magnetic", data_files=[])
cal_data = SensorCalibrationTXT().read_calibration_data(cal_data_path, chan_metadata)
```

Plot the calibration data.

```
fig = cal_data.plot(color="green")
fig.update_layout(height=700)
plotly.io.show(fig)
```

**Total running time of the script:** ( 0 minutes 0.282 seconds)

## Quick functions

When doing fieldwork, it's often useful to quickly assess data before dismantling a site setup. The quick functions are there to provide fast viewing and processing of data without having to set many parameters.

## Reading time data

Resistics can quickly read a single continuous recording using the quick reading functionality. This can be useful for inspecting the metadata and having a look at the data when in the field.

The dataset in this example has been provided for use by the SAMTEX consortium. For more information, please refer to [Jones2009]. Additional details about the dataset can be found at <https://www.mtnet.info/data/kap03/kap03.html>.

```
from pathlib import Path
import seedir as sd
import resistics.letsgo as letsgo
import plotly
```

Define the data path. This is dependent on where the data is stored.

```
time_data_path = Path("../", "..", "data", "time", "quick", "kap123")
sd.seedir(str(time_data_path), style="emoji")
```

```
kap123/
├ metadata.json
└ data.npy
```

Quickly read the time series data and inspect the metadata

```
time_data = letsgo.quick_read(time_data_path)
time_data.metadata.summary()
```

```
{
  'file_info': {
    'created_on_local': '2021-07-07T22:25:45.320529',
    'created_on_utc': '2021-07-07T21:25:45.320529',
    'version': '1.0.0a0'
  },
  'fs': 0.2,
  'chans': ['Hx', 'Hy', 'Hz', 'Ex', 'Ey'],
  'n_chans': 5,
  'n_samples': 361512,
  'first_time': '2003-11-10 15:00:00.000000_000000_000000_000000',
  'last_time': '2003-12-01 13:05:55.000000_000000_000000_000000',
  'system': '',
  'serial': '',
  'wgs84_latitude': -999.0,
  'wgs84_longitude': -999.0,
  'easting': -999.0,
  'northing': -999.0,
  'elevation': -999.0,
  'chans_metadata': {
    'Hx': {
      'name': 'Hx',
      'data_files': ['data.npy'],
      'chan_type': 'magnetic',
      'chan_source': None,
      'sensor': '',
      'serial': '',
      'gain1': 1.0,
      'gain2': 1.0,
      'scaling': 1.0,
      'chopper': False,
      'dipole_dist': 1.0,
      'sensor_calibration_file': '',
      'instrument_calibration_file': ''
    },
    'Hy': {
      'name': 'Hy',
      'data_files': ['data.npy'],
      'chan_type': 'magnetic',
      'chan_source': None,
```

(continues on next page)

(continued from previous page)

```

        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Hz': {
        'name': 'Hz',
        'data_files': ['data.npy'],
        'chan_type': 'magnetic',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Ex': {
        'name': 'Ex',
        'data_files': ['data.npy'],
        'chan_type': 'electric',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Ey': {
        'name': 'Ey',
        'data_files': ['data.npy'],
        'chan_type': 'electric',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,

```

(continues on next page)



(continued from previous page)

```

        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    }
},
'history': {
    'records': [
        {
            'time_local': '2023-05-12T14:40:18.311903',
            'time_utc': '2023-05-12T14:40:18.311902',
            'creator': {
                'name': 'TimeReaderNumpy',
                'apply_scalings': True,
                'extension': '.npy'
            },
            'messages': [
                'Reading raw data from ../../data/time/quick/kap123',
                'Sampling frequency 0.2 Hz',
                'From sample, time: 0, 2003-11-10 15:00:00',
                'To sample, time: 361511, 2003-12-01 13:05:55'
            ],
            'record_type': 'process'
        }
    ]
}
}

```

Take a subsection of the data and inspect the metadata for the subsection

```

time_data_sub = time_data.subsection("2003-11-20 12:00:00", "2003-11-21 00:00:00")
time_data_sub.metadata.summary()

```

```

{
    'file_info': {
        'created_on_local': '2021-07-07T22:25:45.320529',
        'created_on_utc': '2021-07-07T21:25:45.320529',
        'version': '1.0.0a0'
    },
    'fs': 0.2,
    'chans': ['Hx', 'Hy', 'Hz', 'Ex', 'Ey'],
    'n_chans': 5,
    'n_samples': 8641,
    'first_time': '2003-11-20 12:00:00.000000_000000_000000_000000',
    'last_time': '2003-11-21 00:00:00.000000_000000_000000_000000',
    'system': '',
    'serial': '',
    'wgs84_latitude': -999.0,
    'wgs84_longitude': -999.0,
    'easting': -999.0,
    'northing': -999.0,
    'elevation': -999.0,
    'chans_metadata': {
        'Hx': {

```

(continues on next page)

(continued from previous page)

```

        'name': 'Hx',
        'data_files': ['data.npy'],
        'chan_type': 'magnetic',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Hy': {
        'name': 'Hy',
        'data_files': ['data.npy'],
        'chan_type': 'magnetic',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Hz': {
        'name': 'Hz',
        'data_files': ['data.npy'],
        'chan_type': 'magnetic',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Ex': {
        'name': 'Ex',
        'data_files': ['data.npy'],
        'chan_type': 'electric',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,

```

(continues on next page)

(continued from previous page)

```

    'gain2': 1.0,
    'scaling': 1.0,
    'chopper': False,
    'dipole_dist': 1.0,
    'sensor_calibration_file': '',
    'instrument_calibration_file': ''
  },
  'Ey': {
    'name': 'Ey',
    'data_files': ['data.npy'],
    'chan_type': 'electric',
    'chan_source': None,
    'sensor': '',
    'serial': '',
    'gain1': 1.0,
    'gain2': 1.0,
    'scaling': 1.0,
    'chopper': False,
    'dipole_dist': 1.0,
    'sensor_calibration_file': '',
    'instrument_calibration_file': ''
  }
},
'history': {
  'records': [
    {
      'time_local': '2023-05-12T14:40:18.311903',
      'time_utc': '2023-05-12T14:40:18.311902',
      'creator': {
        'name': 'TimeReaderNumpy',
        'apply_scalings': True,
        'extension': '.npy'
      },
      'messages': [
        'Reading raw data from ../../data/time/quick/kap123',
        'Sampling frequency 0.2 Hz',
        'From sample, time: 0, 2003-11-10 15:00:00',
        'To sample, time: 361511, 2003-12-01 13:05:55'
      ],
      'record_type': 'process'
    },
    {
      'time_local': '2023-05-12T14:40:18.334664',
      'time_utc': '2023-05-12T14:40:18.334662',
      'creator': {
        'name': 'Subsection',
        'from_time': '2003-11-20 12:00:00',
        'to_time': '2003-11-21 00:00:00'
      },
      'messages': [
        'Subsection from sample 170640 to 179280',
        'First time: 2003-11-10 15:00:00 -> 2003-11-20 12:00:00',

```

(continues on next page)

(continued from previous page)

```

        'Last time: 2003-12-01 13:05:55 -> 2003-11-21 00:00:00'
    ],
    'record_type': 'process'
}
]
}
}

```

Plot the full time data with LTTB downsampling and a subsection without any downsampling. Comparing the downsampled and original data, there is clearly some loss but the LTTB downsampled data does a reasonable job capturing the main features whilst showing a greater amount of data.

```

fig = time_data.plot(max_pts=1_000)
fig = time_data_sub.plot(
    fig, chans=time_data.metadata.chans, color="red", legend="Subsection", max_pts=None
)
fig.update_layout(height=700)
plotly.io.show(fig)

```

**Total running time of the script:** ( 0 minutes 7.279 seconds)

## Viewing time data

With the quick viewing functionality, it is possible to view time series data without having to setup a project or explicitly read the data first. The quickview decimation option provides an easy way to see the time series at multiple sampling frequencies (decimated to lower frequencies).

**Warning:** The time series data is downsampled for viewing using the LTTB algorithm, which tries to capture the features of the time series using a given number of data points. Setting `max_pts` to `None` will try and plot all points which can cause serious performance issues for large datasets.

Those looking to view non downsampled data are advised to use the quick reading functionality and then plot specific subsections of data.

The dataset in this example has been provided for use by the SAMTEX consortium. For more information, please refer to [Jones2009]. Additional details about the dataset can be found at <https://www.mtnet.info/data/kap03/kap03.html>.

```

from pathlib import Path
import seedir as sd
import resisticks.letsgo as letsgo
import plotly

```

Define the data path. This is dependent on where the data is stored.

```

time_data_path = Path(".", "..", "data", "time", "quick", "kap123")
sd.seedir(str(time_data_path), style="emoji")

```

```

kap123/
├─ metadata.json
└─ data.npy

```

Quickly view the time series data

```
fig = letsgo.quick_view(time_data_path, max_pts=1_000)
fig.update_layout(height=700)
plotly.io.show(fig)
```

In many cases, data plotting at its recording frequency can be quite noisy. The quickview function has the option to plot multiple decimation levels so the data can be compared at multiple sampling frequencies.

```
fig = letsgo.quick_view(time_data_path, max_pts=1_000, decimate=True)
fig.update_layout(height=700)
plotly.io.show(fig)
```

**Total running time of the script:** ( 0 minutes 5.801 seconds)

## Getting spectra data

It can often be useful to have a look at the spectral content of time data. The quick functions make it easy to get the spectra data of a single time series recording.

Note that spectra data are calculated after decimation and spectra data objects include data for multiple decimation levels.

The dataset in this example has been provided for use by the SAMTEX consortium. For more information, please refer to [Jones2009]. Additional details about the dataset can be found at <https://www.mtnet.info/data/kap03/kap03.html>.

```
from pathlib import Path
import seedir as sd
import resisticks.letsgo as letsgo
import plotly
```

Define the data path. This is dependent on where the data is stored.

```
time_data_path = Path("../", "..", "data", "time", "quick", "kap123")
sd.seedir(str(time_data_path), style="emoji")
```

```
kap123/
├─ metadata.json
└─ data.npy
```

Get the spectra data.

```
spec_data = letsgo.quick_spectra(time_data_path)
```

Once the spectra data has been calculated, it can be plotted in a variety of ways. The default plotting function plots the spectral data for multiple decimation levels.

```
fig = spec_data.plot()
fig.update_layout(height=900)
plotly.io.show(fig)
```

It is also possible to plot spectra data for a particular decimation level. In the below example, an optional grouping is being used to stack spectra data for the decimation level into certain time groups

```
fig = spec_data.plot_level_stack(level=0, grouping="3D")
fig.update_layout(height=900)
plotly.io.show(fig)
```

It is also possible to plot spectra heatmaps for a decimation level. Here, the `sphinx_gallery_defer_figures`

```
fig = spec_data.plot_level_section(level=0, grouping="6H")
fig.update_layout(height=900)
plotly.io.show(fig)
```

**Total running time of the script:** ( 0 minutes 4.145 seconds)

## Transfer functions

When doing field work, it can be useful to quickly estimate the transfer function from a single continuous recording. This example shows estimation of the transfer function using all default settings. The default transfer function is the impedance tensor and this will be calculated. Later, the data will be re-processed using an alternative configuration.

The dataset in this example has been provided for use by the SAMTEX consortium. For more information, please refer to [Jones2009]. Additional details about the dataset can be found at <https://www.mtnet.info/data/kap03/kap03.html>.

```
from pathlib import Path
import seedir as sd
import resisticks.letsgo as letsgo
import plotly
```

Define the data path. This is dependent on where the data is stored.

```
time_data_path = Path("../", "..", "data", "time", "quick", "kap123")
sd.seedir(str(time_data_path), style="emoji")
```

```
kap123/
├ metadata.json
└ data.npy
```

Now calculate the transfer function, in this case the impedance tensor

```
soln = letsgo.quick_tf(time_data_path)
fig = soln.tf.plot(
    soln.freqs,
    soln.components,
    to_plot=["ExHy", "EyHx"],
    x_lim=[1, 5],
    res_lim=[0, 4],
    legend="128",
    symbol="circle",
)
fig.update_layout(height=900)
plotly.io.show(fig)
```

```
0%|          | 0/20 [00:00<?, ?it/s]
10%|#         | 2/20 [00:00<00:01, 17.17it/s]
```

(continues on next page)

(continued from previous page)

```

25%|##5      | 5/20 [00:00<00:00, 23.36it/s]
100%|#####| 20/20 [00:00<00:00, 72.20it/s]

0%|          | 0/20 [00:00<?, ?it/s]
5%|5         | 1/20 [00:01<00:23, 1.24s/it]
10%|#        | 2/20 [00:02<00:22, 1.24s/it]
15%|#5       | 3/20 [00:03<00:21, 1.24s/it]
20%|##       | 4/20 [00:04<00:19, 1.24s/it]
25%|##5      | 5/20 [00:06<00:18, 1.24s/it]
30%|###      | 6/20 [00:06<00:13, 1.06it/s]
35%|###5     | 7/20 [00:06<00:09, 1.34it/s]
40%|####     | 8/20 [00:07<00:07, 1.62it/s]
45%|####5    | 9/20 [00:07<00:05, 1.89it/s]
50%|#####   | 10/20 [00:07<00:04, 2.13it/s]
55%|#####5  | 11/20 [00:08<00:03, 2.70it/s]
60%|#####   | 12/20 [00:08<00:02, 3.32it/s]
65%|#####5  | 13/20 [00:08<00:01, 3.94it/s]
70%|#####   | 14/20 [00:08<00:01, 4.54it/s]
75%|#####5  | 15/20 [00:08<00:00, 5.05it/s]
80%|#####   | 16/20 [00:08<00:00, 5.72it/s]
85%|#####5  | 17/20 [00:08<00:00, 6.31it/s]
90%|#####   | 18/20 [00:09<00:00, 6.80it/s]
95%|#####5  | 19/20 [00:09<00:00, 7.22it/s]
100%|#####  | 20/20 [00:09<00:00, 7.53it/s]
100%|#####  | 20/20 [00:09<00:00, 2.16it/s]

```

**Total running time of the script:** ( 0 minutes 10.362 seconds)

## Using projects

Projects in resistics are the best way to deal with multiple recordings and sites. They enable the following functionality:

- Multiple recordings at the same sampling frequency can be used to calculate transfer functions
- Processing which combines data from different sites and requires alignment of windows
- Calculation of statistics and deeper analysis of recordings
- Use of multiple configurations (useful for experimentation or mixed instrument surveys)

The use of projects is highly recommended when dealing with more than one or two sites.

## Making a project

The quick reading functionality of resistics focuses on analysis of single continuous recordings. When there are multiple recordings at a site or multiple sites, it can be more convenient to use a resistics project. This is generally easier to manage and use, especially when doing remote reference or intersite processing.

The data in this example has been provided for use by the SAMTEX consortium. For more information, please refer to [Jones2009]. Additional details about the data can be found at <https://www.mtnet.info/data/kap03/kap03.html>.

```

from pathlib import Path
import seidir as sd

```

(continues on next page)

(continued from previous page)

```
import shutil
import resistics.letsgo as letsgo
import plotly
```

Define the path where the project will be created and any extra project metadata. The only required piece of metadata is the reference time but there are other optional fields.

```
project_path = Path("../", "..", "data", "project", "kap03")
project_info = {
    "ref_time": "2003-10-15 00:00:00",
    "year": 2003,
    "country": "South Africa",
}
```

Create the new project and look at the directory structure. There are no data files in the project yet, so there is not much to see.

```
letsgo.new(project_path, project_info)
sd.seedir(str(project_path), style="emoji")
```

```
kap03/
├── spectra/
├── images/
├── resistics.json
├── masks/
├── results/
├── calibrate/
├── evals/
├── features/
└── time/
```

Load the project and have a look. When loading a project, a resistics environment is returned. This is a combination of a resistics project and a configuration.

```
resenv = letsgo.load(project_path)
resenv.proj.summary()
```

```
{
  'dir_path': '.././data/project/kap03',
  'begin_time': '2023-05-12 14:40:46.102000_000000_000000_000000',
  'end_time': '2023-05-12 14:40:46.102002_000000_000000_000000',
  'metadata': {
    'file_info': {
      'created_on_local': '2023-05-12T14:40:46.099101',
      'created_on_utc': '2023-05-12T14:40:46.099105',
      'version': '1.0.0a3'
    },
    'ref_time': '2003-10-15 00:00:00.000000_000000_000000_000000',
    'location': '',
    'country': 'South Africa',
    'year': 2003,
    'description': '',
  },
}
```

(continues on next page)



(continued from previous page)

```

    'contributors': []
},
'sites': {}
}

```

Now let's copy some time series data into the project and look at the directory structure. Copy the data does not have to be done using Python and users can simply copy and paste the time series data into the time folder

```

copy_from = Path("../", "../", "data", "time", "kap03")
for site in copy_from.glob("*"):
    shutil.copytree(site, project_path / "time" / site.stem)
sd.seedir(str(project_path), style="emoji")

```

```

kap03/
├── spectra/
├── images/
├── resistics.json
├── masks/
├── results/
├── calibrate/
├── evals/
├── features/
├── time/
│   ├── kap172/
│   │   └── meas01/
│   │       ├── metadata.json
│   │       └── data.npy
│   ├── kap163/
│   │   └── meas01/
│   │       ├── metadata.json
│   │       └── data.npy
│   └── kap160/
│       └── meas01/
│           ├── metadata.json
│           └── data.npy

```

Reload the project and print a new summary.

```

resenv = letsgo.reload(resenv)
resenv.proj.summary()

```

```

{
  'dir_path': '../data/project/kap03',
  'begin_time': '2003-10-28 10:00:00.000000_000000_000000_000000',
  'end_time': '2003-11-24 15:31:55.000000_000000_000000_000000',
  'metadata': {
    'file_info': {
      'created_on_local': '2023-05-12T14:40:46.099101',
      'created_on_utc': '2023-05-12T14:40:46.099105',
      'version': '1.0.0a3'
    }
  },
}

```

(continues on next page)

(continued from previous page)

```

    'ref_time': '2003-10-15 00:00:00.000000_000000_000000_000000',
    'location': '',
    'country': 'South Africa',
    'year': 2003,
    'description': '',
    'contributors': []
},
'sites': {
    'kap172': {
        'dir_path': '../data/project/kap03/time/kap172',
        'measurements': {
            'meas01': {
                'site_name': 'kap172',
                'dir_path': '../data/project/kap03/time/kap172/meas01',
                'metadata': {
                    'file_info': {
                        'created_on_local': '2021-07-07T22:27:00.395145',
                        'created_on_utc': '2021-07-07T21:27:00.395145',
                        'version': '1.0.0a0'
                    },
                    'fs': 0.2,
                    'chans': ['Hx', 'Hy', 'Hz', 'Ex', 'Ey'],
                    'n_chans': 5,
                    'n_samples': 414498,
                    'first_time': '2003-10-30 13:00:00.000000_000000_000000_000000',
                    'last_time': '2003-11-23 12:41:25.000000_000000_000000_000000',
                    'system': '',
                    'serial': '',
                    'wgs84_latitude': -999.0,
                    'wgs84_longitude': -999.0,
                    'easting': -999.0,
                    'northing': -999.0,
                    'elevation': -999.0,
                    'chans_metadata': {
                        'Hx': {
                            'name': 'Hx',
                            'data_files': ['data.npy'],
                            'chan_type': 'magnetic',
                            'chan_source': None,
                            'sensor': '',
                            'serial': '',
                            'gain1': 1.0,
                            'gain2': 1.0,
                            'scaling': 1.0,
                            'chopper': False,
                            'dipole_dist': 1.0,
                            'sensor_calibration_file': '',
                            'instrument_calibration_file': ''
                        },
                        'Hy': {
                            'name': 'Hy',
                            'data_files': ['data.npy'],

```

(continues on next page)

(continued from previous page)

```

        'chan_type': 'magnetic',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Hz': {
        'name': 'Hz',
        'data_files': ['data.npy'],
        'chan_type': 'magnetic',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Ex': {
        'name': 'Ex',
        'data_files': ['data.npy'],
        'chan_type': 'electric',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Ey': {
        'name': 'Ey',
        'data_files': ['data.npy'],
        'chan_type': 'electric',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,

```

(continues on next page)

(continued from previous page)

```

        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    },
    'history': {'records': []}
},
'reader': {
    'name': 'TimeReaderNumpy',
    'apply_scalings': True,
    'extension': '.npy'
}
},
},
'begin_time': '2003-10-30 13:00:00.000000_000000_000000_000000',
'end_time': '2003-11-23 12:41:25.000000_000000_000000_000000'
},
'kap163': {
    'dir_path': '../data/project/kap03/time/kap163',
    'measurements': {
        'meas01': {
            'site_name': 'kap163',
            'dir_path': '../data/project/kap03/time/kap163/meas01',
            'metadata': {
                'file_info': {
                    'created_on_local': '2021-07-07T22:26:52.975361',
                    'created_on_utc': '2021-07-07T21:26:52.975361',
                    'version': '1.0.0a0'
                },
            },
            'fs': 0.2,
            'chans': ['Hx', 'Hy', 'Hz', 'Ex', 'Ey'],
            'n_chans': 5,
            'n_samples': 463807,
            'first_time': '2003-10-28 15:30:00.000000_000000_000000_000000',
            'last_time': '2003-11-24 11:40:30.000000_000000_000000_000000',
            'system': '',
            'serial': '',
            'wgs84_latitude': -999.0,
            'wgs84_longitude': -999.0,
            'easting': -999.0,
            'northing': -999.0,
            'elevation': -999.0,
            'chans_metadata': {
                'Hx': {
                    'name': 'Hx',
                    'data_files': ['data.npy'],
                    'chan_type': 'magnetic',
                    'chan_source': None,
                    'sensor': '',
                    'serial': '',
                    'gain1': 1.0,

```

(continues on next page)

(continued from previous page)

```

        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Hy': {
        'name': 'Hy',
        'data_files': ['data.npy'],
        'chan_type': 'magnetic',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Hz': {
        'name': 'Hz',
        'data_files': ['data.npy'],
        'chan_type': 'magnetic',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Ex': {
        'name': 'Ex',
        'data_files': ['data.npy'],
        'chan_type': 'electric',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },

```

(continues on next page)

(continued from previous page)

```

        'Ey': {
            'name': 'Ey',
            'data_files': ['data.npy'],
            'chan_type': 'electric',
            'chan_source': None,
            'sensor': '',
            'serial': '',
            'gain1': 1.0,
            'gain2': 1.0,
            'scaling': 1.0,
            'chopper': False,
            'dipole_dist': 1.0,
            'sensor_calibration_file': '',
            'instrument_calibration_file': ''
        },
        'history': {'records': []}
    },
    'reader': {
        'name': 'TimeReaderNumpy',
        'apply_scalings': True,
        'extension': '.npy'
    }
},
'begin_time': '2003-10-28 15:30:00.000000_000000_000000_000000',
'end_time': '2003-11-24 11:40:30.000000_000000_000000_000000',
},
'kap160': {
    'dir_path': '../data/project/kap03/time/kap160',
    'measurements': {
        'meas01': {
            'site_name': 'kap160',
            'dir_path': '../data/project/kap03/time/kap160/meas01',
            'metadata': {
                'file_info': {
                    'created_on_local': '2021-07-07T22:26:48.851498',
                    'created_on_utc': '2021-07-07T21:26:48.851498',
                    'version': '1.0.0a0'
                },
            },
            'fs': 0.2,
            'chans': ['Hx', 'Hy', 'Hz', 'Ex', 'Ey'],
            'n_chans': 5,
            'n_samples': 470544,
            'first_time': '2003-10-28 10:00:00.000000_000000_000000_000000',
            'last_time': '2003-11-24 15:31:55.000000_000000_000000_000000',
            'system': '',
            'serial': '',
            'wgs84_latitude': -999.0,
            'wgs84_longitude': -999.0,
            'easting': -999.0,
            'northing': -999.0,

```

(continues on next page)

(continued from previous page)

```

'elevation': -999.0,
'chans_metadata': {
  'Hx': {
    'name': 'Hx',
    'data_files': ['data.npy'],
    'chan_type': 'magnetic',
    'chan_source': None,
    'sensor': '',
    'serial': '',
    'gain1': 1.0,
    'gain2': 1.0,
    'scaling': 1.0,
    'chopper': False,
    'dipole_dist': 1.0,
    'sensor_calibration_file': '',
    'instrument_calibration_file': ''
  },
  'Hy': {
    'name': 'Hy',
    'data_files': ['data.npy'],
    'chan_type': 'magnetic',
    'chan_source': None,
    'sensor': '',
    'serial': '',
    'gain1': 1.0,
    'gain2': 1.0,
    'scaling': 1.0,
    'chopper': False,
    'dipole_dist': 1.0,
    'sensor_calibration_file': '',
    'instrument_calibration_file': ''
  },
  'Hz': {
    'name': 'Hz',
    'data_files': ['data.npy'],
    'chan_type': 'magnetic',
    'chan_source': None,
    'sensor': '',
    'serial': '',
    'gain1': 1.0,
    'gain2': 1.0,
    'scaling': 1.0,
    'chopper': False,
    'dipole_dist': 1.0,
    'sensor_calibration_file': '',
    'instrument_calibration_file': ''
  },
  'Ex': {
    'name': 'Ex',
    'data_files': ['data.npy'],
    'chan_type': 'electric',
    'chan_source': None,

```

(continues on next page)

(continued from previous page)

```

        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Ey': {
        'name': 'Ey',
        'data_files': ['data.npy'],
        'chan_type': 'electric',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    }
},
'history': {'records': []}
},
'reader': {
    'name': 'TimeReaderNumpy',
    'apply_scalings': True,
    'extension': '.npy'
}
},
'begin_time': '2003-10-28 10:00:00.000000_000000_000000_000000',
'end_time': '2003-11-24 15:31:55.000000_000000_000000_000000'
}
}

```

Finally, plot the project timeline.

```

fig = resenv.proj.plot()
fig.update_layout(height=700)
plotly.io.show(fig)

```

**Total running time of the script:** ( 0 minutes 0.453 seconds)



## Navigating a project

After creating a project and copying in the time data into the time folder, it is useful to be able to navigate a project. This example shows the various types of objects available in resisticks that can help navigate a project and access data.

The data in this example has been provided for use by the SAMTEX consortium. For more information, please refer to [Jones2009]. Additional details about the data can be found at <https://www.mtnet.info/data/kap03/kap03.html>.

```
from pathlib import Path
import seedir as sd
import resisticks.letsgo as letsgo
import plotly
```

Let's remind ourselves of the project contents, load the project and have a look at its contents.

```
project_path = Path("../", "../", "data", "project", "kap03")
sd.seedir(str(project_path), style="emoji")
resenv = letsgo.load(project_path)
```

```
kap03/
├── spectra/
├── images/
├── resisticks.json
├── masks/
├── results/
├── calibrate/
├── evals/
├── features/
├── time/
│   ├── kap172/
│   │   └── meas01/
│   │       ├── metadata.json
│   │       └── data.npy
│   ├── kap163/
│   │   └── meas01/
│   │       ├── metadata.json
│   │       └── data.npy
│   └── kap160/
│       └── meas01/
│           ├── metadata.json
│           └── data.npy
```

Project summaries can be quite verbose. Instead, let's convert it to a pandas DataFrame and see the information in tabular form.

```
print(resenv.proj.to_dataframe())
```

	name	fs	first_time	last_time	site
0	meas01	0.2	2003-10-30 13:00:00	2003-11-23 12:41:25	kap172
1	meas01	0.2	2003-10-28 15:30:00	2003-11-24 11:40:30	kap163
2	meas01	0.2	2003-10-28 10:00:00	2003-11-24 15:31:55	kap160

The project has three sites, each with a single recording. Another way to look at the sites in the project is to make a list of them.

```
sites = [site.name for site in resenv.proj]
print(sites)
```

```
['kap172', 'kap163', 'kap160']
```

To get more information about a single site, get the corresponding Site object.

```
site = resenv.proj["kap160"]
print(type(site))
```

```
<class 'resistics.project.Site'>
```

Like most objects in resistics, the Site object has a summary method, which prints out a comprehensive summary of the site.

```
site.summary()
```

```
{
  'dir_path': '../data/project/kap03/time/kap160',
  'measurements': {
    'meas01': {
      'site_name': 'kap160',
      'dir_path': '../data/project/kap03/time/kap160/meas01',
      'metadata': {
        'file_info': {
          'created_on_local': '2021-07-07T22:26:48.851498',
          'created_on_utc': '2021-07-07T21:26:48.851498',
          'version': '1.0.0a0'
        },
        'fs': 0.2,
        'chans': ['Hx', 'Hy', 'Hz', 'Ex', 'Ey'],
        'n_chans': 5,
        'n_samples': 470544,
        'first_time': '2003-10-28 10:00:00.000000_000000_000000_000000',
        'last_time': '2003-11-24 15:31:55.000000_000000_000000_000000',
        'system': '',
        'serial': '',
        'wgs84_latitude': -999.0,
        'wgs84_longitude': -999.0,
        'easting': -999.0,
        'northing': -999.0,
        'elevation': -999.0,
        'chans_metadata': {
          'Hx': {
            'name': 'Hx',
            'data_files': ['data.npy'],
            'chan_type': 'magnetic',
            'chan_source': None,
            'sensor': '',
            'serial': '',
            'gain1': 1.0,
            'gain2': 1.0,

```

(continues on next page)

(continued from previous page)

```

        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Hy': {
        'name': 'Hy',
        'data_files': ['data.npy'],
        'chan_type': 'magnetic',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Hz': {
        'name': 'Hz',
        'data_files': ['data.npy'],
        'chan_type': 'magnetic',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Ex': {
        'name': 'Ex',
        'data_files': ['data.npy'],
        'chan_type': 'electric',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Ey': {

```

(continues on next page)

(continued from previous page)

```

        'name': 'Ey',
        'data_files': ['data.npy'],
        'chan_type': 'electric',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'history': {'records': []}
},
'reader': {
    'name': 'TimeReaderNumpy',
    'apply_scalings': True,
    'extension': '.npy'
}
},
'begin_time': '2003-10-28 10:00:00.000000_000000_000000_000000',
'end_time': '2003-11-24 15:31:55.000000_000000_000000_000000'
}

```

Sometimes, it can be more convenient to access the information from the Site object directly.

```

print(site.name)
print(site.begin_time)
print(site.end_time)
measurements = [meas.name for meas in site]
print(measurements)

```

```

kap160
2003-10-28 10:00:00
2003-11-24 15:31:55
['meas01']

```

It's also possible to plot the timeline of a single site.

```

fig = site.plot()
plotly.io.show(fig)

```

There is only a single measurement in this site named “meas01”. Let's get its Measurement object.

```

meas = site["meas01"]
print(type(meas))

```

```
<class 'resistics.project.Measurement'>
```

Unsurprisingly, Measurement objects also have a summary method.

```
meas.summary()
```

```
{
  'site_name': 'kap160',
  'dir_path': '../data/project/kap03/time/kap160/meas01',
  'metadata': {
    'file_info': {
      'created_on_local': '2021-07-07T22:26:48.851498',
      'created_on_utc': '2021-07-07T21:26:48.851498',
      'version': '1.0.0a0'
    },
    'fs': 0.2,
    'chans': ['Hx', 'Hy', 'Hz', 'Ex', 'Ey'],
    'n_chans': 5,
    'n_samples': 470544,
    'first_time': '2003-10-28 10:00:00.000000_000000_000000_000000',
    'last_time': '2003-11-24 15:31:55.000000_000000_000000_000000',
    'system': '',
    'serial': '',
    'wgs84_latitude': -999.0,
    'wgs84_longitude': -999.0,
    'easting': -999.0,
    'northing': -999.0,
    'elevation': -999.0,
    'chans_metadata': {
      'Hx': {
        'name': 'Hx',
        'data_files': ['data.npy'],
        'chan_type': 'magnetic',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
      },
      'Hy': {
        'name': 'Hy',
        'data_files': ['data.npy'],
        'chan_type': 'magnetic',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
```

(continues on next page)

(continued from previous page)

```

        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Hz': {
        'name': 'Hz',
        'data_files': ['data.npy'],
        'chan_type': 'magnetic',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Ex': {
        'name': 'Ex',
        'data_files': ['data.npy'],
        'chan_type': 'electric',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Ey': {
        'name': 'Ey',
        'data_files': ['data.npy'],
        'chan_type': 'electric',
        'chan_source': None,
        'sensor': '',
        'serial': '',
        'gain1': 1.0,
        'gain2': 1.0,
        'scaling': 1.0,
        'chopper': False,
        'dipole_dist': 1.0,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    }
}

```

(continues on next page)

(continued from previous page)

```

    },
    'history': {'records': []}
  },
  'reader': {
    'name': 'TimeReaderNumpy',
    'apply_scalings': True,
    'extension': '.npy'
  }
}

```

Measurement objects only hold metadata to avoid loading in lots of data when projects are loaded. However, it is possible to read the data from the measurement.

```

time_data = meas.reader.run(meas.dir_path, metadata=meas.metadata)
time_data.summary()

```

```

##---Begin Summary-----
<class 'resistics.time.TimeData'>
file_info:
  created_on_local: '2021-07-07T22:26:48.851498'
  created_on_utc: '2021-07-07T21:26:48.851498'
  version: 1.0.0a0
fs: 0.2
chans:
- Hx
- Hy
- Hz
- Ex
- Ey
n_chans: 5
n_samples: 470544
first_time: 2003-10-28 10:00:00.000000_000000_000000_000000
last_time: 2003-11-24 15:31:55.000000_000000_000000_000000
system: ''
serial: ''
wgs84_latitude: -999.0
wgs84_longitude: -999.0
easting: -999.0
northing: -999.0
elevation: -999.0
chans_metadata:
  Hx:
    name: Hx
    data_files:
    - data.npy
    chan_type: magnetic
    chan_source: null
    sensor: ''
    serial: ''
    gain1: 1.0
    gain2: 1.0
    scaling: 1.0

```

(continues on next page)

(continued from previous page)

```
chopper: false
dipole_dist: 1.0
sensor_calibration_file: ''
instrument_calibration_file: ''
Hy:
  name: Hy
  data_files:
  - data.npy
  chan_type: magnetic
  chan_source: null
  sensor: ''
  serial: ''
  gain1: 1.0
  gain2: 1.0
  scaling: 1.0
  chopper: false
  dipole_dist: 1.0
  sensor_calibration_file: ''
  instrument_calibration_file: ''
Hz:
  name: Hz
  data_files:
  - data.npy
  chan_type: magnetic
  chan_source: null
  sensor: ''
  serial: ''
  gain1: 1.0
  gain2: 1.0
  scaling: 1.0
  chopper: false
  dipole_dist: 1.0
  sensor_calibration_file: ''
  instrument_calibration_file: ''
Ex:
  name: Ex
  data_files:
  - data.npy
  chan_type: electric
  chan_source: null
  sensor: ''
  serial: ''
  gain1: 1.0
  gain2: 1.0
  scaling: 1.0
  chopper: false
  dipole_dist: 1.0
  sensor_calibration_file: ''
  instrument_calibration_file: ''
Ey:
  name: Ey
  data_files:
```

(continues on next page)



(continued from previous page)

```

- data.npy
chan_type: electric
chan_source: null
sensor: ''
serial: ''
gain1: 1.0
gain2: 1.0
scaling: 1.0
chopper: false
dipole_dist: 1.0
sensor_calibration_file: ''
instrument_calibration_file: ''
history:
  records:
  - time_local: '2023-05-12T14:40:46.976075'
    time_utc: '2023-05-12T14:40:46.976074'
    creator:
      name: TimeReaderNumpy
      apply_scalings: true
      extension: .npy
    messages:
    - Reading raw data from ../../data/project/kap03/time/kap160/meas01
    - Sampling frequency 0.2 Hz
    - 'From sample, time: 0, 2003-10-28 10:00:00'
    - 'To sample, time: 470543, 2003-11-24 15:31:55'
    record_type: process

##---End summary-----

```

Let's plot the time data.

```

fig = time_data.plot()
fig.update_layout(height=700)
plotly.io.show(fig)

```

**Total running time of the script:** ( 0 minutes 7.512 seconds)

## Processing a project

The quick reading functionality of resisticks focuses on analysis of single continuous recordings. When there are multiple recordings at a site or multiple sites, it can be more convenient to use a resisticks project. This is generally easier to manage and use, especially when doing remote reference or intersite processing.

The data in this example has been provided for use by the SAMTEX consortium. For more information, please refer to [Jones2009]. Additional details about the data can be found at <https://www.mtnet.info/data/kap03/kap03.html>.

```

from pathlib import Path
import seedir as sd
import resisticks.lets go as lets go
import plotly

```

Let's remind ourselves of the project contents and then load the project.

```
project_path = Path("../", "../", "data", "project", "kap03")
sd.seedir(str(project_path), style="emoji")
resenv = letsgo.load(project_path)
```

```
kap03/
├─ spectra/
├─ images/
├─ resistics.json
├─ masks/
├─ results/
├─ calibrate/
├─ evals/
├─ features/
├─ time/
│   └─ kap172/
│       └─ meas01/
│           ├── metadata.json
│           └─ data.npy
│   └─ kap163/
│       └─ meas01/
│           ├── metadata.json
│           └─ data.npy
│   └─ kap160/
│       └─ meas01/
│           ├── metadata.json
│           └─ data.npy
```

Inspect the current configuration. As no custom configuration has been specified, this will be the default configuration.

```
resenv.config.summary()
```

```
{
  'name': 'default',
  'time_readers': [
    {
      'name': 'TimeReaderAscii',
      'apply_scalings': True,
      'extension': '.txt',
      'delimiter': None,
      'n_header': 0
    },
    {
      'name': 'TimeReaderNumpy',
      'apply_scalings': True,
      'extension': '.npy'
    }
  ],
  'time_processors': [
    {'name': 'InterpolateNans'},
    {'name': 'RemoveMean'}
  ],
  'dec_setup': {
```

(continues on next page)

(continued from previous page)

```

    'name': 'DecimationSetup',
    'n_levels': 8,
    'per_level': 5,
    'min_samples': 256,
    'div_factor': 2,
    'eval_freqs': None
},
'decimator': {
    'name': 'Decimator',
    'resample': True,
    'max_single_factor': 3
},
'win_setup': {
    'name': 'WindowSetup',
    'min_size': 128,
    'min_olap': 32,
    'win_factor': 4,
    'olap_proportion': 0.25,
    'min_n_wins': 5,
    'win_sizes': None,
    'olap_sizes': None
},
>windower': {'name': 'Windower'},
'fourier': {
    'name': 'FourierTransform',
    'win_fnc': ['kaiser', 14],
    'detrend': 'linear',
    'workers': -2
},
'spectra_processors': [],
'evals': {'name': 'EvaluationFreqs'},
'sensor_calibrator': {
    'name': 'SensorCalibrator',
    'chans': None,
    'readers': [
        {
            'name': 'SensorCalibrationJSON',
            'extension': '.json',
            'file_str': 'IC_$sensor$extension'
        }
    ]
},
'tf': {
    'name': 'ImpedanceTensor',
    'variation': 'default',
    'out_chans': ['Ex', 'Ey'],
    'in_chans': ['Hx', 'Hy'],
    'cross_chans': ['Hx', 'Hy'],
    'n_out': 2,
    'n_in': 2,
    'n_cross': 2
},

```

(continues on next page)

(continued from previous page)

```

'regression_preparer': {'name': 'RegressionPreparerGathered'},
'solver': {
    'name': 'SolverScikitTheilSen',
    'fit_intercept': False,
    'normalize': False,
    'n_jobs': -2,
    'max_subpopulation': 2000,
    'n_subsamples': None
}
}

```

And it's always useful to know what transfer function will be calculated out.

```
print(resenv.config.tf)
```

```

| Ex | = | Ex_Hx Ex_Hy | | Hx |
| Ey |   | Ey_Hx Ey_Hy | | Hy |

```

Now let's run single site processing on a site and then look at the directory structure again. Begin by transforming to frequency domain and reducing to the evaluation frequencies. Note that whilst there is only a single measurement for this site, the below is written to work when there are more measurements.

```

site = resenv.proj["kap160"]
for meas in site:
    letsgo.process_time_to_evals(resenv, "kap160", meas.name)
sd.seedir(str(project_path), style="emoji")

```

```

kap03/
├─ spectra/
├─ images/
├─ resistics.json
├─ masks/
├─ results/
├─ calibrate/
├─ evals/
├─ kap160/
│   └─ default/
│       └─ meas01/
│           ├── data.npz
│           └─ metadata.json
├─ features/
├─ time/
│   ├── kap172/
│   │   └─ meas01/
│   │       ├── metadata.json
│   │       └─ data.npy
│   ├── kap163/
│   │   └─ meas01/
│   │       ├── metadata.json
│   │       └─ data.npy
│   └─ kap160/

```

(continues on next page)

(continued from previous page)

```
└─ meas01/
   └─ metadata.json
   └─ data.npy
```

Now let's run single site processing on a site and then look at the directory structure again. To run the transfer function calculation, the sampling frequency to process needs to be specified. In this case, it's 0.2 Hz.

```
letsgo.process_evals_to_tf(resenv, 0.2, "kap160")
sd.seedir(str(project_path), style="emoji")
```

```
0%|          | 0/20 [00:00<?, ?it/s]
15%|#5       | 3/20 [00:00<00:00, 22.72it/s]
30%|###      | 6/20 [00:00<00:00, 26.34it/s]
100%|#####  | 20/20 [00:00<00:00, 69.56it/s]
```

```
0%|          | 0/20 [00:00<?, ?it/s]
5%|5         | 1/20 [00:01<00:30, 1.63s/it]
10%|#        | 2/20 [00:03<00:29, 1.62s/it]
15%|#5       | 3/20 [00:04<00:27, 1.62s/it]
20%|##       | 4/20 [00:06<00:25, 1.62s/it]
25%|##5      | 5/20 [00:08<00:24, 1.65s/it]
30%|###      | 6/20 [00:08<00:17, 1.25s/it]
35%|###5     | 7/20 [00:09<00:13, 1.00s/it]
40%|####     | 8/20 [00:09<00:10, 1.19it/s]
45%|####5    | 9/20 [00:10<00:08, 1.37it/s]
50%|#####   | 10/20 [00:10<00:06, 1.52it/s]
55%|#####5  | 11/20 [00:10<00:04, 1.99it/s]
60%|#####  | 12/20 [00:10<00:03, 2.52it/s]
65%|#####5  | 13/20 [00:11<00:02, 3.09it/s]
70%|#####  | 14/20 [00:11<00:01, 3.67it/s]
75%|#####5  | 15/20 [00:11<00:01, 4.24it/s]
80%|#####  | 16/20 [00:11<00:00, 4.95it/s]
85%|#####5  | 17/20 [00:11<00:00, 5.61it/s]
90%|#####  | 18/20 [00:11<00:00, 6.17it/s]
95%|#####5  | 19/20 [00:11<00:00, 6.66it/s]
100%|#####  | 20/20 [00:12<00:00, 7.04it/s]
100%|#####  | 20/20 [00:12<00:00, 1.66it/s]
```

```
kap03/
└─ spectra/
└─ images/
└─ resistics.json
└─ masks/
└─ results/
   └─ kap160/
      └─ default/
         └─ 0_2000000_impedancetensor_default.json
└─ calibrate/
└─ evals/
   └─ kap160/
      └─ default/
         └─ meas01/
            └─ data.npz
```

(continues on next page)

(continued from previous page)

```

├── metadata.json
├── features/
├── time/
│   ├── kap172/
│   │   ├── meas01/
│   │   │   ├── metadata.json
│   │   │   └── data.npy
│   ├── kap163/
│   │   ├── meas01/
│   │   │   ├── metadata.json
│   │   │   └── data.npy
│   └── kap160/
│       ├── meas01/
│       │   ├── metadata.json
│       │   └── data.npy

```

Get the transfer function

```

soln = letsgo.get_solution(
    resenv,
    "kap160",
    resenv.config.name,
    0.2,
    resenv.config.tf.name,
    resenv.config.tf.variation,
)
fig = soln.tf.plot(
    soln.freqs,
    soln.components,
    to_plot=["ExHy", "EyHx"],
    x_lim=[1, 5],
    res_lim=[1, 4],
    legend="128",
    symbol="circle",
)
fig.update_layout(height=900)
plotly.io.show(fig)

```

**Total running time of the script:** ( 0 minutes 13.387 seconds)

## Calibration files

So far, none of our project examples use calibration files. Let's look at how calibration files can be used in the processing sequence.

**Warning:** I need to find an appropriate example where calibration files are required and that can be shared online. If anyone can provide some data that can be openly shared, please get in touch.

Searching for an appropriate example

```
print("Get in touch if you have one")
```

```
Get in touch if you have one
```

**Total running time of the script:** ( 0 minutes 0.001 seconds)

### Remote reference

**Warning:** Remote reference processing does not seem to be working yet. I need to get to the bottom of it.

There's a bug in this soup

```
print("Not working properly yet, watch this space")
```

```
Not working properly yet, watch this space
```

**Total running time of the script:** ( 0 minutes 0.001 seconds)

### Intersite processing

**Warning:** Intersite processing does not seem to be working yet. I need to get to the bottom of it.

There's a bug in this soup

```
print("Not working properly yet, watch this space")
```

```
Not working properly yet, watch this space
```

**Total running time of the script:** ( 0 minutes 0.001 seconds)

### Remote and intersite

**Warning:** Remote reference and intersite processing does not seem to be working yet. I need to get to the bottom of it.

There's a bug in this soup

```
print("Not working properly yet, watch this space")
```

```
Not working properly yet, watch this space
```

**Total running time of the script:** ( 0 minutes 0.001 seconds)

## Configuration

There will be times when users need to customise their processing sequences. This can be achieved using resistics configuration files.

The resistics configuration files allow users to:

- Specify processing parameters
- Save processing sequences for use later on

## Default configuration

This example shows the default resistics configuration. The configuration defines the processing sequence and parameterisation that will be used to process the data.

```
from resistics.config import get_default_configuration
```

Get the default configuration and print the summary.

```
default_config = get_default_configuration()
default_config.summary()
```

```
{
  'name': 'default',
  'time_readers': [
    {
      'name': 'TimeReaderAscii',
      'apply_scalings': True,
      'extension': '.txt',
      'delimiter': None,
      'n_header': 0
    },
    {
      'name': 'TimeReaderNumpy',
      'apply_scalings': True,
      'extension': '.npy'
    }
  ],
  'time_processors': [
    {'name': 'InterpolateNans'},
    {'name': 'RemoveMean'}
  ],
  'dec_setup': {
    'name': 'DecimationSetup',
    'n_levels': 8,
    'per_level': 5,
    'min_samples': 256,
    'div_factor': 2,
    'eval_freqs': None
  },
  'decimator': {
    'name': 'Decimator',
```

(continues on next page)



(continued from previous page)

```

        'resample': True,
        'max_single_factor': 3
    },
    'win_setup': {
        'name': 'WindowSetup',
        'min_size': 128,
        'min_olap': 32,
        'win_factor': 4,
        'olap_proportion': 0.25,
        'min_n_wins': 5,
        'win_sizes': None,
        'olap_sizes': None
    },
    'windower': {'name': 'Windower'},
    'fourier': {
        'name': 'FourierTransform',
        'win_fnc': ['kaiser', 14],
        'detrend': 'linear',
        'workers': -2
    },
    'spectra_processors': [],
    'evals': {'name': 'EvaluationFreqs'},
    'sensor_calibrator': {
        'name': 'SensorCalibrator',
        'chans': None,
        'readers': [
            {
                'name': 'SensorCalibrationJSON',
                'extension': '.json',
                'file_str': 'IC_$sensor$extension'
            }
        ]
    },
    'tf': {
        'name': 'ImpedanceTensor',
        'variation': 'default',
        'out_chans': ['Ex', 'Ey'],
        'in_chans': ['Hx', 'Hy'],
        'cross_chans': ['Hx', 'Hy'],
        'n_out': 2,
        'n_in': 2,
        'n_cross': 2
    },
    'regression_preparer': {'name': 'RegressionPreparerGathered'},
    'solver': {
        'name': 'SolverScikitTheilSen',
        'fit_intercept': False,
        'normalize': False,
        'n_jobs': -2,
        'max_subpopulation': 2000,
        'n_subsamples': None
    }
}

```

(continues on next page)

(continued from previous page)

}

By default, the configuration includes two time data readers. These will be used to try and read any data. Each has parameters that can be altered depending on the type of data. More time readers for particular data formats are available in the `resistics-readers` package.

```
for time_reader in default_config.time_readers:
    time_reader.summary()
```

```
{
    'name': 'TimeReaderAscii',
    'apply_scalings': True,
    'extension': '.txt',
    'delimiter': None,
    'n_header': 0
}
{
    'name': 'TimeReaderNumpy',
    'apply_scalings': True,
    'extension': '.npy'
}
```

The default transfer function is the magnetotelluric impedance tensor. It can be printed out to help show the relationship.

```
default_config.tf.summary()
print(default_config.tf)
```

```
{
    'name': 'ImpedanceTensor',
    'variation': 'default',
    'out_chans': ['Ex', 'Ey'],
    'in_chans': ['Hx', 'Hy'],
    'cross_chans': ['Hx', 'Hy'],
    'n_out': 2,
    'n_in': 2,
    'n_cross': 2
}
| Ex | = | Ex_Hx Ex_Hy | | Hx |
| Ey |   | Ey_Hx Ey_Hy | | Hy |
```

Other important parameters include those related to decimation setup and windowing setup.

```
default_config.win_setup.summary()
default_config.dec_setup.summary()
```

```
{
    'name': 'WindowSetup',
    'min_size': 128,
    'min_olap': 32,
    'win_factor': 4,
    'olap_proportion': 0.25,
```

(continues on next page)

(continued from previous page)

```

    'min_n_wins': 5,
    'win_sizes': None,
    'olap_sizes': None
}
{
    'name': 'DecimationSetup',
    'n_levels': 8,
    'per_level': 5,
    'min_samples': 256,
    'div_factor': 2,
    'eval_freqs': None
}

```

**Total running time of the script:** ( 0 minutes 0.024 seconds)

### Custom configuration

It is possible to customise the configuration and save it for use later. Configurations can either be customised at initialisation or after initialisation.

Configurations can be saved as JSON files and later reloaded. This allows users to keep a library of configurations that can be used depending on the use case or the survey.

```

from pathlib import Path
from resistics.config import Configuration
from resistics.time import Add
from resistics.transfunc import TransferFunction

```

Creating a new configuration requires only a name. In this instance, default parameters will be used for everything else.

```

custom_config = Configuration(name="example")
custom_config.summary()

```

```

{
    'name': 'example',
    'time_readers': [
        {
            'name': 'TimeReaderAscii',
            'apply_scalings': True,
            'extension': '.txt',
            'delimiter': None,
            'n_header': 0
        },
        {
            'name': 'TimeReaderNumpy',
            'apply_scalings': True,
            'extension': '.npz'
        }
    ],
    'time_processors': [
        {'name': 'InterpolateNans'},
    ]
}

```

(continues on next page)

(continued from previous page)

```

        {'name': 'RemoveMean'}
    ],
    'dec_setup': {
        'name': 'DecimationSetup',
        'n_levels': 8,
        'per_level': 5,
        'min_samples': 256,
        'div_factor': 2,
        'eval_freqs': None
    },
    'decimator': {
        'name': 'Decimator',
        'resample': True,
        'max_single_factor': 3
    },
    'win_setup': {
        'name': 'WindowSetup',
        'min_size': 128,
        'min_olap': 32,
        'win_factor': 4,
        'olap_proportion': 0.25,
        'min_n_wins': 5,
        'win_sizes': None,
        'olap_sizes': None
    },
    'windower': {'name': 'Windower'},
    'fourier': {
        'name': 'FourierTransform',
        'win_fnc': ['kaiser', 14],
        'detrend': 'linear',
        'workers': -2
    },
    'spectra_processors': [],
    'evals': {'name': 'EvaluationFreqs'},
    'sensor_calibrator': {
        'name': 'SensorCalibrator',
        'chans': None,
        'readers': [
            {
                'name': 'SensorCalibrationJSON',
                'extension': '.json',
                'file_str': 'IC_$sensor$extension'
            }
        ]
    },
    'tf': {
        'name': 'ImpedanceTensor',
        'variation': 'default',
        'out_chans': ['Ex', 'Ey'],
        'in_chans': ['Hx', 'Hy'],
        'cross_chans': ['Hx', 'Hy'],
        'n_out': 2,

```

(continues on next page)

(continued from previous page)

```

        'n_in': 2,
        'n_cross': 2
    },
    'regression_preparer': {'name': 'RegressionPreparerGathered'},
    'solver': {
        'name': 'SolverScikitTheilSen',
        'fit_intercept': False,
        'normalize': False,
        'n_jobs': -2,
        'max_subpopulation': 2000,
        'n_subsamples': None
    }
}

```

However, it is possible to customise more at initialisation time.

```

custom_config = Configuration(
    name="example",
    time_processors=[Add(add=5)],
    tf=TransferFunction(in_chans=["A", "B"], out_chans=["M", "N"]),
)
custom_config.summary()

```

```

{
    'name': 'example',
    'time_readers': [
        {
            'name': 'TimeReaderAscii',
            'apply_scalings': True,
            'extension': '.txt',
            'delimiter': None,
            'n_header': 0
        },
        {
            'name': 'TimeReaderNumpy',
            'apply_scalings': True,
            'extension': '.npy'
        }
    ],
    'time_processors': [{'name': 'Add', 'add': 5.0}],
    'dec_setup': {
        'name': 'DecimationSetup',
        'n_levels': 8,
        'per_level': 5,
        'min_samples': 256,
        'div_factor': 2,
        'eval_freqs': None
    },
    'decimator': {
        'name': 'Decimator',
        'resample': True,
        'max_single_factor': 3
    }
}

```

(continues on next page)

(continued from previous page)

```

},
'win_setup': {
    'name': 'WindowSetup',
    'min_size': 128,
    'min_olap': 32,
    'win_factor': 4,
    'olap_proportion': 0.25,
    'min_n_wins': 5,
    'win_sizes': None,
    'olap_sizes': None
},
>windower': {'name': 'Windower'},
'fourier': {
    'name': 'FourierTransform',
    'win_fnc': ['kaiser', 14],
    'detrend': 'linear',
    'workers': -2
},
'spectra_processors': [],
'evals': {'name': 'EvaluationFreqs'},
'sensor_calibrator': {
    'name': 'SensorCalibrator',
    'chans': None,
    'readers': [
        {
            'name': 'SensorCalibrationJSON',
            'extension': '.json',
            'file_str': 'IC_$sensor$extension'
        }
    ]
},
'tf': {
    'name': 'TransferFunction',
    'variation': 'generic',
    'out_chans': ['M', 'N'],
    'in_chans': ['A', 'B'],
    'cross_chans': ['A', 'B'],
    'n_out': 2,
    'n_in': 2,
    'n_cross': 2
},
'regression_preparer': {'name': 'RegressionPreparerGathered'},
'solver': {
    'name': 'SolverScikitTheilSen',
    'fit_intercept': False,
    'normalize': False,
    'n_jobs': -2,
    'max_subpopulation': 2000,
    'n_subsamples': None
}
}

```

A configuration can be updated after it has been initialised. For example, let's update a windowing parameter. First,

have a look at the summary of the windowing parameters. Then they can be updated and the summary can be inspected again.

```
custom_config.win_setup.summary()
custom_config.win_setup.min_size = 512
custom_config.win_setup.summary()
```

```
{
  'name': 'WindowSetup',
  'min_size': 128,
  'min_olap': 32,
  'win_factor': 4,
  'olap_proportion': 0.25,
  'min_n_wins': 5,
  'win_sizes': None,
  'olap_sizes': None
}
{
  'name': 'WindowSetup',
  'min_size': 512,
  'min_olap': 32,
  'win_factor': 4,
  'olap_proportion': 0.25,
  'min_n_wins': 5,
  'win_sizes': None,
  'olap_sizes': None
}
```

Configuration information can be saved to JSON files.

```
save_path = Path("../", "..", "data", "config", "custom_config.json")
with save_path.open("w") as f:
    f.write(custom_config.json())
```

Configurations can also be loaded from JSON files.

```
reloaded_config = Configuration.parse_file(save_path)
reloaded_config.summary()
```

```
{
  'name': 'example',
  'time_readers': [
    {
      'name': 'TimeReaderAscii',
      'apply_scalings': True,
      'extension': '.txt',
      'delimiter': None,
      'n_header': 0
    },
    {
      'name': 'TimeReaderNumpy',
      'apply_scalings': True,
      'extension': '.npz'
    }
  ]
}
```

(continues on next page)

(continued from previous page)

```

    }
  ],
  'time_processors': [{'name': 'Add', 'add': 5.0}],
  'dec_setup': {
    'name': 'DecimationSetup',
    'n_levels': 8,
    'per_level': 5,
    'min_samples': 256,
    'div_factor': 2,
    'eval_freqs': None
  },
  'decimator': {
    'name': 'Decimator',
    'resample': True,
    'max_single_factor': 3
  },
  'win_setup': {
    'name': 'WindowSetup',
    'min_size': 512,
    'min_olap': 32,
    'win_factor': 4,
    'olap_proportion': 0.25,
    'min_n_wins': 5,
    'win_sizes': None,
    'olap_sizes': None
  },
  'windower': {'name': 'Windower'},
  'fourier': {
    'name': 'FourierTransform',
    'win_fnc': ['kaiser', 14.0],
    'detrend': 'linear',
    'workers': -2
  },
  'spectra_processors': [],
  'evals': {'name': 'EvaluationFreqs'},
  'sensor_calibrator': {
    'name': 'SensorCalibrator',
    'chans': None,
    'readers': [
      {
        'name': 'SensorCalibrationJSON',
        'extension': '.json',
        'file_str': 'IC_$sensor$extension'
      }
    ]
  },
  'tf': {
    'name': 'TransferFunction',
    'variation': 'generic',
    'out_chans': ['M', 'N'],
    'in_chans': ['A', 'B'],
    'cross_chans': ['A', 'B'],

```

(continues on next page)



(continued from previous page)

```

        'n_out': 2,
        'n_in': 2,
        'n_cross': 2
    },
    'regression_preparer': {'name': 'RegressionPreparerGathered'},
    'solver': {
        'name': 'SolverScikitTheilSen',
        'fit_intercept': False,
        'normalize': False,
        'n_jobs': -2,
        'max_subpopulation': 2000,
        'n_subsamples': None
    }
}

```

**Total running time of the script:** ( 0 minutes 0.049 seconds)

### Quick configuration

If no configuration is passed, the quick processing functions in resistics will use the default configuration. However, it is possible to use a different configuration if preferred.

The dataset in this example has been provided for use by the SAMTEX consortium. For more information, please refer to [Jones2009]. Additional details about the dataset can be found at <https://www.mtnet.info/data/kap03/kap03.html>.

```

from pathlib import Path
import seedir as sd
import resistics.letsgo as letsgo
from resistics.config import Configuration
from resistics.time import InterpolateNans, RemoveMean, Multiply
from resistics.decimate import DecimationSetup
from resistics.window import WindowerTarget
import plotly

```

Define the data path. This is dependent on where the data is stored.

```

time_data_path = Path("../", "..", "data", "time", "quick", "kap123")
sd.seedir(str(time_data_path), style="emoji")

```

```

kap123/
├─ metadata.json
└─ data.npy

```

Quick calculation of the transfer function using default parameters.

```

soln_default = letsgo.quick_tf(time_data_path)
fig = soln_default.tf.plot(
    soln_default.freqs,
    soln_default.components,
    to_plot=["ExHy", "EyHx"],
    x_lim=[1, 5],

```

(continues on next page)

(continued from previous page)

```

    res_lim=[0, 4],
    legend="Default config",
    symbol="circle",
)
fig.update_layout(height=800)
fig

```

```

0%|          | 0/20 [00:00<?, ?it/s]
10%|#         | 2/20 [00:00<00:01, 16.64it/s]
25%|##5       | 5/20 [00:00<00:00, 22.97it/s]
100%|#####| 20/20 [00:00<00:00, 70.90it/s]

0%|          | 0/20 [00:00<?, ?it/s]
5%|5         | 1/20 [00:01<00:23, 1.24s/it]
10%|#        | 2/20 [00:02<00:22, 1.24s/it]
15%|#5       | 3/20 [00:03<00:21, 1.25s/it]
20%|##       | 4/20 [00:04<00:19, 1.25s/it]
25%|##5      | 5/20 [00:06<00:18, 1.25s/it]
30%|###      | 6/20 [00:06<00:13, 1.06it/s]
35%|###5     | 7/20 [00:06<00:09, 1.34it/s]
40%|####     | 8/20 [00:07<00:07, 1.62it/s]
45%|####5    | 9/20 [00:07<00:05, 1.88it/s]
50%|#####   | 10/20 [00:07<00:04, 2.12it/s]
55%|#####5  | 11/20 [00:08<00:03, 2.68it/s]
60%|#####   | 12/20 [00:08<00:02, 3.30it/s]
65%|#####5  | 13/20 [00:08<00:01, 3.91it/s]
70%|#####   | 14/20 [00:08<00:01, 4.51it/s]
75%|#####5  | 15/20 [00:08<00:00, 5.05it/s]
80%|#####   | 16/20 [00:08<00:00, 5.73it/s]
85%|#####5  | 17/20 [00:08<00:00, 6.34it/s]
90%|#####   | 18/20 [00:09<00:00, 6.81it/s]
95%|#####5  | 19/20 [00:09<00:00, 7.26it/s]
100%|#####  | 20/20 [00:09<00:00, 7.56it/s]
100%|#####  | 20/20 [00:09<00:00, 2.16it/s]

```

Looking at the transfer function, it's clear that the phases are in the wrong quadrants. A new time process can be added to correct this by multiplying the electric channels by -1.

Further, let's use a different windower that will change the window size (subject to a minimum) to try and generate a target number of windows. The WindowTarget ignores the min\_size in the WindowSetup and uses its own. This alternative windower will be combined with a modified decimation setup.

```

config = Configuration(
    name="custom",
    time_processors=[
        InterpolateNans(),
        RemoveMean(),
        Multiply(multiplier={"Ex": -1, "Ey": -1}),
    ],
    dec_setup=DecimationSetup(n_levels=3, per_level=7),
    windower=WindowerTarget(target=2_000, min_size=180),
)

```

(continues on next page)

(continued from previous page)

config.summary()

```
{
  'name': 'custom',
  'time_readers': [
    {
      'name': 'TimeReaderAscii',
      'apply_scalings': True,
      'extension': '.txt',
      'delimiter': None,
      'n_header': 0
    },
    {
      'name': 'TimeReaderNumpy',
      'apply_scalings': True,
      'extension': '.npz'
    }
  ],
  'time_processors': [
    {'name': 'InterpolateNans'},
    {'name': 'RemoveMean'},
    {'name': 'Multiply', 'multiplier': {'Ex': -1.0, 'Ey': -1.0}}
  ],
  'dec_setup': {
    'name': 'DecimationSetup',
    'n_levels': 3,
    'per_level': 7,
    'min_samples': 256,
    'div_factor': 2,
    'eval_freqs': None
  },
  'decimator': {
    'name': 'Decimator',
    'resample': True,
    'max_single_factor': 3
  },
  'win_setup': {
    'name': 'WindowSetup',
    'min_size': 128,
    'min_olap': 32,
    'win_factor': 4,
    'olap_proportion': 0.25,
    'min_n_wins': 5,
    'win_sizes': None,
    'olap_sizes': None
  },
  'windower': {
    'name': 'WindowerTarget',
    'target': 2000,
    'min_size': 180,
    'olap_proportion': 0.25
  }
}
```

(continues on next page)

(continued from previous page)

```

    },
    'fourier': {
        'name': 'FourierTransform',
        'win_fnc': ['kaiser', 14],
        'detrend': 'linear',
        'workers': -2
    },
    'spectra_processors': [],
    'evals': {'name': 'EvaluationFreqs'},
    'sensor_calibrator': {
        'name': 'SensorCalibrator',
        'chans': None,
        'readers': [
            {
                'name': 'SensorCalibrationJSON',
                'extension': '.json',
                'file_str': 'IC_$sensor$extension'
            }
        ]
    },
    'tf': {
        'name': 'ImpedanceTensor',
        'variation': 'default',
        'out_chans': ['Ex', 'Ey'],
        'in_chans': ['Hx', 'Hy'],
        'cross_chans': ['Hx', 'Hy'],
        'n_out': 2,
        'n_in': 2,
        'n_cross': 2
    },
    'regression_preparer': {'name': 'RegressionPreparerGathered'},
    'solver': {
        'name': 'SolverScikitTheilSen',
        'fit_intercept': False,
        'normalize': False,
        'n_jobs': -2,
        'max_subpopulation': 2000,
        'n_subsamples': None
    }
}

```

Quick calculate the impedance tensor using the new custom configuration and plot the result.

```

soln_custom = letsgo.quick_tf(time_data_path, config)
fig = soln_custom.tf.plot(
    soln_custom.freqs,
    soln_custom.components,
    to_plot=["ExHy", "EyHx"],
    x_lim=[1, 5],
    res_lim=[0, 4],
    phs_lim=[0, 100],
    legend="Custom config",

```

(continues on next page)

(continued from previous page)

```

    symbol="diamond",
)
fig.update_layout(height=800)
plotly.io.show(fig)

```

```

0%|          | 0/21 [00:00<?, ?it/s]
14%|#4       | 3/21 [00:00<00:00, 29.07it/s]
86%|#####5 | 18/21 [00:00<00:00, 99.25it/s]
100%|#####| 21/21 [00:00<00:00, 102.77it/s]

0%|          | 0/21 [00:00<?, ?it/s]
5%| 4        | 1/21 [00:00<00:13, 1.46it/s]
10%| 9       | 2/21 [00:01<00:13, 1.45it/s]
14%|#4       | 3/21 [00:02<00:12, 1.45it/s]
19%|#9       | 4/21 [00:02<00:11, 1.46it/s]
24%|##3      | 5/21 [00:03<00:11, 1.45it/s]
29%|##8      | 6/21 [00:04<00:10, 1.45it/s]
33%|###3     | 7/21 [00:04<00:09, 1.45it/s]
38%|###8     | 8/21 [00:05<00:06, 1.87it/s]
43%|####2    | 9/21 [00:05<00:05, 2.33it/s]
48%|####7    | 10/21 [00:05<00:03, 2.78it/s]
52%|####2    | 11/21 [00:05<00:03, 3.21it/s]
57%|####7    | 12/21 [00:05<00:02, 3.61it/s]
62%|####1    | 13/21 [00:06<00:02, 3.93it/s]
67%|####6    | 14/21 [00:06<00:01, 4.20it/s]
71%|####1    | 15/21 [00:06<00:01, 4.95it/s]
76%|####6    | 16/21 [00:06<00:00, 5.67it/s]
81%|#####   | 17/21 [00:06<00:00, 6.30it/s]
86%|#####5  | 18/21 [00:06<00:00, 6.85it/s]
90%|#####   | 19/21 [00:06<00:00, 7.28it/s]
95%|#####5  | 20/21 [00:06<00:00, 7.64it/s]
100%|#####  | 21/21 [00:07<00:00, 7.92it/s]
100%|#####  | 21/21 [00:07<00:00, 2.98it/s]

```

**Total running time of the script:** ( 0 minutes 17.849 seconds)

## Project configuration

Alternative configurations can also be used with projects. When using custom configurations in the project environment, the name of the configuration is key as this will determine where any data is saved. The below example shows what happens when using different configurations with a project.

The dataset in this example has been provided for use by the SAMTEX consortium. For more information, please refer to [Jones2009]. Additional details about the dataset can be found at <https://www.mtnet.info/data/kap03/kap03.html>.

```

from pathlib import Path
import seadir as sd
from resistics.config import Configuration
import resistics.lets go as lets go
from resistics.time import TimeReaderNumpy, InterpolateNans, RemoveMean, Multiply
from resistics.decimate import DecimationSetup

```

(continues on next page)

(continued from previous page)

```

from resistics.window import WindowSetup
import plotly

# The first thing to do is define the configuration to use.
myconfig = letsgo.Configuration(
    name="myconfig",
    time_readers=[TimeReaderNumpy()],
    time_processors=[
        InterpolateNans(),
        RemoveMean(),
        Multiply(multiplier={"Ex": -1, "Ey": -1}),
    ],
    dec_setup=DecimationSetup(n_levels=7, per_level=3),
    win_setup=WindowSetup(min_size=64, min_olap=16),
)
myconfig.summary()

```

```

{
  'name': 'myconfig',
  'time_readers': [
    {
      'name': 'TimeReaderNumpy',
      'apply_scalings': True,
      'extension': '.npy'
    }
  ],
  'time_processors': [
    {'name': 'InterpolateNans'},
    {'name': 'RemoveMean'},
    {'name': 'Multiply', 'multiplier': {'Ex': -1.0, 'Ey': -1.0}}
  ],
  'dec_setup': {
    'name': 'DecimationSetup',
    'n_levels': 7,
    'per_level': 3,
    'min_samples': 256,
    'div_factor': 2,
    'eval_freqs': None
  },
  'decimator': {
    'name': 'Decimator',
    'resample': True,
    'max_single_factor': 3
  },
  'win_setup': {
    'name': 'WindowSetup',
    'min_size': 64,
    'min_olap': 16,
    'win_factor': 4,
    'olap_proportion': 0.25,
    'min_n_wins': 5,

```

(continues on next page)

(continued from previous page)

```

        'win_sizes': None,
        'olap_sizes': None
    },
    'windower': {'name': 'Windower'},
    'fourier': {
        'name': 'FourierTransform',
        'win_fnc': ['kaiser', 14],
        'detrend': 'linear',
        'workers': -2
    },
    'spectra_processors': [],
    'evals': {'name': 'EvaluationFreqs'},
    'sensor_calibrator': {
        'name': 'SensorCalibrator',
        'chans': None,
        'readers': [
            {
                'name': 'SensorCalibrationJSON',
                'extension': '.json',
                'file_str': 'IC_$sensor$extension'
            }
        ]
    },
    'tf': {
        'name': 'ImpedanceTensor',
        'variation': 'default',
        'out_chans': ['Ex', 'Ey'],
        'in_chans': ['Hx', 'Hy'],
        'cross_chans': ['Hx', 'Hy'],
        'n_out': 2,
        'n_in': 2,
        'n_cross': 2
    },
    'regression_preparer': {'name': 'RegressionPreparerGathered'},
    'solver': {
        'name': 'SolverScikitTheilSen',
        'fit_intercept': False,
        'normalize': False,
        'n_jobs': -2,
        'max_subpopulation': 2000,
        'n_subsamples': None
    }
}

```

Save the configuration to a file. This is to imitate scenarios where users have an existing configuration file that they want to load in and use.

```

myconfig_path = Path("../", "..", "data", "config", "myconfig.json")
with myconfig_path.open("w") as f:
    f.write(myconfig.json())

```

Let's remind ourselves of the project contents. Note that some processing with default parameters has already taken place.

```
project_path = Path("../", "..", "data", "project", "kap03")
sd.seedir(str(project_path), style="emoji")
```

```
kap03/
├─ spectra/
├─ images/
├─ resistics.json
├─ masks/
├─ results/
├─ kap160/
│   └─ default/
│       └─ 0_2000000_impedancetensor_default.json
├─ calibrate/
├─ evals/
│   └─ kap160/
│       └─ default/
│           └─ meas01/
│               ├── data.npz
│               └─ metadata.json
├─ features/
├─ time/
│   ├── kap172/
│   │   └─ meas01/
│   │       ├── metadata.json
│   │       └─ data.npy
│   ├── kap163/
│   │   └─ meas01/
│   │       ├── metadata.json
│   │       └─ data.npy
│   └─ kap160/
│       └─ meas01/
│           ├── metadata.json
│           └─ data.npy
```

Now load our configuration and the project with myconfig.

```
config = Configuration.parse_file(myconfig_path)
resenv = letsgo.load(project_path, config=config)
resenv.config.summary()
```

```
{
  'name': 'myconfig',
  'time_readers': [
    {
      'name': 'TimeReaderNumpy',
      'apply_scalings': True,
      'extension': '.npy'
    }
  ],
  'time_processors': [
    {'name': 'InterpolateNans'},
    {'name': 'RemoveMean'},
```

(continues on next page)



(continued from previous page)

```

        {'name': 'Multiply', 'multiplier': {'Ex': -1.0, 'Ey': -1.0}}
    ],
    'dec_setup': {
        'name': 'DecimationSetup',
        'n_levels': 7,
        'per_level': 3,
        'min_samples': 256,
        'div_factor': 2,
        'eval_freqs': None
    },
    'decimator': {
        'name': 'Decimator',
        'resample': True,
        'max_single_factor': 3
    },
    'win_setup': {
        'name': 'WindowSetup',
        'min_size': 64,
        'min_olap': 16,
        'win_factor': 4,
        'olap_proportion': 0.25,
        'min_n_wins': 5,
        'win_sizes': None,
        'olap_sizes': None
    },
    'windower': {'name': 'Windower'},
    'fourier': {
        'name': 'FourierTransform',
        'win_fnc': ['kaiser', 14.0],
        'detrend': 'linear',
        'workers': -2
    },
    'spectra_processors': [],
    'evals': {'name': 'EvaluationFreqs'},
    'sensor_calibrator': {
        'name': 'SensorCalibrator',
        'chans': None,
        'readers': [
            {
                'name': 'SensorCalibrationJSON',
                'extension': '.json',
                'file_str': 'IC_$sensor$extension'
            }
        ]
    },
    'tf': {
        'name': 'ImpedanceTensor',
        'variation': 'default',
        'out_chans': ['Ex', 'Ey'],
        'in_chans': ['Hx', 'Hy'],
        'cross_chans': ['Hx', 'Hy'],
        'n_out': 2,

```

(continues on next page)

(continued from previous page)

```

        'n_in': 2,
        'n_cross': 2
    },
    'regression_preparer': {'name': 'RegressionPreparerGathered'},
    'solver': {
        'name': 'SolverScikitTheilSen',
        'fit_intercept': False,
        'normalize': False,
        'n_jobs': -2,
        'max_subpopulation': 2000,
        'n_subsamples': None
    }
}

```

Now calculate the evaluation frequency spectral data and view the directory structure. This shows how resistics handles saving data for different configurations. The data is placed in a new folder with the same name as the the configuration. This is why the configuration name is important.

```

site = resenv.proj["kap160"]
for meas in site:
    letsgo.process_time_to_evals(resenv, "kap160", meas.name)
sd.seedir(str(project_path), style="emoji")

```

```

kap03/
├── spectra/
├── images/
├── resistics.json
├── masks/
├── results/
├── kap160/
│   ├── default/
│   │   └── 0_2000000_impedancetensor_default.json
├── calibrate/
├── evals/
│   ├── kap160/
│   │   ├── default/
│   │   │   ├── meas01/
│   │   │   │   ├── data.npz
│   │   │   │   └── metadata.json
│   │   └── myconfig/
│   │       ├── meas01/
│   │       │   ├── data.npz
│   │       │   └── metadata.json
├── features/
├── time/
│   ├── kap172/
│   │   ├── meas01/
│   │   │   ├── metadata.json
│   │   │   └── data.npy
│   ├── kap163/
│   │   ├── meas01/
│   │   │   └── metadata.json

```

(continues on next page)

(continued from previous page)

```

└─ data.npy
└─ kap160/
   └─ meas01/
      ├── metadata.json
      └─ data.npy

```

Let's calculate the impedance tensor with this configuration. The sampling frequency to process is 0.2 (Hz)

```

letsgo.process_evals_to_tf(resenv, 0.2, "kap160")
sd.seedir(str(project_path), style="emoji")

```

```

0%|          | 0/21 [00:00<?, ?it/s]
10%|9        | 2/21 [00:00<00:01, 11.35it/s]
19%|#9       | 4/21 [00:00<00:01, 13.19it/s]
38%|###8     | 8/21 [00:00<00:00, 21.89it/s]
100%|#####  | 21/21 [00:00<00:00, 45.89it/s]

```

```

0%|          | 0/21 [00:00<?, ?it/s]
5%|4         | 1/21 [00:03<01:03, 3.16s/it]
10%|9        | 2/21 [00:06<01:00, 3.16s/it]
14%|#4       | 3/21 [00:09<00:56, 3.16s/it]
19%|#9       | 4/21 [00:11<00:43, 2.55s/it]
24%|##3      | 5/21 [00:12<00:35, 2.22s/it]
29%|##8      | 6/21 [00:14<00:30, 2.01s/it]
33%|###3     | 7/21 [00:14<00:21, 1.51s/it]
38%|###8     | 8/21 [00:15<00:15, 1.19s/it]
43%|####2    | 9/21 [00:15<00:11, 1.03it/s]
48%|####7    | 10/21 [00:16<00:08, 1.32it/s]
52%|####2    | 11/21 [00:16<00:06, 1.64it/s]
57%|####7    | 12/21 [00:16<00:04, 1.98it/s]
62%|#####1  | 13/21 [00:16<00:03, 2.51it/s]
67%|#####6  | 14/21 [00:16<00:02, 3.08it/s]
71%|#####1  | 15/21 [00:17<00:01, 3.65it/s]
76%|#####6  | 16/21 [00:17<00:01, 4.31it/s]
81%|#####  | 17/21 [00:17<00:00, 4.93it/s]
86%|#####5  | 18/21 [00:17<00:00, 5.49it/s]
90%|#####  | 19/21 [00:17<00:00, 6.17it/s]
95%|#####5  | 20/21 [00:17<00:00, 6.74it/s]
100%|#####  | 21/21 [00:17<00:00, 7.24it/s]
100%|#####  | 21/21 [00:17<00:00, 1.18it/s]

```

```

kap03/
├─ spectra/
├─ images/
├─ resistics.json
├─ masks/
├─ results/
├─ kap160/
│   ├── default/
│   │   └─ 0_2000000_impedancetensor_default.json
│   └─ myconfig/
│       └─ 0_2000000_impedancetensor_default.json
├─ calibrate/

```

(continues on next page)

(continued from previous page)

```

├─ evals/
│   └─ kap160/
│       ├── default/
│       │   ├── meas01/
│       │   │   ├── data.npz
│       │   │   └─ metadata.json
│       │   └─ myconfig/
│       │       ├── meas01/
│       │       │   ├── data.npz
│       │       │   └─ metadata.json
│       └─ features/
├─ time/
│   ├── kap172/
│   │   ├── meas01/
│   │   │   ├── metadata.json
│   │   │   └─ data.npy
│   ├── kap163/
│   │   ├── meas01/
│   │   │   ├── metadata.json
│   │   │   └─ data.npy
│   └─ kap160/
│       ├── meas01/
│       │   ├── metadata.json
│       │   └─ data.npy

```

Finally, let's plot our the impedance tensor for this configuration

```

soln = letsgo.get_solution(
    resenv,
    "kap160",
    resenv.config.name,
    0.2,
    resenv.config.tf.name,
    resenv.config.tf.variation,
)
fig = soln.tf.plot(
    soln.freqs,
    soln.components,
    to_plot=["ExHy", "EyHx"],
    x_lim=[1, 5],
    res_lim=[1, 4],
    phs_lim=[0, 100],
    legend="128",
    symbol="circle",
)
fig.update_layout(height=900)
plotly.io.show(fig)

```

**Total running time of the script:** ( 0 minutes 19.548 seconds)

## Transfer functions

Transfer functions can be customised too depending on needs. There are built-in transfer functions, which have the added benefit of having plotting functions meaning the results can be visualised correctly, for example the impedance tensor.

However, if a completely custom transfer function is required, this can be done with the caveat that there will be no plotting function available. A better solution might be to write a custom transfer function if required. For more about writing custom transfer functions, see the advanced usage.

```
from resistics.transfunc import TransferFunction
```

To initialise a new transfer function, the input and channels need to be defined.

```
tf = TransferFunction(in_chans=["Cat", "Dog"], out_chans=["Tiger", "Wolf"])
print(tf)
tf.summary()
```

```
| Tiger | = | Tiger_Cat  Tiger_Dog  | | Cat  |
| Wolf  |   | Wolf_Cat   Wolf_Dog   | | Dog  |
{
  'name': 'TransferFunction',
  'variation': 'generic',
  'out_chans': ['Tiger', 'Wolf'],
  'in_chans': ['Cat', 'Dog'],
  'cross_chans': ['Cat', 'Dog'],
  'n_out': 2,
  'n_in': 2,
  'n_cross': 2
}
```

It is also possible to set the channels that will be used to calculate out the cross spectra. Note that these channels should be available in the input site, output site and cross site respectively.

```
tf = TransferFunction(
    name="Jungle",
    in_chans=["Cat", "Dog"],
    out_chans=["Tiger", "Wolf"],
    cross_chans=["Lizard", "Crocodile"],
)
print(tf)
tf.summary()
```

```
| Tiger | = | Tiger_Cat  Tiger_Dog  | | Cat  |
| Wolf  |   | Wolf_Cat   Wolf_Dog   | | Dog  |
{
  'name': 'Jungle',
  'variation': 'generic',
  'out_chans': ['Tiger', 'Wolf'],
  'in_chans': ['Cat', 'Dog'],
  'cross_chans': ['Lizard', 'Crocodile'],
  'n_out': 2,
  'n_in': 2,
```

(continues on next page)

(continued from previous page)

```
'n_cross': 2
}
```

In scenarios where the core transfer function stays the same (input and output channels), but the cross channels will be changed, there is an additional variation property that helps separate them.

```
tf = TransferFunction(
    name="Jungle",
    variation="Birds",
    in_chans=["Cat", "Dog"],
    out_chans=["Tiger", "Wolf"],
    cross_chans=["Owl", "Eagle"],
)
print(tf)
tf.summary()
```

```
| Tiger | = | Tiger_Cat  Tiger_Dog  | | Cat  |
| Wolf |   | Wolf_Cat   Wolf_Dog   | | Dog  |
{
  'name': 'Jungle',
  'variation': 'Birds',
  'out_chans': ['Tiger', 'Wolf'],
  'in_chans': ['Cat', 'Dog'],
  'cross_chans': ['Owl', 'Eagle'],
  'n_out': 2,
  'n_in': 2,
  'n_cross': 2
}
```

**Total running time of the script:** ( 0 minutes 0.010 seconds)

## 4.2 Custom processes

Writing a custom process coming soon

## 4.3 resistics package

### 4.3.1 Submodules

#### resistics.calibrate module

Functions and classes for instrument and sensor calibration of data

Calibration data should be given in the frequency domain and has a magnitude and phase component (in radians). Calibration data is the impulse response for an instrument or sensor and is usually deconvolved (division in frequency domain) from the time data.

## Notes

Calibration data for induction coils is given in mV/nT. Because this is deconvolved from magnetic time data, which is in mV, the resultant magnetic time data is in nT.

### pydantic model `resisticks.calibrate.CalibrationData`

Bases: `WriteableMetadata`

Class for holding calibration data

Calibration is usually the transfer function of the instrument or sensor to be removed from the data. It is expected to be in the frequency domain.

Regarding units:

- Magnitude units are dependent on use case
- Phase is in radians

```
{
  "title": "CalibrationData",
  "description": "Class for holding calibration data\n\nCalibration is usually the_\n→transfer function of the instrument or sensor\nto be removed from the data. It is_\n→expected to be in the frequency domain.\n\nRegarding units:\n\n- Magnitude units_\n→are dependent on use case\n- Phase is in radians",
  "type": "object",
  "properties": {
    "file_info": {
      "$ref": "#/definitions/ResisticksFile"
    },
    "file_path": {
      "title": "File Path",
      "type": "string",
      "format": "path"
    },
    "sensor": {
      "title": "Sensor",
      "default": "",
      "type": "string"
    },
    "serial": {
      "title": "Serial",
      "anyOf": [
        {
          "type": "integer"
        },
        {
          "type": "string"
        }
      ]
    },
    "static_gain": {
      "title": "Static Gain",
      "default": 1,
      "type": "number"
    }
  }
}
```

(continues on next page)

(continued from previous page)

```

    "magnitude_unit": {
      "title": "Magnitude Unit",
      "default": "mV/nT",
      "type": "string"
    },
    "frequency": {
      "title": "Frequency",
      "type": "array",
      "items": {
        "type": "number"
      }
    },
    "magnitude": {
      "title": "Magnitude",
      "type": "array",
      "items": {
        "type": "number"
      }
    },
    "phase": {
      "title": "Phase",
      "type": "array",
      "items": {
        "type": "number"
      }
    },
    "n_samples": {
      "title": "N Samples",
      "type": "integer"
    }
  },
  "required": [
    "serial",
    "frequency",
    "magnitude",
    "phase"
  ],
  "definitions": {
    "ResisticsFile": {
      "title": "ResisticsFile",
      "description": "Required information for writing out a resistics file",
      "type": "object",
      "properties": {
        "created_on_local": {
          "title": "Created On Local",
          "type": "string",
          "format": "date-time"
        },
        "created_on_utc": {
          "title": "Created On Utc",
          "type": "string",
          "format": "date-time"
        }
      }
    }
  }
}

```

(continues on next page)



(continued from previous page)

```

    },
    "version": {
        "title": "Version",
        "type": "string"
    }
}
}
}
}
}

```

**field file\_path:** `Path | None = None`

Path to the calibration file

**field sensor:** `str = ''`

Sensor type

**field serial:** `int | str [Required]`

Serial number of the sensor

**field static\_gain:** `float = 1`

Static gain to apply

**field magnitude\_unit:** `str = 'mV/nT'`

Units of the magnitude

**field frequency:** `List[float] [Required]`

Frequencies in Hz

**field magnitude:** `List[float] [Required]`

Magnitude

**field phase:** `List[float] [Required]`

Phase

**field n\_samples:** `int | None = None`

Number of data samples

#### Validated by

- `validate_n_samples`

**plot**(*fig: Figure | None = None, color: str = 'blue', legend: str = 'CalibrationData'*) → Figure

Plot calibration data

#### Parameters

- **fig** (*Optional[go.Figure], optional*) – A figure if adding the calibration data to an existing plot, by default None
- **color** (*str, optional*) – The color for the plot, by default “blue”
- **legend** (*str, optional*) – The legend name, by default “CalibrationData”

#### Returns

Plotly figure with the calibration data added

#### Return type

`go.Figure`

`to_dataframe()` → `DataFrame`

Convert to pandas DataFrame

**pydantic model** `resisticks.calibrate.CalibrationReader`

Bases: `ResisticksProcess`

Parent class for reading calibration data

```
{
  "title": "CalibrationReader",
  "description": "Parent class for reading calibration data",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "extension": {
      "title": "Extension",
      "type": "string"
    }
  }
}
```

**field extension:** `str | None = None`

**pydantic model** `resisticks.calibrate.InstrumentCalibrationReader`

Bases: `CalibrationReader`

Parent class for reading instrument calibration files

```
{
  "title": "InstrumentCalibrationReader",
  "description": "Parent class for reading instrument calibration files",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "extension": {
      "title": "Extension",
      "type": "string"
    }
  }
}
```

**run**(*metadata*: `SpectraMetadata`) → `CalibrationData`

**pydantic model** `resisticks.calibrate.SensorCalibrationReader`

Bases: `CalibrationReader`

Parent class for reading sensor calibration files

Use this reader for induction coil calibration file readers

## Examples

A short example to show how naming substitution works

```
>>> from pathlib import Path
>>> from resisticks.testing import time_metadata_1chan
>>> from resisticks.calibrate import SensorCalibrationReader
>>> calibration_path = Path("test")
>>> metadata = time_metadata_1chan()
>>> metadata.chans_metadata["chan1"].sensor = "example"
>>> metadata.chans_metadata["chan1"].serial = "254"
>>> calibrator = SensorCalibrationReader(extension=".json")
>>> calibrator.file_str
'IC_$sensor$extension'
>>> file_path = calibrator._get_path(calibration_path, metadata, "chan1")
>>> file_path.name
'IC_example.json'
```

If the file name has a different pattern, the file\_str can be changed as required.

```
>>> calibrator = SensorCalibrationReader(file_str="$sensor_$serial$extension",
↳ extension=".json")
>>> file_path = calibrator._get_path(calibration_path, metadata, "chan1")
>>> file_path.name
'example_254.json'
```

```
{
  "title": "SensorCalibrationReader",
  "description": "Parent class for reading sensor calibration files\n\nUse this_
↳ reader for induction coil calibration file readers\n\nExamples\n-----\nA short_
↳ example to show how naming substitution works\n\n>>> from pathlib import Path\n>>>
↳ from resisticks.testing import time_metadata_1chan\n>>> from resisticks.calibrate_
↳ import SensorCalibrationReader\n>>> calibration_path = Path(\"test\")\n>>>_
↳ metadata = time_metadata_1chan()\n>>> metadata.chans_metadata[\"chan1\"].sensor =_
↳ \"example\"\n>>> metadata.chans_metadata[\"chan1\"].serial = \"254\"\n>>>_
↳ calibrator = SensorCalibrationReader(extension=\".json\")\n>>> calibrator.file_
↳ str\n'IC_$sensor$extension'\n>>> file_path = calibrator._get_path(calibration_
↳ path, metadata, \"chan1\")\n>>> file_path.name\n'IC_example.json'\n\nIf the file_
↳ name has a different pattern, the file_str can be changed as\nrequired.\n\n>>>_
↳ calibrator = SensorCalibrationReader(file_str=\"$sensor_$serial$extension\",_
↳ extension=\".json\")\n>>> file_path = calibrator._get_path(calibration_path,_
↳ metadata, \"chan1\")\n>>> file_path.name\n'example_254.json'",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "extension": {
      "title": "Extension",
      "type": "string"
    },
    "file_str": {
```

(continues on next page)

(continued from previous page)

```

        "title": "File Str",
        "default": "IC_${sensor}$extension",
        "type": "string"
    }
}

```

**field file\_str:** `str = 'IC_${sensor}$extension'`

**run**(*dir\_path*: *Path*, *metadata*: *SpectraMetadata*, *chan*: *str*) → *CalibrationData*

Run the calibration file reader

#### Parameters

- **dir\_path** (*Path*) – The directory with calibration files
- **metadata** (*SpectraMetadata*) – TimeData metadata
- **chan** (*str*) – The channel for which to search for a calibration file

#### Returns

The calibration data

#### Return type

*CalibrationData*

#### Raises

**CalibrationFileNotFound** – If the calibration file does not exist

**read\_calibration\_data**(*file\_path*: *Path*, *chan\_metadata*: *ChanMetadata*) → *CalibrationData*

Read calibration data from a file

This is implemented as a separate function for anyone interested in reading a calibration file separately from the run function.

#### Parameters

- **file\_path** (*Path*) – The file path of the calibration file
- **chan\_metadata** (*ChanMetadata*) – The channel metadata

#### Raises

**NotImplementedError** – To be implemented in child classes

**pydantic model** `resistics.calibrate.SensorCalibrationJSON`

Bases: *SensorCalibrationReader*

Read in JSON formatted calibration data

```

{
  "title": "SensorCalibrationJSON",
  "description": "Read in JSON formatted calibration data",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "extension": {

```

(continues on next page)

(continued from previous page)

```

        "title": "Extension",
        "default": ".json",
        "type": "string"
    },
    "file_str": {
        "title": "File Str",
        "default": "IC_${sensor}$extension",
        "type": "string"
    }
}

```

**field extension:** `str = '.json'`

**read\_calibration\_data**(*file\_path*: *Path*, *chan\_metadata*: *ChanMetadata*) → *CalibrationData*

Read the JSON calibration data

#### Parameters

- **file\_path** (*Path*) – The file path of the JSON calibration file
- **chan\_metadata** (*ChanMetadata*) – The channel metadata. Note that this is not used but is kept here to ensure signature match to the parent class

#### Returns

The calibration data

#### Return type

*CalibrationData*

**pydantic model** `resistics.calibrate.SensorCalibrationTXT`

Bases: *SensorCalibrationReader*

Read in calibration data from a TXT file

In general, JSON calibration files are recommended as they are more reliable to read in. However, there are cases where it is easier to write out a text based calibration file.

The format of the calibration file should be as follows:

```

Serial = 710
Sensor = LEMI120
Static gain = 1
Magnitude unit = mV/nT
Phase unit = degrees
Chopper = False

CALIBRATION DATA
1.1000E-4      1.000E-2      9.0000E1
1.1000E-3      1.000E-1      9.0000E1
1.1000E-2      1.000E0      8.9000E1
2.1000E-2      1.903E0      8.8583E1

```

See also:

*SensorCalibrationJSON*

Reader for JSON calibration files

```
{
  "title": "SensorCalibrationTXT",
  "description": "Read in calibration data from a TXT file\n\nIn general, JSON_
↪ calibration files are recommended as they are more reliable\nto read in. However,
↪ there are cases where it is easier to write out a text\nbased calibration file.\n\
↪ The format of the calibration file should be as follows:\n\n.. code-block:: text\
↪ \n\n    Serial = 710\n    Sensor = LEMI120\n    Static gain = 1\n    Magnitude_
↪ unit = mV/nT\n    Phase unit = degrees\n    Chopper = False\n\n    CALIBRATION_
↪ DATA\n    1.1000E-4    1.000E-2    9.0000E1\n    1.1000E-3    1.000E-1
↪ 9.0000E1\n    1.1000E-2    1.000E0    8.9000E1\n    2.1000E-2    1.
↪ 903E0    8.8583E1\n\nSee Also\n-----\nSensorCalibrationJSON : Reader for JSON_
↪ calibration files",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "extension": {
      "title": "Extension",
      "default": ".TXT",
      "type": "string"
    },
    "file_str": {
      "title": "File Str",
      "default": "IC_$sensor$extension",
      "type": "string"
    }
  }
}
```

**read\_calibration\_data**(*file\_path*: *Path*, *chan\_metadata*: *ChanMetadata*) → *CalibrationData*

Read the TXT calibration data

#### Parameters

- **file\_path** (*Path*) – The file path of the JSON calibration file
- **chan\_metadata** (*ChanMetadata*) – The channel metadata. Note that this is not used but is kept here to ensure signature match to the parent class

#### Returns

The calibration data

#### Return type

*CalibrationData*

**pydantic model** `resisticks.calibrate.Calibrator`

Bases: *ResisticksProcess*

Parent class for a calibrator

```
{
  "title": "Calibrator",
  "description": "Parent class for a calibrator",
  "type": "object",
```

(continues on next page)

(continued from previous page)

```

    "properties": {
      "name": {
        "title": "Name",
        "type": "string"
      },
      "chans": {
        "title": "Chans",
        "type": "array",
        "items": {
          "type": "string"
        }
      }
    }
  }
}

```

**field chans:** `List[str] | None = None`

List of channels to calibrate

**run**(*dir\_path*: *Path*, *spec\_data*: *SpectraData*) → *SpectraData*

Run the instrument calibration

**pydantic model** `resistics.calibrate.InstrumentCalibrator`

Bases: *Calibrator*

```

{
  "title": "InstrumentCalibrator",
  "description": "Parent class for a calibrator",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "chans": {
      "title": "Chans",
      "type": "array",
      "items": {
        "type": "string"
      }
    },
    "readers": {
      "title": "Readers",
      "type": "array",
      "items": {
        "$ref": "#/definitions/InstrumentCalibrationReader"
      }
    }
  },
  "required": [
    "readers"
  ],
  "definitions": {

```

(continues on next page)

(continued from previous page)

```

    "InstrumentCalibrationReader": {
      "title": "InstrumentCalibrationReader",
      "description": "Parent class for reading instrument calibration files",
      "type": "object",
      "properties": {
        "name": {
          "title": "Name",
          "type": "string"
        },
        "extension": {
          "title": "Extension",
          "type": "string"
        }
      }
    }
  }
}

```

**field readers:** `List[InstrumentCalibrationReader]` [Required]

List of readers for reading in instrument calibration files

**pydantic model** `resistics.calibrate.SensorCalibrator`

Bases: `Calibrator`

```

{
  "title": "SensorCalibrator",
  "description": "Parent class for a calibrator",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "chans": {
      "title": "Chans",
      "type": "array",
      "items": {
        "type": "string"
      }
    },
    "readers": {
      "title": "Readers",
      "type": "array",
      "items": {
        "$ref": "#/definitions/SensorCalibrationReader"
      }
    }
  },
  "required": [
    "readers"
  ],
  "definitions": {

```

(continues on next page)



(continued from previous page)

```

    "SensorCalibrationReader": {
        "title": "SensorCalibrationReader",
        "description": "Parent class for reading sensor calibration files\n\nUse_
→this reader for induction coil calibration file readers\n\nExamples\n-----\nA_
→short example to show how naming substitution works\n\n>>> from pathlib import_
→Path\n>>> from resistics.testing import time_metadata_1chan\n>>> from resistics.
→calibrate import SensorCalibrationReader\n>>> calibration_path = Path(\"test\")\n>
→>> metadata = time_metadata_1chan()\n>>> metadata.chans_metadata[\"chan1\"].
→sensor = \"example\"\n>>> metadata.chans_metadata[\"chan1\"].serial = \"254\"\n>>>
→calibrator = SensorCalibrationReader(extension=\".json\")\n>>> calibrator.file_
→str\n'IC_$sensor$extension'\n>>> file_path = calibrator._get_path(calibration_
→path, metadata, \"chan1\")\n>>> file_path.name\n'IC_example.json'\n\nIf the file_
→name has a different pattern, the file_str can be changed as\nrequired.\n\n>>>_
→calibrator = SensorCalibrationReader(file_str=\"$sensor_$serial$extension\",_
→extension=\".json\")\n>>> file_path = calibrator._get_path(calibration_path,_
→metadata, \"chan1\")\n>>> file_path.name\n'example_254.json',
        "type": "object",
        "properties": {
            "name": {
                "title": "Name",
                "type": "string"
            },
            "extension": {
                "title": "Extension",
                "type": "string"
            },
            "file_str": {
                "title": "File Str",
                "default": "IC_$sensor$extension",
                "type": "string"
            }
        }
    }
}

```

**field readers:** `List[SensorCalibrationReader]` [Required]

List of readers for reading in sensor calibration files

**run**(*dir\_path*: `Path`, *spec\_data*: `SpectraData`) → `SpectraData`

Calibrate Spectra data

### resistics.common module

Common resistics functions and classes used throughout the package

`resistics.common.get_version()` → `str`

Get the version of resistics

`resistics.common.is_file(file_path: Path)` → `bool`

Check if a path exists and points to a file

**Parameters**

**file\_path** (*Path*) – The path to check

**Returns**

True if it exists and is a file, False otherwise

**Return type**

`bool`

`resistics.common.assert_file(file_path: Path) → None`

Require that a file exists

**Parameters**

**file\_path** (*Path*) – The path to check

**Raises**

- **FileNotFoundError** – If the path does not exist
- **NotFileError** – If the path is not a file

`resistics.common.is_dir(dir_path: Path) → bool`

Check if a path exists and points to a directory

**Parameters**

**dir\_path** (*Path*) – The path to check

**Returns**

True if it exists and is a directory, False otherwise

**Return type**

`bool`

`resistics.common.assert_dir(dir_path: Path) → None`

Require that a path is a directory

**Parameters**

**dir\_path** (*Path*) – Path to check

**Raises**

- **FileNotFoundError** – If the path does not exist
- **NotDirectoryError** – If the path is not a directory

`resistics.common.dir_contents(dir_path: Path) → Tuple[List[Path], List[Path]]`

Get contents of directory

Includes both files and directories

**Parameters**

**dir\_path** (*Path*) – Parent directory path

**Returns**

- **dirs** (*list*) – List of directories
- **files** (*list*) – List of files excluding hidden files

**Raises**

- **PathNotFoundError** – Path does not exist
- **NotDirectoryError** – Path is not a directory

`resistics.common.dir_files(dir_path: Path) → List[Path]`

Get files in directory

Excludes hidden files

**Parameters**

**dir\_path** (*Path*) – Parent directory path

**Returns**

**files** – List of files excluding hidden files

**Return type**

*list*

`resistics.common.dir_subdirs(dir_path: Path) → List[Path]`

Get subdirectories in directory

Excludes hidden files

**Parameters**

**dir\_path** (*Path*) – Parent directory path

**Returns**

**dirs** – List of subdirectories

**Return type**

*list*

`resistics.common.known_chan(chan: str) → bool`

Check whether resistics is familiar with a channel name

**Parameters**

**chan** (*str*) – The channel name

**Returns**

True if it is a resistics known channel, false otherwise

**Return type**

*bool*

## Examples

```
>>> from resistics.common import known_chan
>>> known_chan("Ex")
True
>>> known_chan("Hy")
True
>>> known_chan("cat")
False
```

`resistics.common.is_electric(chan: str) → bool`

Check if a channel is electric

**Parameters**

**chan** (*str*) – Channel name

**Returns**

True if channel is electric

**Return type**`bool`**Examples**

```
>>> from resisticks.common import is_electric
>>> is_electric("Ex")
True
>>> is_electric("Hx")
False
```

`resisticks.common.is_magnetic(chan: str) → bool`

Check if channel is magnetic

**Parameters**

**chan** (`str`) – Channel name

**Returns**

True if channel is magnetic

**Return type**`bool`**Examples**

```
>>> from resisticks.common import is_magnetic
>>> is_magnetic("Ex")
False
>>> is_magnetic("Hx")
True
```

`resisticks.common.get_chan_type(chan: str) → str`

Get the channel type from the channel name

**Parameters**

**chan** (`str`) – The name of the channel

**Returns**

The channel type

**Return type**`str`**Raises**

**ValueError** – If the channel is not known to resisticks

## Examples

```
>>> from resisticks.common import get_chan_type
>>> get_chan_type("Ex")
'electric'
>>> get_chan_type("Hz")
'magnetic'
>>> get_chan_type("abc")
Traceback (most recent call last):
...
ValueError: Channel abc not recognised as either electric or magnetic
```

`resisticks.common.check_chan(chan: str, chans: Collection[str]) → bool`

Check a channel exists and raise a KeyError if not

### Parameters

- **chan** (*str*) – The channel to check
- **chans** (*Collection[str]*) – A collection of channels to check against

### Returns

True if all checks passed

### Return type

*bool*

### Raises

*ChannelNotFoundError* – If the channel is not found in the channel list

`resisticks.common.fs_to_string(fs: float) → str`

Convert sampling frequency into a string for filenames

### Parameters

**fs** (*float*) – The sampling frequency

### Returns

Sample frequency converted to string for the purposes of a filename

### Return type

*str*

## Examples

```
>>> from resisticks.common import fs_to_string
>>> fs_to_string(512.0)
'512_000000'
```

`resisticks.common.array_to_string(data: ndarray, sep: str = ', ', precision: int = 8, scientific: bool = False) → str`

Convert an array to a string for logging or printing

### Parameters

- **data** (*np.ndarray*) – The array
- **sep** (*str, optional*) – The separator to use, by default “,

- **precision** (*int*, *optional*) – Number of decimal places, by default 8. Ignored for integers.
- **scientific** (*bool*, *optional*) – Flag for formatting floats as scientific, by default False

**Returns**

String representation of array

**Return type**

str

**Examples**

```
>>> import numpy as np
>>> from resistics.common import array_to_string
>>> data = np.array([1,2,3,4,5])
>>> array_to_string(data)
'1, 2, 3, 4, 5'
>>> data = np.array([1,2,3,4,5], dtype=np.float32)
>>> array_to_string(data)
'1.00000000, 2.00000000, 3.00000000, 4.00000000, 5.00000000'
>>> array_to_string(data, precision=3, scientific=True)
'1.000e+00, 2.000e+00, 3.000e+00, 4.000e+00, 5.000e+00'
```

**pydantic model** `resistics.common.ResisticsModel`

Bases: `BaseModel`

Base resistics model

```
{
  "title": "ResisticsModel",
  "description": "Base resistics model",
  "type": "object",
  "properties": {}
}
```

**to\_string()** → str

Class info as string

**summary()** → None

Print a summary of the class

**pydantic model** `resistics.common.ResisticsFile`

Bases: `ResisticsModel`

Required information for writing out a resistics file

```
{
  "title": "ResisticsFile",
  "description": "Required information for writing out a resistics file",
  "type": "object",
  "properties": {
    "created_on_local": {
      "title": "Created On Local",
      "type": "string",

```

(continues on next page)

(continued from previous page)

```

        "format": "date-time"
    },
    "created_on_utc": {
        "title": "Created On Utc",
        "type": "string",
        "format": "date-time"
    },
    "version": {
        "title": "Version",
        "type": "string"
    }
}

```

field created\_on\_local: `datetime` [Optional]

field created\_on\_utc: `datetime` [Optional]

field version: `str` | `None` [Optional]

**pydantic model** `resistics.common.Metadata`

Bases: `ResisticsModel`

Parent class for metadata

```

{
    "title": "Metadata",
    "description": "Parent class for metadata",
    "type": "object",
    "properties": {}
}

```

**pydantic model** `resistics.common.WriteableMetadata`

Bases: `Metadata`

Base class for writeable metadata

```

{
    "title": "WriteableMetadata",
    "description": "Base class for writeable metadata",
    "type": "object",
    "properties": {
        "file_info": {
            "$ref": "#/definitions/ResisticsFile"
        }
    },
    "definitions": {
        "ResisticsFile": {
            "title": "ResisticsFile",
            "description": "Required information for writing out a resistics file",
            "type": "object",
            "properties": {
                "created_on_local": {

```

(continues on next page)

(continued from previous page)

```

        "title": "Created On Local",
        "type": "string",
        "format": "date-time"
    },
    "created_on_utc": {
        "title": "Created On Utc",
        "type": "string",
        "format": "date-time"
    },
    "version": {
        "title": "Version",
        "type": "string"
    }
}
}
}
}

```

**field file\_info:** *ResisticsFile* | None = None

Information about a file, relevant if writing out or reading back in

**write(json\_path: Path)**

Write out JSON metadata file

#### Parameters

**json\_path** (*Path*) – Path to write JSON file

**pydantic model** *resistics.common.Record*

Bases: *ResisticsModel*

Class to hold a record

A record holds information about a process that was run. It is intended to track processes applied to data, allowing a process history to be saved along with any datasets.

## Examples

A simple example of creating a process record

```

>>> from resistics.common import Record
>>> messages = ["message 1", "message 2"]
>>> record = Record(
...     creator={"name": "example", "parameter1": 15},
...     messages=messages,
...     record_type="example"
... )
>>> record.summary()
{
  'time_local': '...',
  'time_utc': '...',
  'creator': {'name': 'example', 'parameter1': 15},
  'messages': ['message 1', 'message 2'],
  'record_type': 'example'
}

```



```

{
  "title": "Record",
  "description": "Class to hold a record\n\nA record holds information about a
↪process that was run. It is intended to\ntrack processes applied to data,
↪allowing a process history to be saved\nalong with any datasets.\n\nExamples\n----
↪----\nA simple example of creating a process record\n\n>>> from resistics.common
↪import Record\n\n>>> messages = ['message 1', 'message 2']\n\n>>> record =
↪Record(\n...     creator={'name': 'example', 'parameter1': 15},\n...     ↪
↪messages=messages,\n...     record_type='example'\n... )\n\n>>> record.summary()\n
↪{\n    'time_local': '...',\n    'time_utc': '...',\n    'creator': {'name':
↪'example', 'parameter1': 15},\n    'messages': ['message 1', 'message 2'],\n
↪'record_type': 'example'\n}",
  "type": "object",
  "properties": {
    "time_local": {
      "title": "Time Local",
      "type": "string",
      "format": "date-time"
    },
    "time_utc": {
      "title": "Time Utc",
      "type": "string",
      "format": "date-time"
    },
    "creator": {
      "title": "Creator",
      "type": "object"
    },
    "messages": {
      "title": "Messages",
      "type": "array",
      "items": {
        "type": "string"
      }
    },
    "record_type": {
      "title": "Record Type",
      "type": "string"
    }
  },
  "required": [
    "creator",
    "messages",
    "record_type"
  ]
}

```

**field time\_local:** `datetime` [Optional]

The local time when the process ran

**field time\_utc:** `datetime` [Optional]

The UTC time when the process ran

**field creator:** `Dict[str, Any]` [Required]

The creator and its parameters as a dictionary

**field messages:** `List[str]` [Required]

Any messages in the record

**field record\_type:** `str` [Required]

The record type

**pydantic model** `resisticks.common.History`

Bases: `ResisticksModel`

Class for storing processing history

**Parameters**

**records** (`List[Record]`, *optional*) – List of records, by default []

## Examples

```
>>> from resisticks.testing import record_example1, record_example2
>>> from resisticks.common import History
>>> record1 = record_example1()
>>> record2 = record_example2()
>>> history = History(records=[record1, record2])
>>> history.summary()
{
  'records': [
    {
      'time_local': '...',
      'time_utc': '...',
      'creator': {
        'name': 'example1',
        'a': 5,
        'b': -7.0
      },
      'messages': ['Message 1', 'Message 2'],
      'record_type': 'process'
    },
    {
      'time_local': '...',
      'time_utc': '...',
      'creator': {
        'name': 'example2',
        'a': 'parzen',
        'b': -21
      },
      'messages': ['Message 5', 'Message 6'],
      'record_type': 'process'
    }
  ]
}
```

```
{
  "title": "History",
```

(continues on next page)

(continued from previous page)

```

    "description": "Class for storing processing history\n\nParameters\n-----\n
→nrecords : List[Record], optional\n    List of records, by default []\n\nExamples\n
→n-----\n>>> from resistics.testing import record_example1, record_example2\n>>>
→ from resistics.common import History\n>>> record1 = record_example1()\n>>>
→ record2 = record_example2()\n>>> history = History(records=[record1, record2])\n>>
→ history.summary()\n{\n    'records': [\n        {\n            'time_local': '..
→.',\n            'time_utc': '...',\n            'creator': {\n
→'name': 'example1',\n            'a': 5,\n            'b': -7.0\n
→ },\n            'messages': ['Message 1', 'Message 2'],\n            'record_
→type': 'process'\n        },\n        {\n            'time_local': '...',\n
→            'time_utc': '...',\n            'creator': {\n
→'example2',\n            'a': 'parzen',\n            'b': -21\n
→ },\n            'messages': ['Message 5', 'Message 6'],\n            'record_type
→': 'process'\n        }\n    ]\n}",
    "type": "object",
    "properties": {
        "records": {
            "title": "Records",
            "default": [],
            "type": "array",
            "items": {
                "$ref": "#/definitions/Record"
            }
        }
    },
    "definitions": {
        "Record": {
            "title": "Record",
            "description": "Class to hold a record\n\nA record holds information about
→a process that was run. It is intended to\ntrack processes applied to data,
→allowing a process history to be saved\nalong with any datasets.\n\nExamples\n----
→----\nA simple example of creating a process record\n\n>>> from resistics.common
→import Record\n>>> messages = ["message 1", "message 2"]\n>>> record =
→Record(\n...     creator={"name": "example", "parameter1": 15},\n...
→messages=messages,\n...     record_type="example"\n... )\n>>> record.summary()\n
→{\n    'time_local': '...',\n    'time_utc': '...',\n    'creator': {'name':
→'example', 'parameter1': 15},\n    'messages': ['message 1', 'message 2'],\n
→'record_type': 'example'\n}",
            "type": "object",
            "properties": {
                "time_local": {
                    "title": "Time Local",
                    "type": "string",
                    "format": "date-time"
                },
                "time_utc": {
                    "title": "Time Utc",
                    "type": "string",
                    "format": "date-time"
                },
                "creator": {
                    "title": "Creator",

```

(continues on next page)

(continued from previous page)

```

        "type": "object"
    },
    "messages": {
        "title": "Messages",
        "type": "array",
        "items": {
            "type": "string"
        }
    },
    "record_type": {
        "title": "Record Type",
        "type": "string"
    }
},
"required": [
    "creator",
    "messages",
    "record_type"
]
}
}
}

```

**field records:** `List[Record]` = []

**add\_record**(*record*: `Record`)

Add a process record to the list

#### Parameters

**record** (`Record`) – The record to add

`resistics.common.get_record`(*creator*: `Dict[str, Any]`, *messages*: `str | List[str]`, *record\_type*: `str = 'process'`, *time\_utc*: `datetime | None = None`, *time\_local*: `datetime | None = None`) → `Record`

Get a process record

#### Parameters

- **creator** (`Dict[str, Any]`) – The creator and its parameters as a dictionary
- **messages** (`Union[str, List[str]]`) – The messages as either a single str or a list of strings
- **record\_type** (`str`, *optional*) – The type of record, by default “process”
- **time\_utc** (`Optional[datetime]`, *optional*) – UTC time to attach to the record, by default None. If None, will default to UTC now
- **time\_local** (`Optional[datetime]`, *optional*) – Local time to attach to the record, by default None. If None, will default to local now

#### Returns

The process record

#### Return type

`Record`

## Examples

```
>>> from resistics.common import get_record
>>> record = get_record(
...     creator={"name": "example", "a": 5, "b": -7.0},
...     messages="a message"
... )
>>> record.creator
{'name': 'example', 'a': 5, 'b': -7.0}
>>> record.messages
['a message']
>>> record.record_type
'process'
>>> record.time_utc
datetime.datetime(...)
>>> record.time_local
datetime.datetime(...)
```

`resistics.common.get_history(record: Record, history: History | None = None) → History`

Get a new History instance or add a record to a copy of an existing one

This method always makes a deepcopy of an input history to avoid any unplanned modifications to the inputs.

### Parameters

- **record** ([Record](#)) – The record
- **history** (*Optional* [[History](#)], *optional*) – A history to add to, by default *None*

### Returns

History with the record added

### Return type

[History](#)

## Examples

Get a new History with a single Record

```
>>> from resistics.common import get_history
>>> from resistics.testing import record_example1, record_example2
>>> record1 = record_example1()
>>> history = get_history(record1)
>>> history.summary()
{
  'records': [
    {
      'time_local': '...',
      'time_utc': '...',
      'creator': {
        'name': 'example1',
        'a': 5,
        'b': -7.0
      },
      'messages': ['Message 1', 'Message 2'],
```

(continues on next page)

(continued from previous page)

```

        'record_type': 'process'
    }
]
}

```

Alternatively, add to an existing History. This will make a copy of the original history. If a copy is not needed, the `add_record` method of history can be used.

```

>>> record2 = record_example2()
>>> history = get_history(record2, history)
>>> history.summary()
{
  'records': [
    {
      'time_local': '...',
      'time_utc': '...',
      'creator': {
        'name': 'example1',
        'a': 5,
        'b': -7.0
      },
      'messages': ['Message 1', 'Message 2'],
      'record_type': 'process'
    },
    {
      'time_local': '...',
      'time_utc': '...',
      'creator': {
        'name': 'example2',
        'a': 'parzen',
        'b': -21
      },
      'messages': ['Message 5', 'Message 6'],
      'record_type': 'process'
    }
  ]
}

```

### pydantic model `resistics.common.ResisticsProcess`

Bases: [ResisticsModel](#)

Base class for resistics processes

Resistics processes perform operations on data (including read and write operations). Each time a `ResisticsProcess` child class is run, it should add a process record to the dataset

```

{
  "title": "ResisticsProcess",
  "description": "Base class for resistics processes\n\nResistics processes_\n
↳ perform operations on data (including read and write\noperations). Each time a_\n
↳ ResisticsProcess child class is run, it should add\nna process record to the_\n
↳ dataset",
  "type": "object",

```

(continues on next page)

(continued from previous page)

```

    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        }
    }
}

```

**field name:** `str | None = None`

**Validated by**

- `validate_name`

**classmethod `validate`**(*value*: `ResisticsProcess | Dict[str, Any]`) → *ResisticsProcess*

Validate a *ResisticsProcess* in another pydantic class

**Parameters**

**value** (`Union[ResisticsProcess, Dict[str, Any]]`) – A *ResisticsProcess* child class or a dictionary

**Returns**

A *ResisticsProcess* child class

**Return type**

*ResisticsProcess*

**Raises**

- **ValueError** – If the value is neither a *ResisticsProcess* or a dictionary
- **KeyError** – If name is not in the dictionary
- **ValueError** – If initialising from dictionary fails

## Examples

The following example will show how a generic *ResisticsProcess* child class can be instantiated from *ResisticsProcess* using a dictionary, which might be read in from a JSON configuration file.

```

>>> from resistics.common import ResisticsProcess
>>> from resistics.decimate import DecimationSetup
>>> process = {"name": 'DecimationSetup', "n_levels": 8, "per_level": 5, "min_
↳ samples": 256, "div_factor": 2, "eval_freqs": None}
>>> ResisticsProcess(**process)
ResisticsProcess(name='DecimationSetup')

```

This is not what was expected. To get the right result, the class `validate` method needs to be used. This is done automatically by pydantic.

```

>>> ResisticsProcess.validate(process)
DecimationSetup(name='DecimationSetup', n_levels=8, per_level=5, min_
↳ samples=256, div_factor=2, eval_freqs=None)

```

That's better. Note that errors will be raised if the dictionary is not formatted as expected.

```
>>> process = {"n_levels": 8, "per_level": 5, "min_samples": 256, "div_factor": 2, "eval_freqs": None}
>>> ResisticsProcess.validate(process)
Traceback (most recent call last):
...
KeyError: 'No name provided for initialisation of process'
```

This functionality is most useful in the resistics configurations which can be saved as JSON files. The default configuration uses the default parameterisation of DecimationSetup.

```
>>> from resistics.letsgo import Configuration
>>> config = Configuration(name="example1")
>>> config.dec_setup
DecimationSetup(name='DecimationSetup', n_levels=8, per_level=5, min_
samples=256, div_factor=2, eval_freqs=None)
```

Now create another configuration with a different setup by passing a dictionary. In practise, this dictionary will most likely be read in from a configuration file.

```
>>> setup = DecimationSetup(n_levels=4, per_level=3)
>>> test_dict = setup.dict()
>>> test_dict
{'name': 'DecimationSetup', 'n_levels': 4, 'per_level': 3, 'min_samples': 256,
 'div_factor': 2, 'eval_freqs': None}
>>> config2 = Configuration(name="example2", dec_setup=test_dict)
>>> config2.dec_setup
DecimationSetup(name='DecimationSetup', n_levels=4, per_level=3, min_
samples=256, div_factor=2, eval_freqs=None)
```

This method allows the saving of a configuration with custom processors in a JSON file which can be loaded and used again.

**parameters()** → Dict[str, Any]

Return any process parameters including the process name

These parameters are expected to be primitives and should be sufficient to reinitialise the process and re-run the data. The base class assumes all class variables meet this description.

#### Returns

Dictionary of parameters

#### Return type

Dict[str, Any]

**class resistics.common.ResisticsBase**

Bases: `object`

Resistics base class

Parent class to ensure consistency of common methods

**type\_to\_string()** → str

Get the class type as a string

**to\_string()** → str

Class details as a string



**summary**(symbol: *str* = '-') → None

Print a summary of class details

**class** resisticks.common.ResisticksData

Bases: *ResisticksBase*

Base class for a resisticks data object

**pydantic model** resisticks.common.ResisticksWriter

Bases: *ResisticksProcess*

Parent process for data writers

**Parameters**

**overwrite**(*bool*, *optional*) – Boolean flag for overwriting the existing data, by default False

```
{
  "title": "ResisticksWriter",
  "description": "Parent process for data writers\n\nParameters\n-----\n
↪noverwrite : bool, optional\n    Boolean flag for overwriting the existing data,
↪by default False",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "overwrite": {
      "title": "Overwrite",
      "default": true,
      "type": "boolean"
    }
  }
}
```

**field overwrite:** *bool* = True

**run**(*dir\_path: Path*, *data: ResisticksData*) → None

Write out a ResisticksData child object to a directory

## resisticks.config module

Module containing the resisticks configuration

The configuration is an essential part of a resisticks environment. It defines many dependencies, such as which data readers to use for time series data or calibration data and processing options.

Configuration allows users to insert their own dependencies and processors to work with data.

Configurations can be saved to and loaded from JSON files.

**pydantic model** resisticks.config.Configuration

Bases: *ResisticksModel*

The resisticks configuration

Configuration can be customised by users who wish to use their own custom processes for certain steps. In most cases, customisation will be for:

- Implementing new time data readers
- Implementing readers for specific calibration formats
- Implementing time data processors
- Implementing spectra data processors
- Adding new features to extract from the data

## Examples

Frequently, configuration will be used to change data readers.

```
>>> from resisticks.letsgo import get_default_configuration
>>> config = get_default_configuration()
>>> config.name
'default'
>>> for tr in config.time_readers:
...     tr.summary()
{
  'name': 'TimeReaderAscii',
  'apply_scalings': True,
  'extension': '.txt',
  'delimiter': None,
  'n_header': 0
}
{
  'name': 'TimeReaderNumpy',
  'apply_scalings': True,
  'extension': '.npz'
}
>>> config.sensor_calibrator.summary()
{
  'name': 'SensorCalibrator',
  'chans': None,
  'readers': [
    {
      'name': 'SensorCalibrationJSON',
      'extension': '.json',
      'file_str': 'IC_$sensor$extension'
    }
  ]
}
```

To change these, it's best to make a new configuration with a different name

```
>>> from resisticks.letsgo import Configuration
>>> from resisticks.time import TimeReaderNumpy
>>> config = Configuration(name="myconfig", time_readers=[TimeReaderNumpy(apply_
↵scalings=False)])
>>> for tr in config.time_readers:
...     tr.summary()
{
  'name': 'TimeReaderNumpy',
```

(continues on next page)

(continued from previous page)

```

'apply_scalings': False,
'extension': '.npy'
}

```

Or for the sensor calibration

```

>>> from resistics.calibrate import SensorCalibrator, SensorCalibrationTXT
>>> calibration_reader = SensorCalibrationTXT(file_str="lemi120_IC_$serial$extension
↪")
>>> calibrator = SensorCalibrator(chans=["Hx", "Hy", "Hz"], readers=[calibration_
↪reader])
>>> config = Configuration(name="myconfig", sensor_calibrator=calibrator)
>>> config.sensor_calibrator.summary()
{
  'name': 'SensorCalibrator',
  'chans': ['Hx', 'Hy', 'Hz'],
  'readers': [
    {
      'name': 'SensorCalibrationTXT',
      'extension': '.TXT',
      'file_str': 'lemi120_IC_$serial$extension'
    }
  ]
}

```

As a final example, create a configuration which used targetted windowing instead of specified window sizes

```

>>> from resistics.letsgo import Configuration
>>> from resistics.window import WindowerTarget
>>> config = Configuration(name="window_target",
↪windower=WindowerTarget(target=500))
>>> config.name
'window_target'
>>> config.windower.summary()
{
  'name': 'WindowerTarget',
  'target': 500,
  'min_size': 64,
  'olap_proportion': 0.25
}

```

```

{
  "title": "Configuration",
  "description": "The resistics configuration\n\nConfiguration can be customised_
↪by users who wish to use their own custom\nprocesses for certain steps. In most_
↪cases, customisation will be for:\n\n- Implementing new time data readers\n_
↪Implementing readers for specific calibration formats\n- Implementing time data_
↪processors\n- Implementing spectra data processors\n- Adding new features to_
↪extract from the data\n\nExamples\n-----\n\nFrequently, configuration will be_
↪used to change data readers.\n\n>>> from resistics.letsgo import get_default_
↪configuration\n>>> config = get_default_configuration()\n>>> config.name\n'default'
↪'\n>>> for tr in config.time_readers:\n...     tr.summary()\n{\n    'name':

```

(continues on next page)

(continued from previous page)

```

→ 'TimeReaderAscii',\n      'apply_scalings': True,\n      'extension': '.txt',\n
→ 'delimiter': None,\n      'n_header': 0\n}\n}\n      'name': 'TimeReaderNumpy',\n
→ 'apply_scalings': True,\n      'extension': '.numpy'\n}\n}\n>>> config.sensor_calibrator.
→ summary()\n{\n      'name': 'SensorCalibrator',\n      'chans': None,\n      'readers': \n
→ [\n          {\n              'name': 'SensorCalibrationJSON',\n              'extension'
→ ': '.json',\n              'file_str': 'IC_$sensor$extension'\n          }\n      ]\n}\n
→ \n\nTo change these, it's best to make a new configuration with a different name\n
→ \n>>> from resistics.lets go import Configuration\n>>> from resistics.time import \n
→ TimeReaderNumpy\n>>> config = Configuration(name="myconfig", time_
→ readers=[TimeReaderNumpy(apply_scalings=False)])\n>>> for tr in config.time_
→ readers:\n...      tr.summary()\n{\n      'name': 'TimeReaderNumpy',\n      'apply_
→ scalings': False,\n      'extension': '.numpy'\n}\n}\n\nOr for the sensor calibration\n
→ \n>>> from resistics.calibrate import SensorCalibrator, SensorCalibrationTXT\n>>> \n
→ calibration_reader = SensorCalibrationTXT(file_str="lemi120_IC_$serial$extension"
→ ") \n>>> calibrator = SensorCalibrator(chans=["Hx", "Hy", "Hz"], \n
→ readers=[calibration_reader])\n>>> config = Configuration(name="myconfig", \n
→ sensor_calibrator=calibrator)\n>>> config.sensor_calibrator.summary()\n{\n
→ 'name': 'SensorCalibrator',\n      'chans': ['Hx', 'Hy', 'Hz'],\n      'readers': [\n
→ \n          {\n              'name': 'SensorCalibrationTXT',\n              'extension': '.
→ TXT',\n              'file_str': 'lemi120_IC_$serial$extension'\n          }\n      ]\n}\n
→ \n\nAs a final example, create a configuration which used targetted windowing\
→ \ninstead of specified window sizes\n\n>>> from resistics.lets go import \n
→ Configuration\n>>> from resistics.window import WindowerTarget\n>>> config = \n
→ Configuration(name="window_target", windower=WindowerTarget(target=500))\n>>> \n
→ config.name\n'window_target'\n>>> config.windower.summary()\n{\n      'name':
→ 'WindowerTarget',\n      'target': 500,\n      'min_size': 64,\n      'olap_proportion
→ ': 0.25\n}",
    "type": "object",
    "properties": {
      "name": {
        "title": "Name",
        "type": "string"
      },
    },
    "time_readers": {
      "title": "Time Readers",
      "default": [
        {
          "name": "TimeReaderAscii",
          "apply_scalings": true,
          "extension": ".txt",
          "delimiter": null,
          "n_header": 0
        },
        {
          "name": "TimeReaderNumpy",
          "apply_scalings": true,
          "extension": ".numpy"
        }
      ],
      "type": "array",
      "items": {
        "$ref": "#/definitions/TimeReader"
      }
    }
  }
}

```

(continues on next page)

(continued from previous page)

```

    }
  },
  "time_processors": {
    "title": "Time Processors",
    "default": [
      {
        "name": "InterpolateNans"
      },
      {
        "name": "RemoveMean"
      }
    ],
    "type": "array",
    "items": {
      "$ref": "#/definitions/TimeProcess"
    }
  },
  "dec_setup": {
    "title": "Dec Setup",
    "default": {
      "name": "DecimationSetup",
      "n_levels": 8,
      "per_level": 5,
      "min_samples": 256,
      "div_factor": 2,
      "eval_freqs": null
    },
    "allOf": [
      {
        "$ref": "#/definitions/DecimationSetup"
      }
    ]
  },
  "decimator": {
    "title": "Decimator",
    "default": {
      "name": "Decimator",
      "resample": true,
      "max_single_factor": 3
    },
    "allOf": [
      {
        "$ref": "#/definitions/Decimator"
      }
    ]
  },
  "win_setup": {
    "title": "Win Setup",
    "default": {
      "name": "WindowSetup",
      "min_size": 128,
      "min_olap": 32,

```

(continues on next page)

(continued from previous page)

```

        "win_factor": 4,
        "olap_proportion": 0.25,
        "min_n_wins": 5,
        "win_sizes": null,
        "olap_sizes": null
    },
    "allOf": [
        {
            "$ref": "#/definitions/WindowSetup"
        }
    ]
},
"windower": {
    "title": "Windower",
    "default": {
        "name": "Windower"
    },
    "allOf": [
        {
            "$ref": "#/definitions/Windower"
        }
    ]
},
"fourier": {
    "title": "Fourier",
    "default": {
        "name": "FourierTransform",
        "win_fnc": [
            "kaiser",
            14
        ],
        "detrend": "linear",
        "workers": -2
    },
    "allOf": [
        {
            "$ref": "#/definitions/FourierTransform"
        }
    ]
},
"spectra_processors": {
    "title": "Spectra Processors",
    "default": [],
    "type": "array",
    "items": {
        "$ref": "#/definitions/SpectraProcess"
    }
},
"evals": {
    "title": "Evals",
    "default": {
        "name": "EvaluationFreqs"
    }
}

```

(continues on next page)

(continued from previous page)

```

    },
    "allOf": [
      {
        "$ref": "#/definitions/EvaluationFreqs"
      }
    ]
  },
  "sensor_calibrator": {
    "title": "Sensor Calibrator",
    "default": {
      "name": "SensorCalibrator",
      "chans": null,
      "readers": [
        {
          "name": "SensorCalibrationJSON",
          "extension": ".json",
          "file_str": "IC_$sensor$extension"
        }
      ]
    },
    "allOf": [
      {
        "$ref": "#/definitions/Calibrator"
      }
    ]
  },
  "tf": {
    "title": "Tf",
    "default": {
      "name": "ImpedanceTensor",
      "variation": "default",
      "out_chans": [
        "Ex",
        "Ey"
      ],
      "in_chans": [
        "Hx",
        "Hy"
      ],
      "cross_chans": [
        "Hx",
        "Hy"
      ],
      "n_out": 2,
      "n_in": 2,
      "n_cross": 2
    },
    "allOf": [
      {
        "$ref": "#/definitions/TransferFunction"
      }
    ]
  }
]

```

(continues on next page)

(continued from previous page)

```

    },
    "regression_preparer": {
      "title": "Regression Preparer",
      "default": {
        "name": "RegressionPreparerGathered"
      },
      "allOf": [
        {
          "$ref": "#/definitions/RegressionPreparerGathered"
        }
      ]
    },
    "solver": {
      "title": "Solver",
      "default": {
        "name": "SolverScikitTheilSen",
        "fit_intercept": false,
        "normalize": false,
        "n_jobs": -2,
        "max_subpopulation": 2000,
        "n_subsamples": null
      },
      "allOf": [
        {
          "$ref": "#/definitions/Solver"
        }
      ]
    }
  },
  "required": [
    "name"
  ],
  "definitions": {
    "TimeReader": {
      "title": "TimeReader",
      "description": "Base class for resistics processes\n\nResistics processes_\n→perform operations on data (including read and write\noperations). Each time a_\n→ResisticsProcess child class is run, it should add\na process record to the_\n→dataset",
      "type": "object",
      "properties": {
        "name": {
          "title": "Name",
          "type": "string"
        },
        "apply_scalings": {
          "title": "Apply Scalings",
          "default": true,
          "type": "boolean"
        },
        "extension": {
          "title": "Extension",

```

(continues on next page)



(continued from previous page)

```

        "type": "string"
    }
}
},
"TimeProcess": {
    "title": "TimeProcess",
    "description": "Parent class for processing time data",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        }
    }
},
"DecimationSetup": {
    "title": "DecimationSetup",
    "description": "Process to calculate decimation parameters\n\nParameters\n
→-----\nn_levels : int, optional\n    Number of decimation levels, by default.
→8\nper_level : int, optional\n    Number of frequencies per level, by default 5\
→nmin_samples : int, optional\n    Number of samples under which to quit.
→decimating\ndiv_factor : int, optional\n    Minimum division factor for.
→decimation, by default 2.\neval_freqs : Optional[List[float]], optional\n
→Explicit definition of evaluation frequencies as a flat list, by\n    default.
→None. Must be of size n_levels * per_level\n\nExamples\n-----\n>>> from
→resistics.decimate import DecimationSetup\n>>> dec_setup = DecimationSetup(n_
→levels=3, per_level=2)\n>>> dec_params = dec_setup.run(128)\n>>> print(dec_params.
→to_dataframe())\n
→ndecimation level\n0          0          1      fs factors increments\
→n1          16.0  11.313708  64.0          2          2\n2
→ 8.0   5.656854   32.0          4          2",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        },
        "n_levels": {
            "title": "N Levels",
            "default": 8,
            "type": "integer"
        },
        "per_level": {
            "title": "Per Level",
            "default": 5,
            "type": "integer"
        },
        "min_samples": {
            "title": "Min Samples",
            "default": 256,
            "type": "integer"
        }
    }
},

```

(continues on next page)

(continued from previous page)

```

        "div_factor": {
            "title": "Div Factor",
            "default": 2,
            "type": "integer"
        },
        "eval_freqs": {
            "title": "Eval Freqs",
            "type": "array",
            "items": {
                "type": "number"
            }
        }
    },
    "Decimator": {
        "title": "Decimator",
        "description": "Decimate the time data into multiple levels\n\nThere are_
↪ two options for decimation, using time data Resample or using\ntime data Decimate.
↪ The default is to use Resample.",
        "type": "object",
        "properties": {
            "name": {
                "title": "Name",
                "type": "string"
            },
            "resample": {
                "title": "Resample",
                "default": true,
                "type": "boolean"
            },
            "max_single_factor": {
                "title": "Max Single Factor",
                "default": 3,
                "minimum": 3,
                "type": "integer"
            }
        }
    },
    "WindowSetup": {
        "title": "WindowSetup",
        "description": "Setup WindowParameters\n\nWindowSetup outputs the_
↪ WindowParameters to use for windowing decimated\ntime data.\n\nWindow parameters_
↪ are simply the window and overlap sizes for each\ndecimation level.\n\nParameters\
↪ n-----\nmin_size : int, optional\n    Minimum window size, by default 128\
↪ nmin_olap : int, optional\n    Minimum overlap size, by default 32\nwin_factor :_
↪ int, optional\n    Window factor, by default 4. Window sizes are calculated by_
↪ sampling\n    frequency / 4 to ensure sufficient frequency resolution. If the\n_
↪ sampling frequency is small, window size will be adjusted to\n    min_size\nolap_
↪ proportion : float, optional\n    The proportion of the window size to use as the_
↪ overlap, by default\n    0.25. For example, for a window size of 128, the overlap_
↪ would be\n    0.25 * 128 = 32\nmin_n_wins : int, optional\n    The minimum number_
↪ of windows needed in a decimation level, by\n    default 5\nwin_sizes :_

```

(continues on next page)

(continued from previous page)

```

→Optional[List[int]], optional\n    Explicit define window sizes, by default None.
→Must have the same\n    length as number of decimation levels\nolap_sizes :
→Optional[List[int]], optional\n    Explicitly define overlap sizes, by default
→None. Must have the same\n    length as number of decimation levels\n\nExamples\n
→-----\nGenerate decimation and windowing parameters for data sampled at 0.05 Hz
→or\n20 seconds sampling period\n\n>>> from resistics.decimate import
→DecimationSetup\n>>> from resistics.window import WindowSetup\n>>> dec_params =
→DecimationSetup(n_levels=3, per_level=3).run(0.05)\n>>> dec_params.summary()\n{\n
→  'fs': 0.05,\n    'n_levels': 3,\n    'per_level': 3,\n    'min_samples': 256,\n
→n    'eval_freqs': [\n        0.0125,\n        0.008838834764831844,\n        0.
→00625,\n        0.004419417382415922,\n        0.003125,\n        0.
→002209708691207961,\n        0.0015625,\n        0.0011048543456039805,\n
→0.00078125\n    ],\n    'dec_factors': [1, 2, 8],\n    'dec_increments': [1, 2,
→4],\n    'dec_fs': [0.05, 0.025, 0.00625]\n}\n>>> win_params = WindowSetup().
→run(dec_params.n_levels, dec_params.dec_fs)\n>>> win_params.summary()\n{\n    'n_
→levels': 3,\n    'min_n_wins': 5,\n    'win_sizes': [128, 128, 128],\n    'olap_
→sizes': [32, 32, 32]\n}\n\nWindow parameters can also be explicitly defined\n\n>>>
→ from resistics.decimate import DecimationSetup\n>>> from resistics.window import
→WindowSetup\n>>> dec_setup = DecimationSetup(n_levels=3, per_level=3)\n>>> dec_
→params = dec_setup.run(0.05)\n>>> win_setup = WindowSetup(win_sizes=[1000, 578,
→104])\n>>> win_params = win_setup.run(dec_params.n_levels, dec_params.dec_fs)\n>>>
→ win_params.summary()\n{\n    'n_levels': 3,\n    'min_n_wins': 5,\n    'win_sizes
→': [1000, 578, 104],\n    'olap_sizes': [250, 144, 32]\n}\n\nWhen providing
→explicit window and overlap sizes, the size of the overlap\nis expected to be
→less than the size of the window\n\n>>> from resistics.decimate import
→DecimationSetup\n>>> from resistics.window import WindowSetup\n>>> dec_setup =
→DecimationSetup(n_levels=3, per_level=3)\n>>> dec_params = dec_setup.run(0.05)\n>>
→> win_setup = WindowSetup(win_sizes=[1000, 578, 104], olap_sizes=[1001, 600, 25])\n
→>>> win_params = win_setup.run(dec_params.n_levels, dec_params.dec_fs)\n
→nTraceback (most recent call last):\n...\nValueError: Invalid overlaps found [
→True True False]",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        },
        "min_size": {
            "title": "Min Size",
            "default": 128,
            "type": "integer"
        },
        "min_olap": {
            "title": "Min Olap",
            "default": 32,
            "type": "integer"
        },
        "win_factor": {
            "title": "Win Factor",
            "default": 4,
            "type": "integer"
        }
    },

```

(continues on next page)

(continued from previous page)

```

        "olap_proportion": {
            "title": "Olap Proportion",
            "default": 0.25,
            "type": "number"
        },
        "min_n_wins": {
            "title": "Min N Wins",
            "default": 5,
            "type": "integer"
        },
        "win_sizes": {
            "title": "Win Sizes",
            "type": "array",
            "items": {
                "type": "integer"
            }
        },
        "olap_sizes": {
            "title": "Olap Sizes",
            "type": "array",
            "items": {
                "type": "integer"
            }
        }
    },
    "Windower": {
        "title": "Windower",
        "description": "Windows DecimatedData\n\nThis is the primary window making_
→process for resistics and should be used\nwhen alignment of windows with a site_
→or across sites is required.\n\nThis method uses numpy striding to produce window_
→views into the decimated\ndata.\n\nSee Also\n-----\nWindowerTarget : A_
→windower to make a target number of windows\n\nExamples\n-----\n\nThe Windower_
→windows a DecimatedData object given a reference time and some\nwindow parameters.
→\n\nThere's quite a few imports needed for this example. Begin by doing the\
→nimports, defining a reference time and generating random decimated data.\n\n>>>_
→from resistics.sampling import to_datetime\n>>> from resistics.testing import_
→decimated_data_linear\n>>> from resistics.window import WindowSetup, Windower\n>>>
→dec_data = decimated_data_linear(fs=128)\n>>> ref_time = dec_data.metadata.first_
→time\n>>> print(dec_data.to_string())\n<class 'resistics.decimate.DecimatedData'>\n
→n      fs      dt  n_samples      first_time
→last_time\nlevel\n0      2048.0  0.000488      16384  2021-01-01 00:00:00  2021-
→01-01 00:00:07.99951171875\n1      512.0  0.001953      4096  2021-01-01_
→00:00:00      2021-01-01 00:00:07.998046875\n2      128.0  0.007812      1024 _
→2021-01-01 00:00:00      2021-01-01 00:00:07.9921875\n\nNext, initialise the_
→window parameters. For this example, use small windows,\nwhich will make_
→inspecting them easier.\n\n>>> win_params = WindowSetup(win_sizes=[16,16,16], min_
→olap=4).run(dec_data.metadata.n_levels, dec_data.metadata.fs)\n>>> win_params.
→summary()\n\n      'n_levels': 3,\n      'min_n_wins': 5,\n      'win_sizes': [16, 16,_
→16],\n      'olap_sizes': [4, 4, 4]\n}\n\nPerform the windowing. This actually_
→creates views into the decimated data\nusing the numpy.lib.stride_tricks.sliding_
→window_view function. The shape\nfor a data array at a decimation level is: n_

```

(continues on next page)

(continued from previous page)

```

→wins x n_chans x win_size. The information about each level is also in the
→levels_metadata attribute of WindowedMetadata.
>>> win_data = Windower().
run(ref_time, win_params, dec_data)
>>> win_data.data[0].shape
(1365, 2, 16)
> for level_metadata in win_data.metadata.levels_metadata:
    level_
metadata.summary()
{
  'fs': 2048.0,
  'n_wins': 1365,
  'win_size': 16,
  'olap_size': 4,
  'index_offset': 0
}
{
  'fs': 512.0,
  'n_wins': 341,
  'win_size': 16,
  'olap_size': 4,
  'index_offset': 0
}
{
  'fs': 128.0,
  'n_wins': 85,
  'win_size': 16,
  'olap_size': 4,
  'index_offset': 0
}
Let's look at an example of data from the first
decimation level for the first channel. This is simply a linear set of data
ranging from 0...16_383.
>>> dec_data.data[0][0]
array([ 0, 1, 2, ..., 16381, 16382, 16383])
Inspecting the first few windows shows they are as
expected including the noverlap.
>>> win_data.data[0][0, 0]
array([ 0, 1, 2, 3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15])
>>> win_data.data[0][1, 0]
array([12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27])
>>> win_data.data[0][2, 0]
array([24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39]),
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        }
    }
},
    "FourierTransform": {
        "title": "FourierTransform",
        "description": "Perform a Fourier transform of the windowed data. The
→processor is inspired by the scipy.signal.stft function which performs
→process and involves a Fourier transform along the last axis of the windowed
→data.
Parameters
-----
win_func : Union[str, Tuple[str, float]]
    The window to use before performing the FFT, by default ("kaiser", 14)
detrend : Union[str, None]
    Type of detrending to apply before performing FFT, by
→default linear
    detrend. Setting to None will not apply any detrending to the
→data prior
    to the FFT
workers : int
    The number of CPUs to use, by
→default max - 2
Examples
-----
This example will get periodic decimated
→data, perform windowing and run the Fourier transform on the windowed data.
..
plot::
    :width: 90%
>>> import matplotlib.pyplot as plt
>>>
import numpy as np
>>> from resistics.testing import decimated_data_periodic
>>> from resistics.window import WindowSetup, Windower
>>> from
resistics.spectra import FourierTransform
>>> frequencies = {"chan1": [870,
→590, 110, 32, 12], "chan2": [480, 375, 210, 60, 45]}
>>> dec_data =
decimated_data_periodic(frequencies, fs=128)
>>> dec_data.metadata.chans
['chan1', 'chan2']
>>> print(dec_data.to_string())
<class 'resistics.
→decimate.DecimatedData'>
fs      dt  n_samples      first_
time      last_time
level 0      2048.0 0.000488
→16384 2021-01-01 00:00:00 2021-01-01 00:00:07.99951171875
1      512.0
→0.001953      4096 2021-01-01 00:00:00 2021-01-01 00:00:07.998046875
2
→128.0 0.007812      1024 2021-01-01 00:00:00 2021-01-01 00:00:07.
→9921875
Perform the windowing
>>> win_params = WindowSetup().
run(dec_data.metadata.n_levels, dec_data.metadata.fs)
>>> win_data =
Windower().run(dec_data.metadata.first_time, win_params, dec_data)
And

```

(continues on next page)

(continued from previous page)

```

→ then the Fourier transform. By default, the data will be (linearly)\n
→ detrended and multiplied by a Kaiser window prior to the Fourier\n transform\n
→ \n >>> spec_data = FourierTransform().run(win_data)\n\n For plotting of\n
→ magnitude, let's stack the spectra\n\n >>> freqs_0 = spec_data.metadata.levels_\n
→ metadata[0].freqs\n >>> data_0 = np.absolute(spec_data.data[0]).mean(axis=0)\n
→ \n >>> freqs_1 = spec_data.metadata.levels_metadata[1].freqs\n >>> data_1 = np.\n
→ absolute(spec_data.data[1]).mean(axis=0)\n >>> freqs_2 = spec_data.metadata.\n
→ levels_metadata[2].freqs\n >>> data_2 = np.absolute(spec_data.data[2]).\n
→ mean(axis=0)\n\n Now plot\n\n >>> plt.subplot(3,1,1) # doctest: +SKIP\n >\n
→ >>> plt.plot(freqs_0, data_0[0], label="chan1") # doctest: +SKIP\n >>> plt.\n
→ plot(freqs_0, data_0[1], label="chan2") # doctest: +SKIP\n >>> plt.grid()\n
→ \n >>> plt.title("Decimation level 0") # doctest: +SKIP\n >>> plt.legend() #\n
→ doctest: +SKIP\n >>> plt.subplot(3,1,2) # doctest: +SKIP\n >>> plt.\n
→ plot(freqs_1, data_1[0], label="chan1") # doctest: +SKIP\n >>> plt.\n
→ plot(freqs_1, data_1[1], label="chan2") # doctest: +SKIP\n >>> plt.grid()\n
→ \n >>> plt.title("Decimation level 1") # doctest: +SKIP\n >>> plt.legend() #\n
→ doctest: +SKIP\n >>> plt.subplot(3,1,3) # doctest: +SKIP\n >>> plt.\n
→ plot(freqs_2, data_2[0], label="chan1") # doctest: +SKIP\n >>> plt.\n
→ plot(freqs_2, data_2[1], label="chan2") # doctest: +SKIP\n >>> plt.grid()\n
→ \n >>> plt.title("Decimation level 2") # doctest: +SKIP\n >>> plt.legend() #\n
→ doctest: +SKIP\n >>> plt.xlabel("Frequency") # doctest: +SKIP\n >>> plt.\n
→ tight_layout() # doctest: +SKIP\n >>> plt.show() # doctest: +SKIP",
    "type": "object",
    "properties": {
      "name": {
        "title": "Name",
        "type": "string"
      },
      "win_fnc": {
        "title": "Win Fnc",
        "default": [
          "kaiser",
          14
        ],
        "anyOf": [
          {
            "type": "string"
          },
          {
            "type": "array",
            "minItems": 2,
            "maxItems": 2,
            "items": [
              {
                "type": "string"
              },
              {
                "type": "number"
              }
            ]
          }
        ]
      }
    ]
  }
]

```

(continues on next page)

(continued from previous page)

```

    },
    "detrend": {
        "title": "Detrend",
        "default": "linear",
        "type": "string"
    },
    "workers": {
        "title": "Workers",
        "default": -2,
        "type": "integer"
    }
}
},
"SpectraProcess": {
    "title": "SpectraProcess",
    "description": "Parent class for spectra processes",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        }
    }
}
},
"EvaluationFreqs": {
    "title": "EvaluationFreqs",
    "description": "Calculate the spectra values at the evaluation frequencies\
→n\nThis is done using linear interpolation in the complex domain\n\nExample\n-----
→--\n
→The example will show interpolation to evaluation frequencies on a very\
→simple example. Begin by generating some example spectra data.\n\n>>> from
→resistics.decimate import DecimationSetup\n>>> from resistics.spectra import
→EvaluationFreqs\n>>> from resistics.testing import spectra_data_basic\n>>> spec_
→data = spectra_data_basic()\n>>> spec_data.metadata.n_levels\n1\n>>> spec_data.
→metadata.chans\n['chan1']\n>>> spec_data.metadata.levels_metadata[0].summary()\n{
→n    'fs': 180.0,\n    'n_wins': 2,\n    'win_size': 20,\n    'olap_size': 5,\n
→    'index_offset': 0,\n    'n_freqs': 10,\n    'freqs': [0.0, 10.0, 20.0, 30.0, 40.
→0, 50.0, 60.0, 70.0, 80.0, 90.0]\n}\n\nThe spectra data has only a single channel
→and a single level which has 2\nwindows. Now define our evaluation frequencies.\n
→\n>>> eval_freqs = [1, 12, 23, 34, 45, 56, 67, 78, 89]\n>>> dec_setup =
→DecimationSetup(n_levels=1, per_level=9, eval_freqs=eval_freqs)\n>>> dec_params =
→dec_setup.run(spec_data.metadata.fs[0])\n>>> dec_params.summary()\n{\n    'fs':
→180.0,\n    'n_levels': 1,\n    'per_level': 9,\n    'min_samples': 256,\n
→    'eval_freqs': [1.0, 12.0, 23.0, 34.0, 45.0, 56.0, 67.0, 78.0, 89.0],\n    'dec_
→factors': [1],\n    'dec_increments': [1],\n    'dec_fs': [180.0]\n}\n\nNow
→calculate the spectra at the evaluation frequencies\n\n>>> eval_data =
→EvaluationFreqs().run(dec_params, spec_data)\n>>> eval_data.metadata.levels_
→metadata[0].summary()\n{\n    'fs': 180.0,\n    'n_wins': 2,\n    'win_size': 20,\n
→    'olap_size': 5,\n    'index_offset': 0,\n    'n_freqs': 9,\n    'freqs': [1.
→0, 12.0, 23.0, 34.0, 45.0, 56.0, 67.0, 78.0, 89.0]\n}\n\nTo double check
→everything is as expected, let's compare the data. Comparing\nwindow 1 gives\n\n>>
→print(spec_data.data[0][0, 0])\n[0.+0.j 1.+1.j 2.+2.j 3.+3.j 4.+4.j 5.+5.j 6.+6.
→j 7.+7.j 8.+8.j 9.+9.j]\n>>> print(eval_data.data[0][0, 0])\n[0.1+0.1j 1.2+1.2j 2.

```

(continues on next page)

(continued from previous page)

```

↪3+2.3j 3.4+3.4j 4.5+4.5j 5.6+5.6j 6.7+6.7j 7.8+7.8j\n 8.9+8.9j]\n\nAnd window 2\n\
↪n>>> print(spec_data.data[0][1, 0])\n[-1. +1.j 0. +2.j 1. +3.j 2. +4.j 3. +5.
↪j 4. +6.j 5. +7.j 6. +8.j\n 7. +9.j 8.+10.j]\n>>> print(eval_data.data[0][1,
↪0])\n[-0.9+1.1j 0.2+2.2j 1.3+3.3j 2.4+4.4j 3.5+5.5j 4.6+6.6j 5.7+7.7j\n 6.
↪8+8.8j 7.9+9.9j]",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        }
    },
    "Calibrator": {
        "title": "Calibrator",
        "description": "Parent class for a calibrator",
        "type": "object",
        "properties": {
            "name": {
                "title": "Name",
                "type": "string"
            },
            "chans": {
                "title": "Chans",
                "type": "array",
                "items": {
                    "type": "string"
                }
            }
        }
    },
    "TransferFunction": {
        "title": "TransferFunction",
        "description": "Define a generic transfer function\n\nThis class is a
↪describes generic transfer function, including:\n\n- The output channels for the
↪transfer function\n- The input channels for the transfer function\n- The cross
↪channels for the transfer function\n\nThe cross channels are the channels that
↪will be used to calculate out the\ncross powers for the regression.\n\nThis
↪generic parent class has no implemented plotting function. However,\nchild
↪classes may have a plotting function as different transfer functions\nmay need
↪different types of plots.\n\n.. note::\n\n    Users interested in writing a
↪custom transfer function should inherit\n    from this generic Transfer function\
↪\n\nSee Also\n-----\nImpandanceTensor : Transfer function for the MT impedance
↪tensor\nTipper : Transfer function for the MT tipper\n\nExamples\n-----\nA
↪generic example\n\n>>> from resistics.transfunc import TransferFunction\n>>> tf =
↪TransferFunction(variation="example", out_chans=["bye", "see you", "ciao\
↪"], in_chans=["hello", "hi_there"])\n>>> print(tf.to_string())\n| bye
↪| bye_hello      bye_hi_there      | | hello      |\n| see you  | = | see you_
↪hello      see you_hi_there  | | hi_there |\n| ciao      | | ciao_hello
↪ciao_hi_there      |\n\nCombining the impedance tensor and the tipper into one
↪TransferFunction\n\n>>> tf = TransferFunction(variation="combined", out_chans=[
↪"Ex", "Ey"], in_chans=["Hx", "Hy", "Hz"])\n>>> print(tf.to_string())\n|

```

(continues on next page)



(continued from previous page)

```

↪Ex |      | Ex_Hx Ex_Hy Ex_Hz | | Hx |\n| Ey | = | Ey_Hx Ey_Hy Ey_Hz | | Hy |\n
↪      | Hz |",
    "type": "object",
    "properties": {
      "name": {
        "title": "Name",
        "type": "string"
      },
      "variation": {
        "title": "Variation",
        "default": "generic",
        "maxLength": 16,
        "type": "string"
      },
      "out_chans": {
        "title": "Out Chans",
        "type": "array",
        "items": {
          "type": "string"
        }
      },
      "in_chans": {
        "title": "In Chans",
        "type": "array",
        "items": {
          "type": "string"
        }
      },
      "cross_chans": {
        "title": "Cross Chans",
        "type": "array",
        "items": {
          "type": "string"
        }
      },
      "n_out": {
        "title": "N Out",
        "type": "integer"
      },
      "n_in": {
        "title": "N In",
        "type": "integer"
      },
      "n_cross": {
        "title": "N Cross",
        "type": "integer"
      }
    },
    "required": [
      "out_chans",
      "in_chans"
    ]
  ]

```

(continues on next page)

(continued from previous page)

```

    },
    "RegressionPreparerGathered": {
        "title": "RegressionPreparerGathered",
        "description": "Regression preparer for gathered data\n\nIn nearly all
↪ cases, this is the regresson preparer to use. As input, it\nrequires GatheredData.
↪",
        "type": "object",
        "properties": {
            "name": {
                "title": "Name",
                "type": "string"
            }
        }
    },
    "Solver": {
        "title": "Solver",
        "description": "General resistics solver",
        "type": "object",
        "properties": {
            "name": {
                "title": "Name",
                "type": "string"
            }
        }
    }
}

```

**field name:** `str` [Required]

The name of the configuration

**field time\_readers:** `List[TimeReader]` = [TimeReaderAscii(name='TimeReaderAscii', apply\_scalings=True, extension='.txt', delimiter=None, n\_header=0), TimeReaderNumpy(name='TimeReaderNumpy', apply\_scalings=True, extension='.npy')]

Time readers in the configuration

**field time\_processors:** `List[TimeProcess]` = [InterpolateNans(name='InterpolateNans'), RemoveMean(name='RemoveMean')]

List of time processors to run

**field dec\_setup:** `DecimationSetup` = DecimationSetup(name='DecimationSetup', n\_levels=8, per\_level=5, min\_samples=256, div\_factor=2, eval\_freqs=None)

Process to calculate decimation parameters

**field decimator:** `Decimator` = Decimator(name='Decimator', resample=True, max\_single\_factor=3)

Process to decimate time data

**field win\_setup:** `WindowSetup` = WindowSetup(name='WindowSetup', min\_size=128, min\_olap=32, win\_factor=4, olap\_proportion=0.25, min\_n\_wins=5, win\_sizes=None, olap\_sizes=None)

Process to calculate windowing parameters

**field windower:** *Windower* = Windower(name='Windower')

Process to window the decimated data

**field fourier:** *FourierTransform* = FourierTransform(name='FourierTransform', win\_fnc=('kaiser', 14), detrend='linear', workers=-2)

Process to perform the fourier transform

**field spectra\_processors:** *List[SpectraProcess]* = []

List of processors to run on spectra data

**field evals:** *EvaluationFreqs* = EvaluationFreqs(name='EvaluationFreqs')

Process to get the spectra data at the evaluation frequencies

**field sensor\_calibrator:** *Calibrator* = SensorCalibrator(name='SensorCalibrator', chans=None, readers=[SensorCalibrationJSON(name='SensorCalibrationJSON', extension='.json', file\_str='IC\_\$sensor\$extension')])

The sensor calibrator and associated calibration file readers

**field tf:** *TransferFunction* = ImpedanceTensor(name='ImpedanceTensor', variation='default', out\_chans=['Ex', 'Ey'], in\_chans=['Hx', 'Hy'], cross\_chans=['Hx', 'Hy'], n\_out=2, n\_in=2, n\_cross=2)

The transfer function to solve

**field regression\_preparer:** *RegressionPreparerGathered* = RegressionPreparerGathered(name='RegressionPreparerGathered')

Process to prepare linear equations

**field solver:** *Solver* = SolverScikitTheilSen(name='SolverScikitTheilSen', fit\_intercept=False, normalize=False, n\_jobs=-2, max\_subpopulation=2000, n\_subsamples=None)

The solver to use to estimate the regression parameters

`resistics.config.get_default_configuration()` → *Configuration*

Get the default configuration

## resistics.decimate module

Module for time data decimation including classes and for the following

- Definition of DecimationParameters
- Performing decimation on time data

`resistics.decimate.get_eval_freqs_min(fs: float, f_min: float) → ndarray`

Calculate evaluation frequencies with minimum allowable frequency

Highest frequency is nyquist / 4

### Parameters

- **fs** (*float*) – Sampling frequency
- **f\_min** (*float*) – Minimum allowable frequency

### Returns

Array of evaluation frequencies

### Return type

np.ndarray

**Raises**

**ValueError** – If `f_min <= 0`

**Examples**

```
>>> from resisticks.decimate import get_eval_freqs_min
>>> fs = 256
>>> get_eval_freqs_min(fs, 30)
array([64.          , 45.254834, 32.          ])
>>> get_eval_freqs_min(fs, 128)
Traceback (most recent call last):
...
ValueError: Minimum frequency 128 must be > 64.0
```

`resisticks.decimate.get_eval_freqs_size(fs: float, n_freqs: int) → ndarray`

Calculate evaluation frequencies with maximum size

Highest frequency is nyquist/4

**Parameters**

- **fs** (*float*) – Sampling frequency
- **n\_freqs** (*int*) – Number of evaluation frequencies

**Returns**

Array of evaluation frequencies

**Return type**

`np.ndarray`

**Examples**

```
>>> from resisticks.decimate import get_eval_freqs_size
>>> fs = 256
>>> n_freqs = 3
>>> get_eval_freqs_size(fs, n_freqs)
array([64.          , 45.254834, 32.          ])
```

`resisticks.decimate.get_eval_freqs(fs: float, f_min: float | None = None, n_freqs: int | None = None) → ndarray`

Get evaluation frequencies either based on size or a minimum frequency

**Parameters**

- **fs** (*float*) – Sampling frequency Hz
- **f\_min** (*Optional[float]*, *optional*) – Minimum cutoff for evaluation frequencies, by default `None`
- **n\_freqs** (*Optional[int]*, *optional*) – Number of evaluation frequencies, by default `None`

**Returns**

Evaluation frequencies array

**Return type**

np.ndarray

**Raises****ValueError** – ValueError if both `f_min` and `n_freqs` are None**Examples**

```
>>> from resisticks.decimate import get_eval_freqs
>>> get_eval_freqs(256, f_min=30)
array([64.          , 45.254834, 32.          ])
>>> get_eval_freqs(256, n_freqs=3)
array([64.          , 45.254834, 32.          ])
```

**pydantic model** `resisticks.decimate.DecimationParameters`Bases: `ResisticksModel`

Decimation parameters

**Parameters**

- **fs** (*float*) – Sampling frequency Hz
- **n\_levels** (*int*) – Number of levels
- **per\_level** (*int*) – Evaluation frequencies per level
- **min\_samples** (*int*) – Number of samples to under which to quit decimating
- **eval\_df** (*pd.DataFrame*) – The DataFrame with the decimation information

**Examples**

```
>>> from resisticks.decimate import DecimationSetup
>>> dec_setup = DecimationSetup(n_levels=3, per_level=2)
>>> dec_params = dec_setup.run(128)
>>> type(dec_params)
<class 'resisticks.decimate.DecimationParameters'>
>>> print(dec_params.to_dataframe())
```

	0	1	fs	factors	increments
decimation level					
0	32.0	22.627417	128.0	1	1
1	16.0	11.313708	64.0	2	2
2	8.0	5.656854	32.0	4	2

```
>>> dec_params[2]
[8.0, 5.65685424949238]
>>> dec_params[2,1]
5.65685424949238
>>> dec_params.get_total_factor(2)
4
>>> dec_params.get_incremental_factor(2)
2
```

```

{
  "title": "DecimationParameters",
  "description": "Decimation parameters\n\nParameters\n-----\nfs : float\n↳ Sampling frequency Hz\nn_levels : int\n  Number of levels\nper_level : int\n↳ Evaluation frequencies per level\nmin_samples : int\n  Number of samples to\n↳ under which to quit decimating\nneval_df : pd.DataFrame\n  The DataFrame with\n↳ the decimation information\n\nExamples\n-----\n>>> from resistics.decimate\n↳ import DecimationSetup\n>>> dec_setup = DecimationSetup(n_levels=3, per_level=2)\n↳ \n>>> dec_params = dec_setup.run(128)\n>>> type(dec_params)\n<class 'resistics.\n↳ decimate.DecimationParameters'\n>>> print(dec_params.to_dataframe())\n↳
    0      1      fs  factors  increments\ndecimation level\n0
↳   32.0  22.627417  128.0      1      1\n1      16.0  11.
↳  313708  64.0      2      2\n2      8.0  5.656854  32.0
↳   4      2\n>>> dec_params[2]\n[8.0, 5.65685424949238]\n>>> dec_params[2,1]\n5.65685424949238\n>>> dec_params.get_total_factor(2)\n4\n>>> dec_params.get_
↳ incremental_factor(2)\n2",
  "type": "object",
  "properties": {
    "fs": {
      "title": "Fs",
      "type": "number"
    },
    "n_levels": {
      "title": "N Levels",
      "type": "integer"
    },
    "per_level": {
      "title": "Per Level",
      "type": "integer"
    },
    "min_samples": {
      "title": "Min Samples",
      "exclusiveMinimum": 0,
      "type": "integer"
    },
    "eval_freqs": {
      "title": "Eval Freqs",
      "type": "array",
      "items": {
        "type": "number"
      }
    },
    "dec_factors": {
      "title": "Dec Factors",
      "type": "array",
      "items": {
        "type": "integer"
      }
    },
    "dec_increments": {
      "title": "Dec Increments",
      "type": "array",

```

(continues on next page)

(continued from previous page)

```

        "items": {
            "type": "integer"
        },
        "dec_fs": {
            "title": "Dec Fs",
            "type": "array",
            "items": {
                "type": "number"
            }
        }
    },
    "required": [
        "fs",
        "n_levels",
        "per_level",
        "min_samples",
        "eval_freqs",
        "dec_factors"
    ]
}

```

field fs: float [Required]

field n\_levels: int [Required]

field per\_level: int [Required]

field min\_samples: PositiveInt [Required]

#### Constraints

- exclusiveMinimum = 0

field eval\_freqs: List[float] [Required]

field dec\_factors: List[int] [Required]

field dec\_increments: List[int] | None = None

#### Validated by

- set\_dec\_increments

field dec\_fs: List[float] | None = None

#### Validated by

- set\_dec\_fs

check\_level(level: int)

Check level

check\_eval\_idx(idx: int)

Check evaluation frequency index

**get\_eval\_freqs**(*level: int*) → List[float]

Get the evaluation frequencies for a level

**Parameters**

**level** (*int*) – The decimation level

**Returns**

List of evaluation frequencies

**Return type**

List[float]

**get\_eval\_freq**(*level: int, idx: int*) → float

Get an evaluation frequency

**Parameters**

- **level** (*int*) – The level
- **idx** (*int*) – Evaluation frequency index

**Returns**

The evaluation frequency

**Return type**

float

**get\_fs**(*level: int*) → float

Get sampling frequency for level

**Parameters**

**level** (*int*) – The decimation level

**Returns**

Sampling frequency Hz

**Return type**

float

**get\_total\_factor**(*level: int*) → int

Get total decimation factor for a level

**Parameters**

**level** (*int*) – The level

**Returns**

The decimation factor

**Return type**

int

**get\_incremental\_factor**(*level: int*) → int

Get incremental decimation factor

**Parameters**

**level** (*int*) – The level

**Returns**

The incremental decimation factor

**Return type**

int



`to_numpy()` → `ndarray`

Get evaluation frequencies as a 2-D array

`to_dataframe()` → `DataFrame`

Provide decimation parameters as DataFrame

**pydantic model** `resistics.decimate.DecimationSetup`

Bases: `ResisticsProcess`

Process to calculate decimation parameters

#### Parameters

- `n_levels` (`int`, `optional`) – Number of decimation levels, by default 8
- `per_level` (`int`, `optional`) – Number of frequencies per level, by default 5
- `min_samples` (`int`, `optional`) – Number of samples under which to quit decimating
- `div_factor` (`int`, `optional`) – Minimum division factor for decimation, by default 2.
- `eval_freqs` (`Optional[List[float]]`, `optional`) – Explicit definition of evaluation frequencies as a flat list, by default None. Must be of size `n_levels * per_level`

#### Examples

```
>>> from resistics.decimate import DecimationSetup
>>> dec_setup = DecimationSetup(n_levels=3, per_level=2)
>>> dec_params = dec_setup.run(128)
>>> print(dec_params.to_dataframe())
```

	0	1	fs	factors	increments
decimation level					
0	32.0	22.627417	128.0	1	1
1	16.0	11.313708	64.0	2	2
2	8.0	5.656854	32.0	4	2

```
{
  "title": "DecimationSetup",
  "description": "Process to calculate decimation parameters\n\nParameters\n-----\n\n---\nn_levels : int, optional\n    Number of decimation levels, by default 8\nper_level : int, optional\n    Number of frequencies per level, by default 5\nmin_samples : int, optional\n    Number of samples under which to quit decimating\n\ndiv_factor : int, optional\n    Minimum division factor for decimation, by default 2.\neval_freqs : Optional[List[float]], optional\n    Explicit definition of evaluation frequencies as a flat list, by default None. Must be of size n_levels * per_level\n\nExamples\n-----\n\n>>> from resistics.decimate import DecimationSetup\n>>> dec_setup = DecimationSetup(n_levels=3, per_level=2)\n>>> dec_params = dec_setup.run(128)\n>>> print(dec_params.to_dataframe())\n\n   0      1    fs  factors  increments\n0  32.0  22.627417  128.0      1          1\n1  16.0  11.313708   64.0      2          2\n2   8.0   5.656854   32.0      4          2\n\n  "type": "object",
  "properties": {
    "name": {
```

(continues on next page)

(continued from previous page)

```

        "title": "Name",
        "type": "string"
    },
    "n_levels": {
        "title": "N Levels",
        "default": 8,
        "type": "integer"
    },
    "per_level": {
        "title": "Per Level",
        "default": 5,
        "type": "integer"
    },
    "min_samples": {
        "title": "Min Samples",
        "default": 256,
        "type": "integer"
    },
    "div_factor": {
        "title": "Div Factor",
        "default": 2,
        "type": "integer"
    },
    "eval_freqs": {
        "title": "Eval Freqs",
        "type": "array",
        "items": {
            "type": "number"
        }
    }
}

```

**field** `n_levels`: `int` = 8

**field** `per_level`: `int` = 5

**field** `min_samples`: `int` = 256

**field** `div_factor`: `int` = 2

**field** `eval_freqs`: `List[float] | None` = None

**run**(*fs*: *float*) → *DecimationParameters*

Run DecimationSetup

#### Parameters

**fs** (*float*) – Sampling frequency, Hz

#### Returns

Decimation parameterisation

#### Return type

*DecimationParameters*

**pydantic model** `resistics.decimate.DecimatedLevelMetadata`Bases: `Metadata`

Metadata for a decimation level

```
{
  "title": "DecimatedLevelMetadata",
  "description": "Metadata for a decimation level",
  "type": "object",
  "properties": {
    "fs": {
      "title": "Fs",
      "type": "number"
    },
    "n_samples": {
      "title": "N Samples",
      "type": "integer"
    },
    "first_time": {
      "title": "First Time",
      "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
      "examples": [
        "2021-01-01 00:00:00.000061_035156_250000_000000"
      ]
    },
    "last_time": {
      "title": "Last Time",
      "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
      "examples": [
        "2021-01-01 00:00:00.000061_035156_250000_000000"
      ]
    }
  },
  "required": [
    "fs",
    "n_samples",
    "first_time",
    "last_time"
  ]
}
```

**field** `fs`: `float` [Required]

The sampling frequency of the decimation level

**field** `n_samples`: `int` [Required]

The number of samples in the decimation level

**field** `first_time`: `HighResDateTime` [Required]

The first time in the decimation level

**Constraints**

- `pattern` = `%Y-%m-%d %H:%M:%S.%f_%o_%q_%v`
- `examples` = `['2021-01-01 00:00:00.000061_035156_250000_000000']`

field `last_time`: *HighResDateTime* [Required]

The last time in the decimation level

**Constraints**

- `pattern` = `%Y-%m-%d %H:%M:%S.%f_%o_%q_%v`
- `examples` = [`'2021-01-01 00:00:00.000061_035156_250000_000000'`]

property `dt`

pydantic model `resisticks.decimate.DecimatedMetadata`

Bases: *WriteableMetadata*

Metadata for DecimatedData

```
{
  "title": "DecimatedMetadata",
  "description": "Metadata for DecimatedData",
  "type": "object",
  "properties": {
    "file_info": {
      "$ref": "#/definitions/ResisticksFile"
    },
    "fs": {
      "title": "Fs",
      "type": "array",
      "items": {
        "type": "number"
      }
    },
    "chans": {
      "title": "Chans",
      "type": "array",
      "items": {
        "type": "string"
      }
    },
    "n_chans": {
      "title": "N Chans",
      "type": "integer"
    },
    "n_levels": {
      "title": "N Levels",
      "type": "integer"
    },
    "first_time": {
      "title": "First Time",
      "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
      "examples": [
        "2021-01-01 00:00:00.000061_035156_250000_000000"
      ]
    },
    "last_time": {
      "title": "Last Time",
      "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
```

(continues on next page)

(continued from previous page)

```

    "examples": [
      "2021-01-01 00:00:00.000061_035156_250000_000000"
    ]
  },
  "system": {
    "title": "System",
    "default": "",
    "type": "string"
  },
  "serial": {
    "title": "Serial",
    "default": "",
    "type": "string"
  },
  "wgs84_latitude": {
    "title": "Wgs84 Latitude",
    "default": -999.0,
    "type": "number"
  },
  "wgs84_longitude": {
    "title": "Wgs84 Longitude",
    "default": -999.0,
    "type": "number"
  },
  "easting": {
    "title": "Easting",
    "default": -999.0,
    "type": "number"
  },
  "northing": {
    "title": "Northing",
    "default": -999.0,
    "type": "number"
  },
  "elevation": {
    "title": "Elevation",
    "default": -999.0,
    "type": "number"
  },
  "chans_metadata": {
    "title": "Chans Metadata",
    "type": "object",
    "additionalProperties": {
      "$ref": "#/definitions/ChanMetadata"
    }
  },
  "levels_metadata": {
    "title": "Levels Metadata",
    "type": "array",
    "items": {
      "$ref": "#/definitions/DecimatedLevelMetadata"
    }
  }

```

(continues on next page)

(continued from previous page)

```

    },
    "history": {
      "title": "History",
      "default": {
        "records": []
      },
      "allOf": [
        {
          "$ref": "#/definitions/History"
        }
      ]
    },
    "required": [
      "fs",
      "chans",
      "n_levels",
      "first_time",
      "last_time",
      "chans_metadata",
      "levels_metadata"
    ],
    "definitions": {
      "ResisticsFile": {
        "title": "ResisticsFile",
        "description": "Required information for writing out a resistics file",
        "type": "object",
        "properties": {
          "created_on_local": {
            "title": "Created On Local",
            "type": "string",
            "format": "date-time"
          },
          "created_on_utc": {
            "title": "Created On Utc",
            "type": "string",
            "format": "date-time"
          },
          "version": {
            "title": "Version",
            "type": "string"
          }
        }
      },
      "ChanMetadata": {
        "title": "ChanMetadata",
        "description": "Channel metadata",
        "type": "object",
        "properties": {
          "name": {
            "title": "Name",
            "type": "string"
          }
        }
      }
    }
  },
  "ChanMetadata": {
    "title": "ChanMetadata",
    "description": "Channel metadata",
    "type": "object",
    "properties": {
      "name": {
        "title": "Name",
        "type": "string"
      }
    }
  }
}

```

(continues on next page)

(continued from previous page)

```

    },
    "data_files": {
      "title": "Data Files",
      "type": "array",
      "items": {
        "type": "string"
      }
    },
    "chan_type": {
      "title": "Chan Type",
      "type": "string"
    },
    "chan_source": {
      "title": "Chan Source",
      "type": "string"
    },
    "sensor": {
      "title": "Sensor",
      "default": "",
      "type": "string"
    },
    "serial": {
      "title": "Serial",
      "default": "",
      "type": "string"
    },
    "gain1": {
      "title": "Gain1",
      "default": 1,
      "type": "number"
    },
    "gain2": {
      "title": "Gain2",
      "default": 1,
      "type": "number"
    },
    "scaling": {
      "title": "Scaling",
      "default": 1,
      "type": "number"
    },
    "chopper": {
      "title": "Chopper",
      "default": false,
      "type": "boolean"
    },
    "dipole_dist": {
      "title": "Dipole Dist",
      "default": 1,
      "type": "number"
    },
    "sensor_calibration_file": {

```

(continues on next page)

(continued from previous page)

```

        "title": "Sensor Calibration File",
        "default": "",
        "type": "string"
    },
    "instrument_calibration_file": {
        "title": "Instrument Calibration File",
        "default": "",
        "type": "string"
    }
},
"required": [
    "name"
]
},
"DecimatedLevelMetadata": {
    "title": "DecimatedLevelMetadata",
    "description": "Metadata for a decimation level",
    "type": "object",
    "properties": {
        "fs": {
            "title": "Fs",
            "type": "number"
        },
        "n_samples": {
            "title": "N Samples",
            "type": "integer"
        },
        "first_time": {
            "title": "First Time",
            "pattern": "%Y-%m-%d %H:%M:%S.%f_o_%q_%v",
            "examples": [
                "2021-01-01 00:00:00.000061_035156_250000_000000"
            ]
        },
        "last_time": {
            "title": "Last Time",
            "pattern": "%Y-%m-%d %H:%M:%S.%f_o_%q_%v",
            "examples": [
                "2021-01-01 00:00:00.000061_035156_250000_000000"
            ]
        }
    },
    "required": [
        "fs",
        "n_samples",
        "first_time",
        "last_time"
    ]
},
"Record": {
    "title": "Record",
    "description": "Class to hold a record\n\nA record holds information about_

```

(continues on next page)



(continued from previous page)

```

→ a process that was run. It is intended to track processes applied to data,
→ allowing a process history to be saved along with any datasets.
→ -----
→ -----\nA simple example of creating a process record\n\n>>> from resistics.common
→ import Record\n>>> messages = ["message 1", "message 2"]\n>>> record =
→ Record(\n...      creator={"name": "example", "parameter1": 15},\n...
→ messages=messages,\n...      record_type="example"\n... )\n>>> record.summary()\n
→ {\n  'time_local': '...',\n  'time_utc': '...',\n  'creator': {'name':
→ 'example', 'parameter1': 15},\n  'messages': ['message 1', 'message 2'],\n
→ 'record_type': 'example'\n},
    "type": "object",
    "properties": {
      "time_local": {
        "title": "Time Local",
        "type": "string",
        "format": "date-time"
      },
      "time_utc": {
        "title": "Time Utc",
        "type": "string",
        "format": "date-time"
      },
      "creator": {
        "title": "Creator",
        "type": "object"
      },
      "messages": {
        "title": "Messages",
        "type": "array",
        "items": {
          "type": "string"
        }
      },
      "record_type": {
        "title": "Record Type",
        "type": "string"
      }
    },
    "required": [
      "creator",
      "messages",
      "record_type"
    ]
  },
  "History": {
    "title": "History",
    "description": "Class for storing processing history\n\nParameters\n-----
→ -----\nrecords : List[Record], optional\n    List of records, by default []\n\
→ nExamples\n-----\n\n>>> from resistics.testing import record_example1, record_
→ example2\n>>> from resistics.common import History\n>>> record1 = record_
→ example1()\n>>> record2 = record_example2()\n>>> history =
→ History(records=[record1, record2])\n>>> history.summary()\n{\n  'records': [\n
→    {\n      'time_local': '...',\n      'time_utc': '...',\n

```

(continues on next page)

(continued from previous page)

```

↪      'creator': {\n                'name': 'example1',\n                'a': 5,\n↪n                'b': -7.0\n                },\n                'messages': ['Message 1',\n↪'Message 2'],\n                'record_type': 'process'\n                },\n                {\n↪      'time_local': '...',\n                'time_utc': '...',\n                'creator': {\n↪      'name': 'example2',\n                'a': 'parzen',\n↪      'b': -21\n                },\n                'messages': ['Message 5', 'Message 6'],\n                'record_type': 'process'\n                }\n    },\n    "type": "object",\n    "properties": {\n        "records": {\n            "title": "Records",\n            "default": [],\n            "type": "array",\n            "items": {\n                "$ref": "#/definitions/Record"\n            }\n        }\n    }\n}\n}

```

field fs: `List[float]` [Required]

field chans: `List[str]` [Required]

field n\_chans: `int | None` = None

Validated by

- `validate_n_chans`

field n\_levels: `int` [Required]

field first\_time: `HighResDateTime` [Required]

Constraints

- `pattern` = `%Y-%m-%d %H:%M:%S.%f_%o_%q_%v`
- `examples` = `['2021-01-01 00:00:00.000061_035156_250000_000000']`

field last\_time: `HighResDateTime` [Required]

Constraints

- `pattern` = `%Y-%m-%d %H:%M:%S.%f_%o_%q_%v`
- `examples` = `['2021-01-01 00:00:00.000061_035156_250000_000000']`

field system: `str` = ''

field serial: `str` = ''

field wgs84\_latitude: `float` = -999.0

field wgs84\_longitude: `float` = -999.0

```

field easting: float = -999.0
field northing: float = -999.0
field elevation: float = -999.0
field chans_metadata: Dict[str, ChanMetadata] [Required]
field levels_metadata: List[DecimatedLevelMetadata] [Required]
field history: History = History(records=[])

```

```
class resistics.decimate.DecimatedData(metadata: DecimatedMetadata, data: Dict[int, ndarray])
```

Bases: *ResisticsData*

Data class for storing decimated data

The data for is stored in a dictionary attribute named data. The indices are integers representing the decimation level. Each decimation level is a numpy array of shape:

n\_chans x n\_samples

#### Parameters

- **metadata** (*DecimatedMetadata*) – The metadata
- **data** (*Dict[int, TimeData]*) – The decimated time data

#### Examples

```


>>> import matplotlib.pyplot as plt
>>> from resistics.testing import time_data_random
>>> from resistics.decimate import DecimationSetup, Decimator
>>> time_data = time_data_random(fs=256, n_samples=10_000)
>>> dec_params = DecimationSetup(n_levels=4, per_freq=4).run(time_data.metadata.fs)
>>> dec_data = Decimator().run(dec_params, time_data)
>>> for level_metadata in dec_data.metadata.levels_metadata:
...     level_metadata.summary()
{
  'fs': 256.0,
  'n_samples': 10000,
  'first_time': '2020-01-01 00:00:00.000000_000000_000000_000000',
  'last_time': '2020-01-01 00:00:39.058593_750000_000000_000000'
}
{
  'fs': 64.0,
  'n_samples': 2500,
  'first_time': '2020-01-01 00:00:00.000000_000000_000000_000000',
  'last_time': '2020-01-01 00:00:39.046875_000000_000000_000000'
}
{
  'fs': 8.0,
  'n_samples': 313,
  'first_time': '2020-01-01 00:00:00.000000_000000_000000_000000',
  'last_time': '2020-01-01 00:00:39.000000_000000_000000_000000'
}

```

(continues on next page)

(continued from previous page)

```
>>> for ilevel in range(0, dec_data.metadata.n_levels):
...     data = dec_data.get_level(ilevel)
...     plt.plot(dec_data.get_timestamps(ilevel), data[0], label=f"Level{ilevel}")
>>> plt.legend(loc=3)
>>> plt.tight_layout()
>>> plt.show()
```



**get\_level**(level: *int*) → ndarray

Get data for a decimation level

**Parameters**

**level** (*int*) – The level

**Returns**

The data for the decimation level

**Return type**

np.ndarray

**Raises**

**ValueError** – If level > max\_level

**get\_timestamps**(level: *int*, samples: ndarray | None = None, estimate: bool = True) → ndarray |

DatetimeIndex

Get an array of timestamps

**Parameters**

- **level** (*int*) – The decimation level
- **samples** (*Optional[np.ndarray]*, *optional*) – If provided, timestamps are only returned for the specified samples, by default None
- **estimate** (*bool*, *optional*) – Flag for using estimates instead of high precision dates, by default True

**Returns**

The return dates. This will be a numpy array of RSDatetime objects if estimate is False, else it will be a pandas DatetimeIndex

**Return type**

Union[np.ndarray, pd.DatetimeIndex]

**Raises**

**ValueError** – If the level is not within bounds

**plot**(*max\_pts: int | None = 10000*) → Figure

Plot the decimated data

**Parameters**

**max\_pts** (*Optional[int]*, *optional*) – The maximum number of points in any individual plot before applying lttbc downsampling, by default 10\_000. If set to None, no downsampling will be applied.

**Returns**

Plotly Figure

**Return type**

go.Figure

**to\_string**() → str

Class details as a string

**pydantic model** `resistics.decimate.Decimator`

Bases: `ResisticsProcess`

Decimate the time data into multiple levels

There are two options for decimation, using time data Resample or using time data Decimate. The default is to use Resample.

```
{
  "title": "Decimator",
  "description": "Decimate the time data into multiple levels\n\nThere are two_
↪options for decimation, using time data Resample or using\ntime data Decimate._
↪The default is to use Resample.",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "resample": {
      "title": "Resample",
      "default": true,
      "type": "boolean"
    }
  },
}
```

(continues on next page)

(continued from previous page)

```

    "max_single_factor": {
        "title": "Max Single Factor",
        "default": 3,
        "minimum": 3,
        "type": "integer"
    }
}

```

**field resample:** `bool = True`

Boolean flag for using resampling instead of decimation

**field max\_single\_factor:** `ConstrainedIntValue = 3`

Maximum single decimation factor, only used if resample is False

#### Constraints

- **minimum** = 3

**run**(*dec\_params*: [DecimationParameters](#), *time\_data*: [TimeData](#)) → [DecimatedData](#)

Decimate the TimeData

#### Parameters

- **dec\_params** ([DecimationParameters](#)) – The decimation parameters
- **time\_data** ([TimeData](#)) – TimeData to decimate

#### Returns

DecimatedData instance with all the decimated data

#### Return type

[DecimatedData](#)

**pydantic model** `resistics.decimate.DecimatedDataWriter`

Bases: [ResisticsWriter](#)

Writer of resistics decimated data

```

{
    "title": "DecimatedDataWriter",
    "description": "Writer of resistics decimated data",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        },
        "overwrite": {
            "title": "Overwrite",
            "default": true,
            "type": "boolean"
        }
    }
}

```

**run**(*dir\_path*: *Path*, *dec\_data*: *DecimatedData*) → *None*

Write out *DecimatedData*

#### Parameters

- **dir\_path** (*Path*) – The directory path to write to
- **dec\_data** (*DecimatedData*) – Decimated data to write out

#### Raises

**WriteError** – If unable to write to the directory

**pydantic model** *resistics.decimate.DecimatedDataReader*

Bases: *ResisticsProcess*

Reader of *resistics* decimated data

```
{
  "title": "DecimatedDataReader",
  "description": "Reader of resistics decimated data",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    }
  }
}
```

**run**(*dir\_path*: *Path*, *metadata\_only*: *bool* = *False*) → *DecimatedMetadata* | *DecimatedData*

Read *DecimatedData*

#### Parameters

- **dir\_path** (*Path*) – The directory path to read from
- **metadata\_only** (*bool*, *optional*) – Flag for getting metadata only, by default *False*

#### Returns

*DecimatedData* or *DecimatedMetadata* if *metadata\_only*

#### Return type

Union[*DecimatedMetadata*, *DecimatedData*]

#### Raises

**ReadError** – If the directory does not exist

## resistics.errors module

Module for custom *resistics* errors

**resistics.errors.path\_to\_string**(*path*: *Path*) → *str*

Convert a path to a string in a OS agnostic way

#### Parameters

**path** (*Path*) – The path to convert

#### Returns

A string for the path

**Return type**`str`**exception** `resistics.errors.PathError(path: Path)`Bases: `Exception`

Use for a general error with paths

**exception** `resistics.errors.PathNotFoundError(path: Path)`Bases: `PathError`

Use if path does not exist

**exception** `resistics.errors.NotFileError(path: Path)`Bases: `PathError`

Use if expected a file and got a directory

**exception** `resistics.errors.NotDirectoryError(path: Path)`Bases: `PathError`

Use if expected a directory and got a file

**exception** `resistics.errors.WriteError(path: Path, message: str = "")`Bases: `Exception`**exception** `resistics.errors.ReadError(path: Path, message: str = "")`Bases: `Exception`**exception** `resistics.errors.MetadataReadError(path: Path, message: str | None = None)`Bases: `Exception`

Use when failed to read a metadata

**exception** `resistics.errors.ProjectPathError(project_dir: Path, message: str)`Bases: `Exception`

Use for a general error with a project path

**exception** `resistics.errors.ProjectCreateError(project_dir: Path, message: str)`Bases: `ProjectPathError`

Use if encounter an error creating a project

**exception** `resistics.errors.ProjectLoadError(project_dir: Path, message: str)`Bases: `ProjectPathError`

Use if error on project load

**exception** `resistics.errors.MeasurementNotFoundError(site_name: str, meas_name: str)`Bases: `Exception`

Use if unable to find a measurement

**exception** `resistics.errors.SiteNotFoundError(site_name: str)`Bases: `Exception`

Use if unable to find a site

**exception** `resistics.errors.TimeDataReadError(dir_path: Path, message: str)`Bases: `Exception`

Use when encounter an error reading time series data



**exception** `resistics.errors.ChannelNotFoundError(chan: str, chans: Collection[str])`

Bases: `Exception`

Use when a channel is not found

**exception** `resistics.errors.CalibrationFileNotFound(dir_path: Path, file_paths: Path | List[Path], message: str = "")`

Bases: `Exception`

Use when calibration files are not found

**exception** `resistics.errors.CalibrationFileReadError(calibration_path: Path, message: str = "")`

Bases: `Exception`

Use if encounter an error reading a calibration file

**exception** `resistics.errors.ProcessRunError(process: str, message: str)`

Bases: `Exception`

Use when a error is encountered during a process run

## resistics.gather module

Module for gathering data that will be combined to calculate transfer functions

There are two scenarios considered here. The first is the simplest, which is quick processing outside the project environment. In this case data gathering is not complicated. This workflow does not involve a data selector, meaning only a single step is required.

- QuickGather to put together the out\_data, in\_data and cross\_data

When inside the project environment, regardless of whether it is single site or multi site processing, the workflow follows:

- Selector to select shared windows across all sites for a sampling frequency
- Gather to gather the combined evaluation frequency data

**Warning:** There may be some confusion in the code with many references to spectra data and evaluation frequency data. Evaluation frequency data, referred to below as eval\_data is actually an instance of Spectra data. However, it is named differently to highlight the fact that it is not the complete spectra data, but is actually spectra data at a reduced set of frequencies corresponding to the evaluation frequencies.

Within a project, there are separate folders for users who want to save both the full spectra data with all the frequencies as well as the evaluation frequency spectra data with the smaller subset of frequencies. Only the evaluation frequency data is required to calculate the transfer function, but the full spectral data might be useful for visualisation and analysis reasons.

`resistics.gather.get_site_evals_metadata(config_name: str, proj: Project, site_name: str, fs: float) → Dict[str, SpectraMetadata]`

Get spectra metadata for a given site and sampling frequency

### Parameters

- **config\_name** (`str`) – The configuration name to get the right data
- **proj** (`Project`) – The project instance to get the measurements
- **site\_name** (`str`) – The name of the site for which to gather the SpectraMetadata

- **fs** (*float*) – The original recording sampling frequency

**Returns**

Dictionary of measurement name to SpectraMetadata

**Return type**

Dict[str, SpectraMetadata]

`resistics.gather.get_site_level_wins(meas_metadata: Dict[str, SpectraMetadata], level: int) → Series`

Get site windows for a decimation level given a sampling frequency

**Parameters**

- **meas\_metadata** (Dict[str, SpectraMetadata]) – The measurement spectra metadata for a site
- **level** (*int*) – The decimation level

**Returns**

A series with an index of global windows for the site and values the measurements which have that global window. This is for a single decimation level

**Return type**

pd.Series

See also:

**`get_site_wins`**

Get windows for all decimation levels

**Examples**

An example getting the site windows for decimation level 0 when there are three measurements in the site.

```
>>> from resistics.testing import spectra_metadata_multilevel
>>> from resistics.gather import get_site_level_wins
>>> meas_metadata = {}
>>> meas_metadata["meas1"] = spectra_metadata_multilevel(n_wins=[3, 2, 2], index_
↳offset=[3, 2, 1])
>>> meas_metadata["meas2"] = spectra_metadata_multilevel(n_wins=[4, 3, 2], index_
↳offset=[28, 25, 22])
>>> meas_metadata["meas3"] = spectra_metadata_multilevel(n_wins=[2, 2, 1], index_
↳offset=[108, 104, 102])
>>> get_site_level_wins(meas_metadata, 0)
3      meas1
4      meas1
5      meas1
28     meas2
29     meas2
30     meas2
31     meas2
108    meas3
109    meas3
dtype: object
>>> get_site_level_wins(meas_metadata, 1)
2      meas1
3      meas1
```

(continues on next page)

(continued from previous page)

```

25     meas2
26     meas2
27     meas2
104    meas3
105    meas3
dtype: object
>>> get_site_level_wins(meas_metadata, 2)
1      meas1
2      meas1
22     meas2
23     meas2
102    meas3
dtype: object

```

`resistics.gather.get_site_wins(config_name: str, proj: Project, site_name: str, fs: float) → Dict[int, Series]`  
 Get site windows for all levels given a sampling frequency

**Parameters**

- **config\_name** (*str*) – The configuration name to get the right data
- **proj** (*Project*) – The project instance to get the measurements
- **site\_name** (*str*) – The site name
- **fs** (*float*) – The recording sampling frequency

**Returns**

Dictionary of integer to levels, with one entry for each decimation level

**Return type**

Dict[int, pd.Series]

**Raises**

**ValueError** – If no matching spectra metadata is found

**class** `resistics.gather.Selection(sites: List[Site], dec_params: DecimationParameters, tables: Dict[int, DataFrame])`

Bases: *ResisticsData*

Selections are output by the Selector. They hold information about the data that should be gathered for the regression.

**get\_n\_evals()** → int

Get the total number of evaluation frequencies

**Returns**

The total number of evaluation frequencies that can be calculated

**Return type**

int

**get\_n\_wins(level: int, eval\_idx: int) → int**

Get the number of windows for an evaluation frequency

**Parameters**

- **level** (*int*) – The decimation level
- **eval\_idx** (*int*) – The evaluation frequency index in the decimation level

**Returns**

The number of windows

**Return type**

`int`

**Raises**

**ValueError** – If the level is greater than the maximum level available

**get\_measurements**(*site*: `Site`) → `List[str]`

Get the measurement names to read from a Site

**Parameters**

**site** (`Site`) – The site for which to get the measurements

**Returns**

The measurements to read from

**Return type**

`List[str]`

**get\_eval\_freqs**() → `List[float]`

Get the evaluation frequencies

**Returns**

The evaluation frequencies as a flat list of floats

**Return type**

`List[float]`

**get\_eval\_wins**(*level*: `int`, *eval\_idx*: `int`) → `DataFrame`

Limit the level windows to the evaluation frequency

**Parameters**

- **level** (`int`) – The decimation level
- **eval\_idx** (`int`) – The evaluation frequency index in the decimation level

**Returns**

pandas DataFrame of the windows and the measurements from each site the window can be read from

**Return type**

`pd.DataFrame`

**pydantic model** `resistics.gather.Selector`

Bases: `ResisticsProcess`

The Selector takes Sites and tries to find shared windows across them. A project instance is required for the Selector to be able to find shared windows.

The Selector should be used for remote reference and intersite processing and single site processing when masks are involved.

```
{
  "title": "Selector",
  "description": "The Selector takes Sites and tries to find shared windows across_\n→them. A\nproject instance is required for the Selector to be able to find shared_\n→nwindows.\n\nThe Selector should be used for remote reference and intersite_\n→processing\nand single site processing when masks are involved.",
```

(continues on next page)

(continued from previous page)

```

    "type": "object",
    "properties": {
      "name": {
        "title": "Name",
        "type": "string"
      }
    }
  }
}

```

**run**(*config\_name*: *str*, *proj*: *Project*, *site\_names*: *List[str]*, *dec\_params*: *DecimationParameters*, *masks*: *Dict[str, str] | None = None*) → *Selection*

Run the selector

If a site repeats, the selector only considers it once. This might be the case when performing intersite or other cross site style processing.

#### Parameters

- **config\_name** (*str*) – The configuration name
- **proj** (*Project*) – The project instance
- **site\_names** (*List[str]*) – The names of the sites to get data from
- **dec\_params** (*DecimationParameters*) – The decimation parameters with number of levels etc.
- **masks** (*Optional[Dict[str, str]]*, *optional*) – Any masks to add, by default *None*

#### Returns

The Selection information defining the measurements and windows to read for each site

#### Return type

*Selection*

**pydantic model** `resistics.gather.SiteCombinedMetadata`

Bases: *WriteableMetadata*

Metadata for combined data

Combined metadata stores metadata for measurements that are combined from a single site.

```

{
  "title": "SiteCombinedMetadata",
  "description": "Metadata for combined data\n\nCombined metadata stores metadata_\n↪for measurements that are combined from\nna single site.",
  "type": "object",
  "properties": {
    "file_info": {
      "$ref": "#/definitions/ResisticsFile"
    },
    "site_name": {
      "title": "Site Name",
      "type": "string"
    },
    "fs": {

```

(continues on next page)

(continued from previous page)

```
    "title": "Fs",
    "type": "number"
  },
  "system": {
    "title": "System",
    "default": "",
    "type": "string"
  },
  "serial": {
    "title": "Serial",
    "default": "",
    "type": "string"
  },
  "wgs84_latitude": {
    "title": "Wgs84 Latitude",
    "default": -999.0,
    "type": "number"
  },
  "wgs84_longitude": {
    "title": "Wgs84 Longitude",
    "default": -999.0,
    "type": "number"
  },
  "easting": {
    "title": "Easting",
    "default": -999.0,
    "type": "number"
  },
  "northing": {
    "title": "Northing",
    "default": -999.0,
    "type": "number"
  },
  "elevation": {
    "title": "Elevation",
    "default": -999.0,
    "type": "number"
  },
  "measurements": {
    "title": "Measurements",
    "type": "array",
    "items": {
      "type": "string"
    }
  },
  "chans": {
    "title": "Chans",
    "type": "array",
    "items": {
      "type": "string"
    }
  },
}
```

(continues on next page)

(continued from previous page)

```

    "n_evals": {
      "title": "N Evals",
      "type": "integer"
    },
    "eval_freqs": {
      "title": "Eval Freqs",
      "type": "array",
      "items": {
        "type": "number"
      }
    },
    "histories": {
      "title": "Histories",
      "type": "object",
      "additionalProperties": {
        "$ref": "#/definitions/History"
      }
    }
  },
  "required": [
    "site_name",
    "fs",
    "chans",
    "n_evals",
    "eval_freqs",
    "histories"
  ],
  "definitions": {
    "ResisticsFile": {
      "title": "ResisticsFile",
      "description": "Required information for writing out a resistics file",
      "type": "object",
      "properties": {
        "created_on_local": {
          "title": "Created On Local",
          "type": "string",
          "format": "date-time"
        },
        "created_on_utc": {
          "title": "Created On Utc",
          "type": "string",
          "format": "date-time"
        },
        "version": {
          "title": "Version",
          "type": "string"
        }
      }
    }
  },
  "Record": {
    "title": "Record",
    "description": "Class to hold a record\n\nA record holds information about_"
  }

```

(continues on next page)

(continued from previous page)

```

→ a process that was run. It is intended to track processes applied to data,
→ allowing a process history to be saved along with any datasets.
→
→ -----
→ A simple example of creating a process record
→
→ >>> from resistics.common
→ import Record
→ >>> messages = ["message 1", "message 2"]
→ >>> record =
→ Record(
→     creator={"name": "example", "parameter1": 15},
→     messages=messages,
→     record_type="example"
→ )
→ >>> record.summary()
→ {
→     'time_local': '...',
→     'time_utc': '...',
→     'creator': {'name':
→ 'example', 'parameter1': 15},
→     'messages': ['message 1', 'message 2'],
→     'record_type': 'example'
→ },
→     "type": "object",
→     "properties": {
→         "time_local": {
→             "title": "Time Local",
→             "type": "string",
→             "format": "date-time"
→         },
→         "time_utc": {
→             "title": "Time Utc",
→             "type": "string",
→             "format": "date-time"
→         },
→         "creator": {
→             "title": "Creator",
→             "type": "object"
→         },
→         "messages": {
→             "title": "Messages",
→             "type": "array",
→             "items": {
→                 "type": "string"
→             }
→         },
→         "record_type": {
→             "title": "Record Type",
→             "type": "string"
→         }
→     },
→     "required": [
→         "creator",
→         "messages",
→         "record_type"
→     ]
→ },
→     "History": {
→         "title": "History",
→         "description": "Class for storing processing history
→ -----
→ records : List[Record], optional
→ List of records, by default []
→
→ Examples
→ -----
→ >>> from resistics.testing import record_example1, record_
→ example2
→ >>> from resistics.common import History
→ >>> record1 = record_
→ example1()
→ >>> record2 = record_example2()
→ >>> history =
→ History(records=[record1, record2])
→ >>> history.summary()
→ {
→     'records': [
→         {
→             'time_local': '...',
→             'time_utc': '...',

```

(continues on next page)



(continued from previous page)

```

→      'creator': {\n                'name': 'example1',\n                'a': 5,\n→n                'b': -7.0\n                },\n                'messages': ['Message 1',\n→'Message 2'],\n                'record_type': 'process'\n                },\n                {\n→      'time_local': '...',\n                'time_utc': '...',\n                'creator\n→': {\n                'name': 'example2',\n                'a': 'parzen',\n→      'b': -21\n                },\n                'messages': ['Message 5', 'Message\n→6'],\n                'record_type': 'process'\n                }\n    },\n    "type": "object",\n    "properties": {\n        "records": {\n            "title": "Records",\n            "default": [],\n            "type": "array",\n            "items": {\n                "$ref": "#/definitions/Record"\n            }\n        }\n    }\n}

```

**field site\_name:** `str` [Required]

The name of the site

**field fs:** `float` [Required]

Recording sampling frequency

**field system:** `str` = ''

The system used for recording

**field serial:** `str` = ''

Serial number of the system

**field wgs84\_latitude:** `float` = -999.0

Latitude in WGS84

**field wgs84\_longitude:** `float` = -999.0

Longitude in WGS84

**field easting:** `float` = -999.0

The easting of the site in local cartersian coordinates

**field northing:** `float` = -999.0

The northing of the site in local cartersian coordinates

**field elevation:** `float` = -999.0

The elevation of the site

**field measurements:** `List[str] | None` = None

List of measurement names that were included in the combined data

**field chans:** `List[str]` [Required]

List of channels, these are common amongst all the measurements

**field** `n_evals`: `int` [Required]

The number of evaluation frequencies

**field** `eval_freqs`: `List[float]` [Required]

The evaluation frequencies

**field** `histories`: `Dict[str, History]` [Required]

Dictionary mapping measurement name to measurement processing history

**class** `resistics.gather.SiteCombinedData`(`metadata`: `SiteCombinedMetadata`, `data`: `Dict[int, ndarray]`)

Bases: `ResisticsData`

Combined data is data that is combined from a single site for the purposes of regression.

All of the data that is combined should have the same sampling frequency, same evaluation frequencies and some shared channels.

Data is stored in the data attribute of the class. This is a dictionary mapping evaluation frequency index to data for the evaluation frequency from all windows in the site. The shape of data for a single evaluation frequency is:

`n_wins x n_chans`

The data is complex valued.

**class** `resistics.gather.GatheredData`(`out_data`: `SiteCombinedData`, `in_data`: `SiteCombinedData`,  
`cross_data`: `SiteCombinedData`)

Bases: `ResisticsData`

Class to hold data to be used in by Regression preparers

Gathered data has an `out_data`, `in_data` and `cross_data`. The important thing here is that the data is all aligned with regards to windows

**pydantic model** `resistics.gather.ProjectGather`

Bases: `ResisticsProcess`

Gather aligned data from a single or multiple sites in the project

Aligned data means that the same index of data across multiple sites points to data covering the same global window (i.e. the same time window). This is essential for calculating intersite or remote reference transfer functions.

```
{
  "title": "ProjectGather",
  "description": "Gather aligned data from a single or multiple sites in the_\nproject\n\nAligned data means that the same index of data across multiple sites_\npoints\nto data covering the same global window (i.e. the same time window). This_\nis essential for calculating intersite or remote reference transfer\nfunctions.",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    }
  }
}
```

**run**(`config_name`: `str`, `proj`: `Project`, `selection`: `Selection`, `tf`: `TransferFunction`, `out_name`: `str`, `in_name`: `str` |  
`None` = `None`, `cross_name`: `str` | `None` = `None`) → `GatheredData`

Gather data for input into the regression preparer

#### Parameters

- **config\_name** (*str*) – The config name for getting the correct evals data
- **proj** (*Project*) – The project instance
- **selection** (*Selection*) – The selection
- **tf** (*TransferFunction*) – The transfer function
- **out\_name** (*str*) – The name of the output site
- **in\_name** (*Optional[str]*, *optional*) – The name of the input site, by default None
- **cross\_name** (*Optional[str]*, *optional*) – The name of the cross site, by default None

#### Returns

The data gathered for the regression preparer

#### Return type

*GatheredData*

**pydantic model** `resistics.gather.QuickGather`

Bases: *ResisticsProcess*

Processor to gather data outside of a resistics environment

This is intended for use when quickly calculating out a transfer function for a single measurement and only a single spectra data instance is accepted as input.

Remote reference or intersite processing is not possible using QuickGather

See also:

#### *ProjectGather*

For more advanced gathering of data in a project

```
{
  "title": "QuickGather",
  "description": "Processor to gather data outside of a resistics environment\n\
↪ This is intended for use when quickly calculating out a transfer function\nfor a_\
↪ single measurement and only a single spectra data instance is accepted\nas input.\
↪ \n\nRemote reference or intersite processing is not possible using QuickGather\n\
↪ See Also\n-----\nProjectGather : For more advanced gathering of data in a_\
↪ project",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    }
  }
}
```

**run**(*dir\_path*: *Path*, *dec\_params*: *DecimationParameters*, *tf*: *TransferFunction*, *eval\_data*: *SpectraData*) → *GatheredData*

Generate the `GatheredData` object for input into regression preparation

The input is a single spectra data instance and is used to populate the `in_data`, `out_data` and `cross_data`.

#### Parameters

- **dir\_path** (*Path*) – The directory path to the measurement
- **dec\_params** (*DecimationParameters*) – The decimation parameters
- **tf** (*TransferFunction*) – The transfer function
- **eval\_data** (*SpectraData*) – The spectra data at the evaluation frequencies

#### Returns

`GatheredData` for regression preparer

#### Return type

*GatheredData*

## resisticks.letsgo module

This module is the main interface to resisticks and includes:

- Classes and functions for making, loading and using resisticks projects
- Functions for processing data

**pydantic model** `resisticks.letsgo.ProjectCreator`

Bases: *ResisticksProcess*

Process to create a project

```
{
  "title": "ProjectCreator",
  "description": "Process to create a project",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "dir_path": {
      "title": "Dir Path",
      "type": "string",
      "format": "path"
    },
    "metadata": {
      "$ref": "#/definitions/ProjectMetadata"
    }
  },
  "required": [
    "dir_path",
    "metadata"
  ],
  "definitions": {
    "ResisticksFile": {
```

(continues on next page)

(continued from previous page)

```

    "title": "ResisticsFile",
    "description": "Required information for writing out a resistics file",
    "type": "object",
    "properties": {
      "created_on_local": {
        "title": "Created On Local",
        "type": "string",
        "format": "date-time"
      },
      "created_on_utc": {
        "title": "Created On Utc",
        "type": "string",
        "format": "date-time"
      },
      "version": {
        "title": "Version",
        "type": "string"
      }
    }
  },
  "ProjectMetadata": {
    "title": "ProjectMetadata",
    "description": "Project metadata",
    "type": "object",
    "properties": {
      "file_info": {
        "$ref": "#/definitions/ResisticsFile"
      },
      "ref_time": {
        "title": "Ref Time",
        "pattern": "%Y-%m-%d %H:%M:%S.%f%o_%q_%v",
        "examples": [
          "2021-01-01 00:00:00.000061_035156_250000_000000"
        ]
      },
      "location": {
        "title": "Location",
        "default": "",
        "type": "string"
      },
      "country": {
        "title": "Country",
        "default": "",
        "type": "string"
      },
      "year": {
        "title": "Year",
        "default": -999,
        "type": "integer"
      },
      "description": {
        "title": "Description",

```

(continues on next page)

(continued from previous page)

```

        "default": "",
        "type": "string"
    },
    "contributors": {
        "title": "Contributors",
        "default": [],
        "type": "array",
        "items": {
            "type": "string"
        }
    }
},
"required": [
    "ref_time"
]
}
}
}

```

**field** `dir_path`: `Path` [Required]

**field** `metadata`: `ProjectMetadata` [Required]

**run()**

Create the project

**Raises**

`ProjectCreateError` – If an existing project found

`resistics.letsgo.new(dir_path: Path | str, proj_info: Dict[str, Any]) → bool`

Create a new project

**Parameters**

- `dir_path` (`Union[Path, str]`) – The directory to create the project in
- `proj_info` (`Dict[str, Any]`) – Any project details

**Returns**

True if the creator was successful

**Return type**

`bool`

**pydantic model** `resistics.letsgo.ProjectLoader`

Bases: `ResisticsProcess`

Project loader

```

{
    "title": "ProjectLoader",
    "description": "Project loader",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",

```

(continues on next page)

(continued from previous page)

```

        "type": "string"
    },
    "dir_path": {
        "title": "Dir Path",
        "type": "string",
        "format": "path"
    }
},
"required": [
    "dir_path"
]
}

```

**field** `dir_path`: `Path` [Required]

**run**(*config*: `Configuration`) → `Project`

Load a project

**Parameters**

**config** (`Configuration`) – The configuration for the purposes of getting the time readers

**Returns**

Project instance

**Return type**

`Project`

**Raises**

`ProjectLoadError` – If the resistics project metadata is not found

**pydantic model** `resistics.letsgo.ResisticsEnvironment`

Bases: `ResisticsModel`

A Resistics environment which combines a project and a configuration

```

{
    "title": "ResisticsEnvironment",
    "description": "A Resistics environment which combines a project and a ↵
↵configuration",
    "type": "object",
    "properties": {
        "proj": {
            "$ref": "#/definitions/Project"
        },
        "config": {
            "$ref": "#/definitions/Configuration"
        }
    },
    "required": [
        "proj",
        "config"
    ],
    "definitions": {
        "ResisticsFile": {
            "title": "ResisticsFile",

```

(continues on next page)

(continued from previous page)

```

    "description": "Required information for writing out a resistics file",
    "type": "object",
    "properties": {
      "created_on_local": {
        "title": "Created On Local",
        "type": "string",
        "format": "date-time"
      },
      "created_on_utc": {
        "title": "Created On Utc",
        "type": "string",
        "format": "date-time"
      },
      "version": {
        "title": "Version",
        "type": "string"
      }
    }
  },
  "ProjectMetadata": {
    "title": "ProjectMetadata",
    "description": "Project metadata",
    "type": "object",
    "properties": {
      "file_info": {
        "$ref": "#/definitions/ResisticsFile"
      },
      "ref_time": {
        "title": "Ref Time",
        "pattern": "%Y-%m-%d %H:%M:%S.%f_o_%q_%v",
        "examples": [
          "2021-01-01 00:00:00.000061_035156_250000_000000"
        ]
      },
      "location": {
        "title": "Location",
        "default": "",
        "type": "string"
      },
      "country": {
        "title": "Country",
        "default": "",
        "type": "string"
      },
      "year": {
        "title": "Year",
        "default": -999,
        "type": "integer"
      },
      "description": {
        "title": "Description",
        "default": "",

```

(continues on next page)



(continued from previous page)

```

        "type": "string"
    },
    "contributors": {
        "title": "Contributors",
        "default": [],
        "type": "array",
        "items": {
            "type": "string"
        }
    }
},
"required": [
    "ref_time"
],
"ChanMetadata": {
    "title": "ChanMetadata",
    "description": "Channel metadata",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        },
        "data_files": {
            "title": "Data Files",
            "type": "array",
            "items": {
                "type": "string"
            }
        },
        "chan_type": {
            "title": "Chan Type",
            "type": "string"
        },
        "chan_source": {
            "title": "Chan Source",
            "type": "string"
        },
        "sensor": {
            "title": "Sensor",
            "default": "",
            "type": "string"
        },
        "serial": {
            "title": "Serial",
            "default": "",
            "type": "string"
        },
        "gain1": {
            "title": "Gain1",
            "default": 1,

```

(continues on next page)

(continued from previous page)

```

        "type": "number"
    },
    "gain2": {
        "title": "Gain2",
        "default": 1,
        "type": "number"
    },
    "scaling": {
        "title": "Scaling",
        "default": 1,
        "type": "number"
    },
    "chopper": {
        "title": "Chopper",
        "default": false,
        "type": "boolean"
    },
    "dipole_dist": {
        "title": "Dipole Dist",
        "default": 1,
        "type": "number"
    },
    "sensor_calibration_file": {
        "title": "Sensor Calibration File",
        "default": "",
        "type": "string"
    },
    "instrument_calibration_file": {
        "title": "Instrument Calibration File",
        "default": "",
        "type": "string"
    }
},
"required": [
    "name"
]
},
"Record": {
    "title": "Record",
    "description": "Class to hold a record\n\nA record holds information about
↪ a process that was run. It is intended to\ntrack processes applied to data,
↪ allowing a process history to be saved\nalong with any datasets.\n\nExamples\n----
↪ ----\nA simple example of creating a process record\n\n>>> from resistics.common
↪ import Record\n>>> messages = ["message 1", "message 2"]\n>>> record =
↪ Record(\n...     creator={"name": "example", "parameter1": 15},\n...
↪ messages=messages,\n...     record_type="example"\n... )\n>>> record.summary()
↪ {\n    'time_local': '...',\n    'time_utc': '...',\n    'creator': {'name':
↪ 'example', 'parameter1': 15},\n    'messages': ['message 1', 'message 2'],\n
↪ 'record_type': 'example'\n}",
    "type": "object",
    "properties": {
        "time_local": {

```

(continues on next page)

(continued from previous page)

```

        "title": "Time Local",
        "type": "string",
        "format": "date-time"
    },
    "time_utc": {
        "title": "Time Utc",
        "type": "string",
        "format": "date-time"
    },
    "creator": {
        "title": "Creator",
        "type": "object"
    },
    "messages": {
        "title": "Messages",
        "type": "array",
        "items": {
            "type": "string"
        }
    },
    "record_type": {
        "title": "Record Type",
        "type": "string"
    }
},
"required": [
    "creator",
    "messages",
    "record_type"
],
"History": {
    "title": "History",
    "description": "Class for storing processing history\n\nParameters\n-----
→---\nrecords : List[Record], optional\n    List of records, by default []\n\
→nExamples\n-----\n>>> from resistics.testing import record_example1, record_
→example2\n>>> from resistics.common import History\n>>> record1 = record_
→example1()\n>>> record2 = record_example2()\n>>> history =
→History(records=[record1, record2])\n>>> history.summary()\n{\n    'records': [\n
→    {\n        'time_local': '...',\n        'time_utc': '...',\n
→    'creator': {\n        'name': 'example1',\n        'a': 5,\n
→    'b': -7.0\n        },\n        'messages': ['Message 1',
→'Message 2'],\n        'record_type': 'process'\n        },\n        {\n
→    'time_local': '...',\n        'time_utc': '...',\n        'creator
→': {\n        'name': 'example2',\n        'a': 'parzen',\n
→    'b': -21\n        },\n        'messages': ['Message 5', 'Message
→6'],\n        'record_type': 'process'\n        }\n    ]\n}",
    "type": "object",
    "properties": {
        "records": {
            "title": "Records",
            "default": [],

```

(continues on next page)

(continued from previous page)

```

        "type": "array",
        "items": {
            "$ref": "#/definitions/Record"
        }
    }
},
"TimeMetadata": {
    "title": "TimeMetadata",
    "description": "Time metadata",
    "type": "object",
    "properties": {
        "file_info": {
            "$ref": "#/definitions/ResisticsFile"
        },
        "fs": {
            "title": "Fs",
            "type": "number"
        },
        "chans": {
            "title": "Chans",
            "type": "array",
            "items": {
                "type": "string"
            }
        },
        "n_chans": {
            "title": "N Chans",
            "type": "integer"
        },
        "n_samples": {
            "title": "N Samples",
            "type": "integer"
        },
        "first_time": {
            "title": "First Time",
            "pattern": "%Y-%m-%d %H:%M:%S.%f_o_%q_%v",
            "examples": [
                "2021-01-01 00:00:00.000061_035156_250000_000000"
            ]
        },
        "last_time": {
            "title": "Last Time",
            "pattern": "%Y-%m-%d %H:%M:%S.%f_o_%q_%v",
            "examples": [
                "2021-01-01 00:00:00.000061_035156_250000_000000"
            ]
        },
        "system": {
            "title": "System",
            "default": "",
            "type": "string"
        }
    }
}

```

(continues on next page)

(continued from previous page)

```

    },
    "serial": {
      "title": "Serial",
      "default": "",
      "type": "string"
    },
    "wgs84_latitude": {
      "title": "Wgs84 Latitude",
      "default": -999.0,
      "type": "number"
    },
    "wgs84_longitude": {
      "title": "Wgs84 Longitude",
      "default": -999.0,
      "type": "number"
    },
    "easting": {
      "title": "Easting",
      "default": -999.0,
      "type": "number"
    },
    "northing": {
      "title": "Northing",
      "default": -999.0,
      "type": "number"
    },
    "elevation": {
      "title": "Elevation",
      "default": -999.0,
      "type": "number"
    },
    "chans_metadata": {
      "title": "Chans Metadata",
      "type": "object",
      "additionalProperties": {
        "$ref": "#/definitions/ChanMetadata"
      }
    },
    "history": {
      "title": "History",
      "default": {
        "records": []
      },
      "allOf": [
        {
          "$ref": "#/definitions/History"
        }
      ]
    },
  },
  "required": [
    "fs",

```

(continues on next page)

(continued from previous page)

```

        "chans",
        "n_samples",
        "first_time",
        "last_time",
        "chans_metadata"
    ]
},
"TimeReader": {
    "title": "TimeReader",
    "description": "Base class for resistics processes\n\nResistics processes_
↪perform operations on data (including read and write\noperations). Each time a_
↪ResisticsProcess child class is run, it should add\na process record to the_
↪dataset",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        },
        "apply_scalings": {
            "title": "Apply Scalings",
            "default": true,
            "type": "boolean"
        },
        "extension": {
            "title": "Extension",
            "type": "string"
        }
    }
},
"Measurement": {
    "title": "Measurement",
    "description": "Class for interfacing with a measurement\n\nThe class_
↪holds the original time series metadata and can provide\ninformation about other_
↪types of data",
    "type": "object",
    "properties": {
        "site_name": {
            "title": "Site Name",
            "type": "string"
        },
        "dir_path": {
            "title": "Dir Path",
            "type": "string",
            "format": "path"
        },
        "metadata": {
            "$ref": "#/definitions/TimeMetadata"
        },
        "reader": {
            "$ref": "#/definitions/TimeReader"
        }
    }
}

```

(continues on next page)

(continued from previous page)

```

    },
    "required": [
        "site_name",
        "dir_path",
        "metadata",
        "reader"
    ]
},
"Site": {
    "title": "Site",
    "description": "Class for describing Sites\n\n.. note::\n\n    This should_
↪essentially describe a single instrument setup. If the same\n    site is re-
↪occupied later with a different instrument setup, it is\n    suggested to split_
↪this into a different site.",
    "type": "object",
    "properties": {
        "dir_path": {
            "title": "Dir Path",
            "type": "string",
            "format": "path"
        },
        "measurements": {
            "title": "Measurements",
            "type": "object",
            "additionalProperties": {
                "$ref": "#/definitions/Measurement"
            }
        },
        "begin_time": {
            "title": "Begin Time",
            "pattern": "%Y-%m-%d %H:%M:%S.%f_o_%q_%v",
            "examples": [
                "2021-01-01 00:00:00.000061_035156_250000_000000"
            ]
        },
        "end_time": {
            "title": "End Time",
            "pattern": "%Y-%m-%d %H:%M:%S.%f_o_%q_%v",
            "examples": [
                "2021-01-01 00:00:00.000061_035156_250000_000000"
            ]
        }
    },
    "required": [
        "dir_path",
        "measurements",
        "begin_time",
        "end_time"
    ]
},
"Project": {
    "title": "Project",

```

(continues on next page)

(continued from previous page)

```

    "description": "Class to describe a resistics project\n\nThe resistics_
    ↪Project Class connects all resistics data. It is an essential\npart of processing_
    ↪data with resistics.\n\nResistics projects are in directory with several sub-
    ↪directories. Project\nmetadata is saved in the resistics.json file at the top_
    ↪level directory.",
    "type": "object",
    "properties": {
      "dir_path": {
        "title": "Dir Path",
        "type": "string",
        "format": "path"
      },
      "begin_time": {
        "title": "Begin Time",
        "pattern": "%Y-%m-%d %H:%M:%S.%f_o_%q_%v",
        "examples": [
          "2021-01-01 00:00:00.000061_035156_250000_000000"
        ]
      },
      "end_time": {
        "title": "End Time",
        "pattern": "%Y-%m-%d %H:%M:%S.%f_o_%q_%v",
        "examples": [
          "2021-01-01 00:00:00.000061_035156_250000_000000"
        ]
      },
      "metadata": {
        "$ref": "#/definitions/ProjectMetadata"
      },
      "sites": {
        "title": "Sites",
        "default": {},
        "type": "object",
        "additionalProperties": {
          "$ref": "#/definitions/Site"
        }
      }
    },
    "required": [
      "dir_path",
      "begin_time",
      "end_time",
      "metadata"
    ],
    "TimeProcess": {
      "title": "TimeProcess",
      "description": "Parent class for processing time data",
      "type": "object",
      "properties": {
        "name": {
          "title": "Name",

```

(continues on next page)



```

    "type": "string"
  }
},
"DecimationSetup": {
  "title": "DecimationSetup",
  "description": "Process to calculate decimation parameters\n\nParameters\n-----\nn_levels : int, optional\n    Number of decimation levels, by default 8\nper_level : int, optional\n    Number of frequencies per level, by default 5\nmin_samples : int, optional\n    Number of samples under which to quit\ndecimating\ndiv_factor : int, optional\n    Minimum division factor for decimation, by default 2.\neval_freqs : Optional[List[float]], optional\n    Explicit definition of evaluation frequencies as a flat list, by default None. Must be of size n_levels * per_level\n\nExamples\n-----\n>>> from resistics.decimate import DecimationSetup\n>>> dec_setup = DecimationSetup(n_levels=3, per_level=2)\n>>> dec_params = dec_setup.run(128)\n>>> print(dec_params.to_dataframe())\n\n   0      1      fs  factors  increments\nndecimation level\n0      32.0  22.627417  128.0      1      1\n1      16.0  11.313708   64.0      2      2\n2      8.0   5.656854   32.0      4      2",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "n_levels": {
      "title": "N Levels",
      "default": 8,
      "type": "integer"
    },
    "per_level": {
      "title": "Per Level",
      "default": 5,
      "type": "integer"
    },
    "min_samples": {
      "title": "Min Samples",
      "default": 256,
      "type": "integer"
    },
    "div_factor": {
      "title": "Div Factor",
      "default": 2,
      "type": "integer"
    },
    "eval_freqs": {
      "title": "Eval Freqs",
      "type": "array",
      "items": {
        "type": "number"
      }
    }
  }
}

```

### 4.3. resistics package

(continued from previous page)

```

    }
  },
  "Decimator": {
    "title": "Decimator",
    "description": "Decimate the time data into multiple levels\n\nThere are_
→two options for decimation, using time data Resample or using\ntime data Decimate.
→ The default is to use Resample.",
    "type": "object",
    "properties": {
      "name": {
        "title": "Name",
        "type": "string"
      },
      "resample": {
        "title": "Resample",
        "default": true,
        "type": "boolean"
      },
      "max_single_factor": {
        "title": "Max Single Factor",
        "default": 3,
        "minimum": 3,
        "type": "integer"
      }
    }
  },
  "WindowSetup": {
    "title": "WindowSetup",
    "description": "Setup WindowParameters\n\nWindowSetup outputs the_
→WindowParameters to use for windowing decimated\ntime data.\n\nWindow parameters_
→are simply the window and overlap sizes for each\ndecimation level.\n\nParameters\
→n-----\nmin_size : int, optional\n    Minimum window size, by default 128\
→nmin_olap : int, optional\n    Minimum overlap size, by default 32\nwin_factor :_
→int, optional\n    Window factor, by default 4. Window sizes are calculated by_
→sampling\n    frequency / 4 to ensure sufficient frequency resolution. If the\n _
→ sampling frequency is small, window size will be adjusted to\n    min_size\nolap_
→proportion : float, optional\n    The proportion of the window size to use as the_
→overlap, by default\n    0.25. For example, for a window size of 128, the overlap_
→would be\n    0.25 * 128 = 32\nmin_n_wins : int, optional\n    The minimum number_
→of windows needed in a decimation level, by\n    default 5\nwin_sizes :_
→Optional[List[int]], optional\n    Explicit define window sizes, by default None._
→Must have the same\n    length as number of decimation levels\nolap_sizes :_
→Optional[List[int]], optional\n    Explicitly define overlap sizes, by default_
→None. Must have the same\n    length as number of decimation levels\n\nExamples\n
→-----\nGenerate decimation and windowing parameters for data sampled at 0.05 Hz_
→or\n20 seconds sampling period\n\n>>> from resistics.decimate import_
→DecimationSetup\n>>> from resistics.window import WindowSetup\n>>> dec_params =_
→DecimationSetup(n_levels=3, per_level=3).run(0.05)\n>>> dec_params.summary()\n{\n_
→  'fs': 0.05,\n    'n_levels': 3,\n    'per_level': 3,\n    'min_samples': 256,\n
→n    'eval_freqs': [\n        0.0125,\n        0.008838834764831844,\n        0.
→00625,\n        0.004419417382415922,\n        0.003125,\n        0.

```

(continues on next page)

(continued from previous page)

```

→002209708691207961,\n      0.0015625,\n      0.0011048543456039805,\n
→0.00078125\n    ],\n    'dec_factors': [1, 2, 8],\n    'dec_increments': [1, 2,\n
→4],\n    'dec_fs': [0.05, 0.025, 0.00625]\n}\n>>> win_params = WindowSetup().
→run(dec_params.n_levels, dec_params.dec_fs)\n>>> win_params.summary()\n{\n    'n_
→levels': 3,\n    'min_n_wins': 5,\n    'win_sizes': [128, 128, 128],\n    'olap_
→sizes': [32, 32, 32]\n}\n\nWindow parameters can also be explicitly defined\n\n>>>
→ from resistics.decimate import DecimationSetup\n>>> from resistics.window import
→WindowSetup\n>>> dec_setup = DecimationSetup(n_levels=3, per_level=3)\n>>> dec_
→params = dec_setup.run(0.05)\n>>> win_setup = WindowSetup(win_sizes=[1000, 578,\n
→104])\n>>> win_params = win_setup.run(dec_params.n_levels, dec_params.dec_fs)\n>>>
→ win_params.summary()\n{\n    'n_levels': 3,\n    'min_n_wins': 5,\n    'win_sizes
→': [1000, 578, 104],\n    'olap_sizes': [250, 144, 32]\n}\n\nWhen providing
→explicit window and overlap sizes, the size of the overlap\nis expected to be
→less than the size of the window\n\n>>> from resistics.decimate import
→DecimationSetup\n>>> from resistics.window import WindowSetup\n>>> dec_setup =
→DecimationSetup(n_levels=3, per_level=3)\n>>> dec_params = dec_setup.run(0.05)\n>>
→> win_setup = WindowSetup(win_sizes=[1000, 578, 104], olap_sizes=[1001, 600, 25])\n
→>>> win_params = win_setup.run(dec_params.n_levels, dec_params.dec_fs)\n
→nTraceback (most recent call last):\n...\nValueError: Invalid overlaps found [\n
→True True False]",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        },
        "min_size": {
            "title": "Min Size",
            "default": 128,
            "type": "integer"
        },
        "min_olap": {
            "title": "Min Olap",
            "default": 32,
            "type": "integer"
        },
        "win_factor": {
            "title": "Win Factor",
            "default": 4,
            "type": "integer"
        },
        "olap_proportion": {
            "title": "Olap Proportion",
            "default": 0.25,
            "type": "number"
        },
        "min_n_wins": {
            "title": "Min N Wins",
            "default": 5,
            "type": "integer"
        },
        "win_sizes": {

```

(continues on next page)

(continued from previous page)

```

        "title": "Win Sizes",
        "type": "array",
        "items": {
            "type": "integer"
        }
    },
    "olap_sizes": {
        "title": "Olap Sizes",
        "type": "array",
        "items": {
            "type": "integer"
        }
    }
}

},
"Windower": {
    "title": "Windower",
    "description": "Windows DecimatedData\n\nThis is the primary window making
→process for resistics and should be used\nwhen alignment of windows with a site.
→or across sites is required.\n\nThis method uses numpy striding to produce window
→views into the decimated\ndata.\n\nSee Also\n-----\nWindowerTarget : A
→windower to make a target number of windows\n\nExamples\n-----\n\nThe Windower
→windows a DecimatedData object given a reference time and some\nwindow parameters.
→\n\nThere's quite a few imports needed for this example. Begin by doing the\
→nimports, defining a reference time and generating random decimated data.\n\n>>>
→from resistics.sampling import to_datetime\n>>> from resistics.testing import
→decimated_data_linear\n>>> from resistics.window import WindowSetup, Windower\n>>>
→dec_data = decimated_data_linear(fs=128)\n>>> ref_time = dec_data.metadata.first_
→time\n>>> print(dec_data.to_string())\n<class 'resistics.decimate.DecimatedData'>\
→n
→fs      dt  n_samples      first_time
→last_time\nlevel\n0      2048.0  0.000488      16384  2021-01-01 00:00:00  2021-
→01-01 00:00:07.99951171875\n1      512.0  0.001953      4096  2021-01-01
→00:00:00  2021-01-01 00:00:07.998046875\n2      128.0  0.007812      1024
→2021-01-01 00:00:00  2021-01-01 00:00:07.9921875\n\nNext, initialise the
→window parameters. For this example, use small windows,\nwhich will make
→inspecting them easier.\n\n>>> win_params = WindowSetup(win_sizes=[16,16,16], min_
→olap=4).run(dec_data.metadata.n_levels, dec_data.metadata.fs)\n>>> win_params.
→summary()\n{\n  'n_levels': 3,\n  'min_n_wins': 5,\n  'win_sizes': [16, 16,
→16],\n  'olap_sizes': [4, 4, 4]\n}\n\nPerform the windowing. This actually
→creates views into the decimated data\nusing the numpy.lib.stride_tricks.sliding_
→window_view function. The shape\nfor a data array at a decimation level is: n_
→wins x n_chans x win_size. The\ninformation about each level is also in the
→levels_metadata attribute of\nWindowedMetadata.\n\n>>> win_data = Windower().
→run(ref_time, win_params, dec_data)\n>>> win_data.data[0].shape\n(1365, 2, 16)\n>>
→for level_metadata in win_data.metadata.levels_metadata:\n...   level_
→metadata.summary()\n{\n  'fs': 2048.0,\n  'n_wins': 1365,\n  'win_size': 16,
→\n  'olap_size': 4,\n  'index_offset': 0\n}\n{\n  'fs': 512.0,\n  'n_wins
→': 341,\n  'win_size': 16,\n  'olap_size': 4,\n  'index_offset': 0\n}\n{\n
→'fs': 128.0,\n  'n_wins': 85,\n  'win_size': 16,\n  'olap_size': 4,\n
→'index_offset': 0\n}\n\nLet's look at an example of data from the first
→decimation level for the\nfirst channel. This is simply a linear set of data
→ranging from 0...16_383.\n\n>>> dec_data.data[0][0]\narray([  0,    1,    2, .

```

(continues on next page)

(continued from previous page)

```

→..., 16381, 16382, 16383]))\n\nInspecting the first few windows shows they are as_
→expected including the\noverlap.\n\n>>> win_data.data[0][0, 0]\narray([ 0, 1, 2,
→ 3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15])\n>>> win_data.data[0][1, 0]\n
→array([12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27])\n>>> win_
→data.data[0][2, 0]\narray([24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37,
→ 38, 39])",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        }
    }
},
    "FourierTransform": {
        "title": "FourierTransform",
        "description": "Perform a Fourier transform of the windowed data\n\nThe_
→processor is inspired by the scipy.signal.stft function which performs\na similar_
→process and involves a Fourier transform along the last axis of\nthe windowed_
→data.\n\nParameters\n-----\nwin_func : Union[str, Tuple[str, float]]\n    The_
→window to use before performing the FFT, by default (\"kaiser\", 14)\ndetrend :_
→Union[str, None]\n    Type of detrending to apply before performing FFT, by_
→default linear\n    detrend. Setting to None will not apply any detrending to the_
→data prior\n    to the FFT\nworkers : int\n    The number of CPUs to use, by_
→default max - 2\n\nExamples\n-----\n\nThis example will get periodic decimated_
→data, perform windowing and run the\nFourier transform on the windowed data.\n\n..
→ plot::\n    :width: 90%\n\n    >>> import matplotlib.pyplot as plt\n    >>>_
→import numpy as np\n    >>> from resistics.testing import decimated_data_periodic\
→n    >>> from resistics.window import WindowSetup, Windower\n    >>> from_
→resistics.spectra import FourierTransform\n    >>> frequencies = {\"chan1\": [870,
→ 590, 110, 32, 12], \"chan2\": [480, 375, 210, 60, 45]}\n    >>> dec_data =_
→decimated_data_periodic(frequencies, fs=128)\n    >>> dec_data.metadata.chans\n    _
→ ['chan1', 'chan2']\n    >>> print(dec_data.to_string())\n    <class 'resistics._
→decimate.DecimatedData'>\n\n                fs          dt n_samples          first_
→time                last_time\n    level\n    0          2048.0 0.000488 _
→ 16384 2021-01-01 00:00:00 2021-01-01 00:00:07.99951171875\n    1          512.0 _
→0.001953          4096 2021-01-01 00:00:00 2021-01-01 00:00:07.998046875\n    2 _
→          128.0 0.007812          1024 2021-01-01 00:00:00 2021-01-01 00:00:07.
→9921875\n\n    Perform the windowing\n\n    >>> win_params = WindowSetup().
→run(dec_data.metadata.n_levels, dec_data.metadata.fs)\n    >>> win_data =_
→Windower().run(dec_data.metadata.first_time, win_params, dec_data)\n\n    And_
→then the Fourier transform. By default, the data will be (linearly)\n    _
→detrended and multiplied by a Kaiser window prior to the Fourier\n    transform\n\
→n    >>> spec_data = FourierTransform().run(win_data)\n\n    For plotting of_
→magnitude, let's stack the spectra\n\n    >>> freqs_0 = spec_data.metadata.levels_
→metadata[0].freqs\n    >>> data_0 = np.absolute(spec_data.data[0]).mean(axis=0)\n_
→n    >>> freqs_1 = spec_data.metadata.levels_metadata[1].freqs\n    >>> data_1 = np.
→absolute(spec_data.data[1]).mean(axis=0)\n    >>> freqs_2 = spec_data.metadata.
→levels_metadata[2].freqs\n    >>> data_2 = np.absolute(spec_data.data[2]).
→mean(axis=0)\n\n    Now plot\n\n    >>> plt.subplot(3,1,1) # doctest: +SKIP\n    >
→>> plt.plot(freqs_0, data_0[0], label=\"chan1\") # doctest: +SKIP\n    >>> plt.
→plot(freqs_0, data_0[1], label=\"chan2\") # doctest: +SKIP\n    >>> plt.grid()\n    _

```

(continues on next page)

(continued from previous page)

```

→ >>> plt.title("\Decimation level 0\") # doctest: +SKIP\n    >>> plt.legend() #_
→doctest: +SKIP\n    >>> plt.subplot(3,1,2) # doctest: +SKIP\n    >>> plt.
→plot(freqs_1, data_1[0], label="\chan1\") # doctest: +SKIP\n    >>> plt.
→plot(freqs_1, data_1[1], label="\chan2\") # doctest: +SKIP\n    >>> plt.grid()\n _
→ >>> plt.title("\Decimation level 1\") # doctest: +SKIP\n    >>> plt.legend() #_
→doctest: +SKIP\n    >>> plt.subplot(3,1,3) # doctest: +SKIP\n    >>> plt.
→plot(freqs_2, data_2[0], label="\chan1\") # doctest: +SKIP\n    >>> plt.
→plot(freqs_2, data_2[1], label="\chan2\") # doctest: +SKIP\n    >>> plt.grid()\n _
→ >>> plt.title("\Decimation level 2\") # doctest: +SKIP\n    >>> plt.legend() #_
→doctest: +SKIP\n    >>> plt.xlabel("\Frequency\") # doctest: +SKIP\n    >>> plt.
→tight_layout() # doctest: +SKIP\n    >>> plt.show() # doctest: +SKIP",
    "type": "object",
    "properties": {
      "name": {
        "title": "Name",
        "type": "string"
      },
      "win_fnc": {
        "title": "Win Fnc",
        "default": [
          "kaiser",
          14
        ],
        "anyOf": [
          {
            "type": "string"
          },
          {
            "type": "array",
            "minItems": 2,
            "maxItems": 2,
            "items": [
              {
                "type": "string"
              },
              {
                "type": "number"
              }
            ]
          }
        ]
      },
      "detrend": {
        "title": "Detrend",
        "default": "linear",
        "type": "string"
      },
      "workers": {
        "title": "Workers",
        "default": -2,
        "type": "integer"
      }
    }
  }

```

(continues on next page)

(continued from previous page)

```

    }
  },
  "SpectraProcess": {
    "title": "SpectraProcess",
    "description": "Parent class for spectra processes",
    "type": "object",
    "properties": {
      "name": {
        "title": "Name",
        "type": "string"
      }
    }
  },
  "EvaluationFreqs": {
    "title": "EvaluationFreqs",
    "description": "Calculate the spectra values at the evaluation frequencies\
↪\n\nThis is done using linear interpolation in the complex domain\n\nExample\n-----\
↪--\n\nThe example will show interpolation to evaluation frequencies on a very\
↪simple example. Begin by generating some example spectra data.\n\n>>> from\
↪resistics.decimate import DecimationSetup\n>>> from resistics.spectra import\
↪EvaluationFreqs\n>>> from resistics.testing import spectra_data_basic\n>>> spec\
↪data = spectra_data_basic()\n>>> spec_data.metadata.n_levels\n1\n>>> spec_data.\
↪metadata.chans\n['chan1']\n>>> spec_data.metadata.levels_metadata[0].summary()\n{\
↪n  'fs': 180.0,\n  'n_wins': 2,\n  'win_size': 20,\n  'olap_size': 5,\n  \
↪'index_offset': 0,\n  'n_freqs': 10,\n  'freqs': [0.0, 10.0, 20.0, 30.0, 40.\
↪0, 50.0, 60.0, 70.0, 80.0, 90.0]\n}\n\nThe spectra data has only a single channel\
↪and a single level which has 2\nwindows. Now define our evaluation frequencies.\n\
↪n>>> eval_freqs = [1, 12, 23, 34, 45, 56, 67, 78, 89]\n>>> dec_setup =\
↪DecimationSetup(n_levels=1, per_level=9, eval_freqs=eval_freqs)\n>>> dec_params =\
↪dec_setup.run(spec_data.metadata.fs[0])\n>>> dec_params.summary()\n{\n  'fs':\
↪180.0,\n  'n_levels': 1,\n  'per_level': 9,\n  'min_samples': 256,\n\
↪'eval_freqs': [1.0, 12.0, 23.0, 34.0, 45.0, 56.0, 67.0, 78.0, 89.0],\n  'dec_\
↪factors': [1],\n  'dec_increments': [1],\n  'dec_fs': [180.0]\n}\n\nNow\
↪calculate the spectra at the evaluation frequencies\n\n>>> eval_data =\
↪EvaluationFreqs().run(dec_params, spec_data)\n>>> eval_data.metadata.levels_\
↪metadata[0].summary()\n{\n  'fs': 180.0,\n  'n_wins': 2,\n  'win_size': 20,\n\
↪'olap_size': 5,\n  'index_offset': 0,\n  'n_freqs': 9,\n  'freqs': [1.\
↪0, 12.0, 23.0, 34.0, 45.0, 56.0, 67.0, 78.0, 89.0]\n}\n\nTo double check\
↪everything is as expected, let's compare the data. Comparing\nwindow 1 gives\n\n>> print(spec_data.data[0][0, 0])\n[0.+0.j 1.+1.j 2.+2.j 3.+3.j 4.+4.j 5.+5.j 6.+6.\
↪j 7.+7.j 8.+8.j 9.+9.j]\n>>> print(eval_data.data[0][0, 0])\n[0.1+0.1j 1.2+1.2j 2.\
↪3+2.3j 3.4+3.4j 4.5+4.5j 5.6+5.6j 6.7+6.7j 7.8+7.8j\n 8.9+8.9j]\n\nAnd window 2\n\
↪n>>> print(spec_data.data[0][1, 0])\n[-1. +1.j  0. +2.j  1. +3.j  2. +4.j  3. +5.\
↪j  4. +6.j  5. +7.j  6. +8.j\n 7. +9.j  8.+10.j]\n>>> print(eval_data.data[0][1,\
↪0])\n[-0.9+1.1j  0.2+2.2j  1.3+3.3j  2.4+4.4j  3.5+5.5j  4.6+6.6j  5.7+7.7j\n 6.\
↪8+8.8j  7.9+9.9j]",
    "type": "object",
    "properties": {
      "name": {
        "title": "Name",
        "type": "string"
      }
    }
  }
}

```

(continues on next page)

(continued from previous page)

```

    }
  },
  "Calibrator": {
    "title": "Calibrator",
    "description": "Parent class for a calibrator",
    "type": "object",
    "properties": {
      "name": {
        "title": "Name",
        "type": "string"
      },
      "chans": {
        "title": "Chans",
        "type": "array",
        "items": {
          "type": "string"
        }
      }
    }
  },
  "TransferFunction": {
    "title": "TransferFunction",
    "description": "Define a generic transfer function\n\nThis class is a
→describes generic transfer function, including:\n\n- The output channels for the
→transfer function\n- The input channels for the transfer function\n- The cross
→channels for the transfer function\n\nThe cross channels are the channels that
→will be used to calculate out the\ncross powers for the regression.\n\nThis
→generic parent class has no implemented plotting function. However,\nchild
→classes may have a plotting function as different transfer functions\nmay need
→different types of plots.\n\n.. note::\n\n    Users interested in writing a
→custom transfer function should inherit\n    from this generic Transfer function\
→\n\nSee Also\n-----\nImpandanceTensor : Transfer function for the MT impedance
→tensor\nTipper : Transfer function for the MT tipper\n\nExamples\n-----\nA
→generic example\n\n>>> from resistics.transfunc import TransferFunction\n>>> tf =
→TransferFunction(variation=\"example\", out_chans=[\"bye\", \"see you\", \"ciao\
→\"], in_chans=[\"hello\", \"hi_there\"])\n>>> print(tf.to_string())\n| bye
→ | bye_hello      bye_hi_there      | | hello      |\n| see you | = | see you_
→hello      see you_hi_there | | hi_there |\n| ciao      | | ciao_hello
→ciao_hi_there      |\n\nCombining the impedance tensor and the tipper into one
→TransferFunction\n\n>>> tf = TransferFunction(variation=\"combined\", out_chans=[
→\"Ex\", \"Ey\"], in_chans=[\"Hx\", \"Hy\", \"Hz\"])\n>>> print(tf.to_string())\n|
→Ex |      | Ex_Hx Ex_Hy Ex_Hz | | Hx | \n| Ey | = | Ey_Hx Ey_Hy Ey_Hz | | Hy | \n
→      | Hz |\",
    "type": "object",
    "properties": {
      "name": {
        "title": "Name",
        "type": "string"
      },
      "variation": {
        "title": "Variation",
        "default": "generic",

```

(continues on next page)



(continued from previous page)

```

        "maxLength": 16,
        "type": "string"
    },
    "out_chans": {
        "title": "Out Chans",
        "type": "array",
        "items": {
            "type": "string"
        }
    },
    "in_chans": {
        "title": "In Chans",
        "type": "array",
        "items": {
            "type": "string"
        }
    },
    "cross_chans": {
        "title": "Cross Chans",
        "type": "array",
        "items": {
            "type": "string"
        }
    },
    "n_out": {
        "title": "N Out",
        "type": "integer"
    },
    "n_in": {
        "title": "N In",
        "type": "integer"
    },
    "n_cross": {
        "title": "N Cross",
        "type": "integer"
    }
},
"required": [
    "out_chans",
    "in_chans"
],
"RegressionPreparerGathered": {
    "title": "RegressionPreparerGathered",
    "description": "Regression preparer for gathered data\n\nIn nearly all
↪ cases, this is the regresson preparer to use. As input, it\nrequires GatheredData.
↪",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        }
    }
}

```

(continues on next page)

(continued from previous page)

```

    }
  },
  "Solver": {
    "title": "Solver",
    "description": "General resistics solver",
    "type": "object",
    "properties": {
      "name": {
        "title": "Name",
        "type": "string"
      }
    }
  },
  "Configuration": {
    "title": "Configuration",
    "description": "The resistics configuration\n\nConfiguration can be
→ customised by users who wish to use their own custom\n\nprocesses for certain steps.
→ In most cases, customisation will be for:\n\n- Implementing new time data
→ readers\n- Implementing readers for specific calibration formats\n- Implementing
→ time data processors\n- Implementing spectra data processors\n- Adding new
→ features to extract from the data\n\nExamples\n-----\n\nFrequently,
→ configuration will be used to change data readers.\n\n>>> from resistics.letsgo
→ import get_default_configuration\n>>> config = get_default_configuration()\n>>>
→ config.name\n'default'\n>>> for tr in config.time_readers:\n...    tr.summary()\n
→ {\n    'name': 'TimeReaderAscii',\n    'apply_scalings': True,\n    'extension':
→ '.txt',\n    'delimiter': None,\n    'n_header': 0\n}\n\n{\n    'name':
→ 'TimeReaderNumpy',\n    'apply_scalings': True,\n    'extension': '.numpy'\n}\n>>>
→ config.sensor_calibrator.summary()\n{\n    'name': 'SensorCalibrator',\n    'chans
→ ': None,\n    'readers': [\n        {\n            'name': 'SensorCalibrationJSON
→ ',\n            'extension': '.json',\n            'file_str': 'IC_$sensor
→ $extension'\n        }\n    ]\n}\n\nTo change these, it's best to make a new
→ configuration with a different name\n\n>>> from resistics.letsgo import
→ Configuration\n>>> from resistics.time import TimeReaderNumpy\n>>> config =
→ Configuration(name="myconfig", time_readers=[TimeReaderNumpy(apply_
→ scalings=False)])\n>>> for tr in config.time_readers:\n...    tr.summary()\n{\n
→ 'name': 'TimeReaderNumpy',\n    'apply_scalings': False,\n    'extension': '.numpy
→ '\n}\n\nOr for the sensor calibration\n\n>>> from resistics.calibrate import
→ SensorCalibrator, SensorCalibrationTXT\n>>> calibration_reader =
→ SensorCalibrationTXT(file_str="lemi120_IC_$serial$extension")\n>>> calibrator =
→ SensorCalibrator(chans=["Hx", "Hy", "Hz"], readers=[calibration_reader])\n>>>
→ config = Configuration(name="myconfig", sensor_calibrator=calibrator)\n>>>
→ config.sensor_calibrator.summary()\n{\n    'name': 'SensorCalibrator',\n    'chans
→ ': ['Hx', 'Hy', 'Hz'],\n    'readers': [\n        {\n            'name':
→ 'SensorCalibrationTXT',\n            'extension': '.TXT',\n            'file_str
→ ': 'lemi120_IC_$serial$extension'\n        }\n    ]\n}\n\nAs a final example,
→ create a configuration which used targetted windowing\n\ninstead of specified
→ window sizes\n\n>>> from resistics.letsgo import Configuration\n>>> from
→ resistics.window import WindowerTarget\n>>> config = Configuration(name="window_
→ target", windower=WindowerTarget(target=500))\n>>> config.name\n'window_target'\n
→ >>> config.windower.summary()\n{\n    'name': 'WindowerTarget',\n    'target':
→ 500,\n    'min_size': 64,\n    'olap_proportion': 0.25\n}",

```

(continues on next page)

(continued from previous page)

```

"type": "object",
"properties": {
  "name": {
    "title": "Name",
    "type": "string"
  },
  "time_readers": {
    "title": "Time Readers",
    "default": [
      {
        "name": "TimeReaderAscii",
        "apply_scalings": true,
        "extension": ".txt",
        "delimiter": null,
        "n_header": 0
      },
      {
        "name": "TimeReaderNumpy",
        "apply_scalings": true,
        "extension": ".npz"
      }
    ],
    "type": "array",
    "items": {
      "$ref": "#/definitions/TimeReader"
    }
  },
  "time_processors": {
    "title": "Time Processors",
    "default": [
      {
        "name": "InterpolateNans"
      },
      {
        "name": "RemoveMean"
      }
    ],
    "type": "array",
    "items": {
      "$ref": "#/definitions/TimeProcess"
    }
  },
  "dec_setup": {
    "title": "Dec Setup",
    "default": {
      "name": "DecimationSetup",
      "n_levels": 8,
      "per_level": 5,
      "min_samples": 256,
      "div_factor": 2,
      "eval_freqs": null
    }
  },

```

(continues on next page)

(continued from previous page)

```

        "allOf": [
            {
                "$ref": "#/definitions/DecimationSetup"
            }
        ]
    },
    "decimator": {
        "title": "Decimator",
        "default": {
            "name": "Decimator",
            "resample": true,
            "max_single_factor": 3
        },
        "allOf": [
            {
                "$ref": "#/definitions/Decimator"
            }
        ]
    },
    "win_setup": {
        "title": "Win Setup",
        "default": {
            "name": "WindowSetup",
            "min_size": 128,
            "min_olap": 32,
            "win_factor": 4,
            "olap_proportion": 0.25,
            "min_n_wins": 5,
            "win_sizes": null,
            "olap_sizes": null
        },
        "allOf": [
            {
                "$ref": "#/definitions/WindowSetup"
            }
        ]
    },
    "windower": {
        "title": "Windower",
        "default": {
            "name": "Windower"
        },
        "allOf": [
            {
                "$ref": "#/definitions/Windower"
            }
        ]
    },
    "fourier": {
        "title": "Fourier",
        "default": {
            "name": "FourierTransform",

```

(continues on next page)

(continued from previous page)

```

        "win_fnc": [
            "kaiser",
            14
        ],
        "detrend": "linear",
        "workers": -2
    },
    "allOf": [
        {
            "$ref": "#/definitions/FourierTransform"
        }
    ]
},
"spectra_processors": {
    "title": "Spectra Processors",
    "default": [],
    "type": "array",
    "items": {
        "$ref": "#/definitions/SpectraProcess"
    }
},
"evals": {
    "title": "Evals",
    "default": {
        "name": "EvaluationFreqs"
    },
    "allOf": [
        {
            "$ref": "#/definitions/EvaluationFreqs"
        }
    ]
},
"sensor_calibrator": {
    "title": "Sensor Calibrator",
    "default": {
        "name": "SensorCalibrator",
        "chans": null,
        "readers": [
            {
                "name": "SensorCalibrationJSON",
                "extension": ".json",
                "file_str": "IC_$sensor$extension"
            }
        ]
    },
    "allOf": [
        {
            "$ref": "#/definitions/Calibrator"
        }
    ]
},
"tf": {

```

(continues on next page)

(continued from previous page)

```

    "title": "Tf",
    "default": {
      "name": "ImpedanceTensor",
      "variation": "default",
      "out_chans": [
        "Ex",
        "Ey"
      ],
      "in_chans": [
        "Hx",
        "Hy"
      ],
      "cross_chans": [
        "Hx",
        "Hy"
      ],
      "n_out": 2,
      "n_in": 2,
      "n_cross": 2
    },
    "allOf": [
      {
        "$ref": "#/definitions/TransferFunction"
      }
    ]
  },
  "regression_preparer": {
    "title": "Regression Preparer",
    "default": {
      "name": "RegressionPreparerGathered"
    },
    "allOf": [
      {
        "$ref": "#/definitions/RegressionPreparerGathered"
      }
    ]
  },
  "solver": {
    "title": "Solver",
    "default": {
      "name": "SolverScikitTheilSen",
      "fit_intercept": false,
      "normalize": false,
      "n_jobs": -2,
      "max_subpopulation": 2000,
      "n_subsamples": null
    },
    "allOf": [
      {
        "$ref": "#/definitions/Solver"
      }
    ]
  }
]

```

(continues on next page)

(continued from previous page)

```

        }
    },
    "required": [
        "name"
    ]
}
}
}

```

**field proj:** *Project* [Required]

The project

**field config:** *Configuration* [Required]

The configuration for processing

**resistics.letsgo.load**(*dir\_path: Path | str, config: Configuration | None = None*) → *ResisticsEnvironment*

Load an existing project into a ResisticsEnvironment

**Parameters**

- **dir\_path** (*Union[Path, str]*) – The project directory
- **config** (*Optional[Configuration]*, *optional*) – A configuration of parameters to use

**Returns**

The ResisticsEnvironment combining a project and a configuration

**Return type**

*ResisticsEnvironment*

**Raises**

*ProjectLoadError* – If the loading failed

**resistics.letsgo.reload**(*resenv: ResisticsEnvironment*) → *ResisticsEnvironment*

Reload the project in the ResisticsEnvironment

**Parameters**

**resenv** (*ResisticsEnvironment*) – The current resistics environment

**Returns**

The resistics environment with the project reloaded

**Return type**

*ResisticsEnvironment*

**resistics.letsgo.run\_time\_processors**(*config: Configuration, time\_data: TimeData*) → *TimeData*

Process time data

**Parameters**

- **config** (*Configuration*) – The configuration
- **time\_data** (*TimeData*) – Time data to process

**Returns**

Process time data

**Return type**

*TimeData*

`resistics.letsgo.run_decimation`(*config*: `Configuration`, *time\_data*: `TimeData`, *dec\_params*: `DecimationParameters` | *None* = *None*) → *DecimatedData*

Decimate TimeData

**Parameters**

- **config** (`Configuration`) – The configuration
- **time\_data** (`TimeData`) – Time data to decimate
- **dec\_params** (`DecimationParameters`) – Number of levels, decimation factors etc.

**Returns**

Decimated time data

**Return type**

*DecimatedData*

`resistics.letsgo.run_windowing`(*config*: `Configuration`, *ref\_time*: `HighResDateTime`, *dec\_data*: `DecimatedData`) → *WindowedData*

Window time data

**Parameters**

- **config** (`Configuration`) – The configuration
- **ref\_time** (`HighResDateTime`) – The reference time
- **dec\_data** (`DecimatedData`) – Decimated data to window

**Returns**

The windowed data

**Return type**

*WindowedData*

`resistics.letsgo.run_fft`(*config*: `Configuration`, *win\_data*: `WindowedData`) → *SpectraData*

Run Fourier transform

**Parameters**

- **config** (`Configuration`) – The configuration
- **win\_data** (`WindowedData`) – Windowed data

**Returns**

Fourier transformed windowed data

**Return type**

*SpectraData*

`resistics.letsgo.run_spectra_processors`(*config*: `Configuration`, *spec\_data*: `SpectraData`) → *SpectraData*

Run any spectra processors

**Parameters**

- **config** (`Configuration`) – The configuration
- **spec\_data** (`SpectraData`) – Spectra data

**Returns**

Processed spectra data

**Return type**

*SpectraData*



`resistics.letsgo.run_evals`(*config*: *Configuration*, *dec\_params*: *DecimationParameters*, *spec\_data*: *SpectraData*) → *SpectraData*

Run evaluation frequency data calculator

#### Parameters

- **config** (*Configuration*) – The configuration
- **dec\_params** (*DecimationParameters*) – Decimation parameters with the evaluation frequencies
- **spec\_data** (*SpectraData*) – The spectra data

#### Returns

Spectra data at evaluation frequencies

#### Return type

*SpectraData*

`resistics.letsgo.run_sensor_calibration`(*config*: *Configuration*, *calibration\_path*: *Path*, *spec\_data*: *SpectraData*) → *SpectraData*

Run calibration

#### Parameters

- **config** (*Configuration*) – The configuration
- **calibration\_path** (*Path*) – Path to calibration data
- **spec\_data** (*SpectraData*) – Spectra data to calibrate

#### Returns

Calibrated spectra data

#### Return type

*SpectraData*

`resistics.letsgo.run_regression_preparer`(*config*: *Configuration*, *gathered\_data*: *GatheredData*) → *RegressionInputData*

Prepare linear regression data

#### Parameters

- **config** (*Configuration*) – The configuration
- **gathered\_data** (*GatheredData*) – Gathered data to input into the regression

#### Returns

Regression inputs for all evaluation frequencies

#### Return type

*RegressionInputData*

`resistics.letsgo.run_solver`(*config*: *Configuration*, *reg\_data*: *RegressionInputData*) → *Solution*

Run the regression solver

#### Parameters

- **config** (*Configuration*) – The configuration
- **reg\_data** (*RegressionInputData*) – The regression input data

#### Returns

Transfer function estimate

**Return type***Solution*

```
resistics.letsgo.quick_read(dir_path: Path, config: Configuration | None = None, from_time: str |  
Timestamp | datetime | None = None, to_time: str | Timestamp | datetime | None  
= None, from_sample: None = None, to_sample: None = None) → TimeData
```

Read time data folder

**Parameters**

- **dir\_path** (*Path*) – The directory path to read
- **config** (*Optional[Configuration]*, *optional*) – Configuration with appropriate readers, by default None.
- **from\_time** (*Union[DateTimeLike, None]*, *optional*) – Timestamp to read from, by default None
- **to\_time** (*Union[DateTimeLike, None]*, *optional*) – Timestamp to read to, by default None
- **from\_sample** (*Union[int, None]*, *optional*) – Sample to read from, by default None
- **to\_sample** (*Union[int, None]*, *optional*) – Sample to read to, by default None

**Returns**

The read TimeData

**Return type***TimeData***Raises***TimeDataReadError* – If unable to read data

```
resistics.letsgo.quick_view(dir_path: Path, config: Configuration | None = None, decimate: bool = False,  
max_pts: int = 10000)
```

Quick plotting of time data

**Parameters**

- **dir\_path** (*Path*) – The directory path
- **config** (*Optional[Configuration]*, *optional*) – The configuration with the required time readers, by default None
- **decimate** (*bool*, *optional*) – Boolean flag for decimating, by default False
- **max\_pts** (*Optional[int]*, *optional*) – Max points in lttb decimation, by default 10\_000

**Returns**

Plotly figure

**Return type***go.Figure***Raises***ValueError* – If time data fails reading

```
resistics.letsgo.quick_spectra(dir_path: Path, config: Configuration | None = None) → SpectraData
```

Quick plotting of time data

**Parameters**

- **dir\_path** (*Path*) – The directory path

- **config** (*Optional*[[Configuration](#)], *optional*) – The configuration with the required time readers, by default None

**Returns**

The spectra data

**Return type**

[SpectraData](#)

**Raises**

[ValueError](#) – If time data fails reading

`resistics.letsgo.quick_tf(dir_path: Path, config: Configuration | None = None, calibration_path: Path | None = None) → Solution`

Quickly calculate out a transfer function for time data in its own directory

**Parameters**

- **dir\_path** ([Path](#)) – The directory path
- **config** (*Optional*[[Configuration](#)], *optional*) – A configuration instance, by default None
- **calibration\_path** (*Optional*[[Path](#)], *optional*) – The path to the calibration data, by default None

**Returns**

Transfer function estimate

**Return type**

[Solution](#)

`resistics.letsgo.profile_windowing(dir_path: Path, config: Configuration | None = None, ref_time: str | Timestamp | datetime | None = None) → Dict[int, DataFrame]`

Profile windowing for a measurement

This function will return window tables for each decimation level. Note that any time processes are run first in case these changes the start or end time of the data.

**Parameters**

- **dir\_path** ([Path](#)) – Directory path of the time data
- **config** (*Optional*[[Configuration](#)], *optional*) – Configuration to use, by default None. If not provided, the default configuration will be used.
- **ref\_time** (*Optional*[[DateTimeLike](#)], *optional*) – A reference time to perform windowing against, by default None. If not provided, the start time of the recording will be used as the reference time.

**Returns**

Mapping from decimation level to a pandas [DataFrame](#) of the windows for the decimation level

**Return type**

[Dict](#)[[int](#), [pd.DataFrame](#)]

`resistics.letsgo.process_time(resenv: ResisticsEnvironment, site_name: str, meas_name: str, out_site: str, out_meas: str, input_from_time: str | Timestamp | datetime | None = None, input_to_time: str | Timestamp | datetime | None = None, output_from_time: str | Timestamp | datetime | None = None, output_to_time: str | Timestamp | datetime | None = None) → None`

Process time data and save as a new measurement

This is useful when resampling data to use with other measurements

#### Parameters

- **resenv** (`ResisticksEnvironment`) – The resisticks environment
- **site\_name** (`str`) – The name of the site with the data to process
- **meas\_name** (`str`) – The name of the measurement to process
- **out\_site** (`str`) – The site to output the data to
- **out\_meas** (`str`) – The name of the measurement to output the data to
- **input\_from\_time** (`Optional[DateTimeLike]`, `optional`) – Time to read data from for the input data, by default `None`. If `None`, the first time of the time series data is used.
- **input\_to\_time** (`Optional[DateTimeLike]`, `optional`) – Time to read data to for the input data, by default `None`. If `None`, the last time of the input time series data is used.
- **output\_from\_time** (`Optional[DateTimeLike]`, `optional`) – Time to output data from, by default `None`. If `None`, the first time of input data is used.
- **output\_to\_time** (`Optional[DateTimeLike]`, `optional`) – Time to output data to, by default `None`. If `None`, the last time of the input data is used.

```
resisticks.letsgo.process_time_to_evals(resenv: ResisticksEnvironment, site_name: str, meas_name: str)
                                     → None
```

Process from time data to Fourier spectra

#### Parameters

- **resenv** (`ResisticksEnvironment`) – The resisticks environment containing the project and configuration
- **site\_name** (`str`) – The name of the site
- **meas\_name** (`str`) – The name of the measurement to process

```
resisticks.letsgo.process_evals_to_tf(resenv: ResisticksEnvironment, fs: float, out_site: str, in_site: str |
                                     None = None, cross_site: str | None = None, masks: Dict[str, str] |
                                     None = None, postfix: str | None = None) → Solution
```

Process spectra to transfer functions

#### Parameters

- **resenv** (`ResisticksEnvironment`) – The resisticks environment
- **fs** (`float`) – The sampling frequency to process
- **out\_site** (`str`) – The name of the output site
- **in\_site** (`Optional[str]`, `optional`) – The name of the input site, by default `None`. This should be used for intersite processing
- **cross\_site** (`Optional[str]`, `optional`) – The name of the cross site, by default `None`. This is usually the site to use as the remote reference.
- **masks** (`Optional[Dict[str, str]]`, `optional`) – Any masks to apply, by default `None`
- **postfix** (`Optional[str]`) – String to add to the end of solution, by default `None`

#### Returns

Transfer function estimate

**Return type***Solution*

`resisticks.letsgo.get_solution(resenv: ResisticksEnvironment, site_name: str, config_name: str, fs: float, tf_name: str, tf_var: str, postfix: str | None = None) → Solution`

Get a solution

**Parameters**

- **resenv** (`ResisticksEnvironment`) – The resisticks environment
- **site\_name** (`str`) – The site for which to get the solution
- **config\_name** (`str`) – The configuration that was used
- **fs** (`float`) – The sampling frequency
- **tf\_name** (`str`) – The transfer function name
- **tf\_var** (`str`) – The transfer function variation
- **postfix** (`Optional[str]`, `optional`) – Any postfix on the solution, by default None

**Returns**

The solution

**Return type***Solution***resisticks.plot module**

Module to help plotting various data

`resisticks.plot.lttb_downsample(x: ndarray, y: ndarray, max_pts: int = 5000) → Tuple[ndarray, ndarray]`

Downsample x, y for visualisation

**Parameters**

- **x** (`np.ndarray`) – x array
- **y** (`np.ndarray`) – y array
- **max\_pts** (`int`, `optional`) – Maximum number of points after downsampling, by default 5000

**Returns**

(new\_x, new\_y), the downsampled x and y arrays

**Return type**

`Tuple[np.ndarray, np.ndarray]`

**Raises**

**ValueError** – If the size of x does not match the size of y

`resisticks.plot.apply_lttb(data: ndarray, max_pts: int | None) → Tuple[ndarray, ndarray]`

A helper function for applying lttb downsampling if max\_pts is not None

**Parameters**

- **data** (`np.ndarray`) – The data to downsample
- **max\_pts** (`Union[int, None]`) – The maximum number of points or None. If None, no downsampling is performed

**Returns**

Indices and data selected for plotting

**Return type**

Tuple[np.ndarray, np.ndarray]

`resisticks.plot.plot_timeline(df: DataFrame, y_col: str, title: str = 'Timeline', ref_time: Timestamp | None = None) → Figure`

Plot a timeline

**Parameters**

- **df** (*pd.DataFrame*) – DataFrame with the first and last times of the horizontal bars
- **y\_col** (*str*) – The column to use for the y axis
- **title** (*str*, *optional*) – The title for the plot, by default “Timeline”
- **ref\_time** (*Optional[pd.Timestamp]*, *optional*) – The reference time, by default None

**Returns**

Plotly figure

**Return type**

go.Figure

`resisticks.plot.get_calibration_fig() → Figure`

Get a figure for plotting calibration data

**Returns**

Plotly figure

**Return type**

go.Figure

`resisticks.plot.get_time_fig(chans: List[str], y_axis_label: Dict[str, str]) → Figure`

Get a figure for plotting time data

**Parameters**

- **chans** (*List[str]*) – The channels to plot
- **y\_axis\_label** (*Dict[str, str]*) – The labels to use for the y axis

**Returns**

Plotly figure

**Return type**

go.Figure

`resisticks.plot.get_spectra_stack_fig(chans: List[str], y_axis_label: Dict[str, str]) → Figure`

Get a figure for plotting spectra stack data

**Parameters**

- **chans** (*List[str]*) – The channels to plot
- **y\_axis\_label** (*Dict[str, str]*) – The y axis labels

**Returns**

Plotly figure

**Return type**

go.Figure

`resisticks.plot.get_spectra_section_fig(chans: List[str]) → Figure`

Get figure for plotting spectra sections

**Parameters**

**chans** (`List[str]`) – The channels to plot

**Returns**

Plotly figure

**Return type**

`go.Figure`

## resisticks.project module

Classes and methods to enable a resisticks project

A project is an essential element of a resisticks environment together with a configuration.

In particular, this module includes the core Project, Site and Measurement classes and some supporting functions.

`resisticks.project.get_calibration_path(proj_dir: Path) → Path`

Get the path to the calibration data

`resisticks.project.get_meas_time_path(proj_dir: Path, site_name: str, meas_name: str) → Path`

Get path to measurement time data

`resisticks.project.get_meas_spectra_path(proj_dir: Path, site_name: str, meas_name: str, config_name: str) → Path`

Get path to measurement spectra data

`resisticks.project.get_meas_evals_path(proj_dir: Path, site_name: str, meas_name: str, config_name: str) → Path`

Get path to measurement evaluation frequency spectra data

`resisticks.project.get_meas_features_path(proj_dir: Path, site_name: str, meas_name: str, config_name: str) → Path`

Get path to measurement features data

`resisticks.project.get_mask_path(proj_dir: Path, site_name: str, config_name: str) → Path`

Get path to mask data

`resisticks.project.get_mask_name(fs: float, mask_name: str) → str`

Get the name of a mask file

`resisticks.project.get_results_path(proj_dir: Path, site_name: str, config_name: str) → Path`

Get path to solutions

`resisticks.project.get_solution_name(fs: float, tf_name: str, tf_var: str, postfix: str | None = None) → str`

Get the name of a solution file

**pydantic model** `resisticks.project.Measurement`

Bases: `ResisticksModel`

Class for interfacing with a measurement

The class holds the original time series metadata and can provide information about other types of data

```

{
  "title": "Measurement",
  "description": "Class for interfacing with a measurement\n\nThe class holds the
↪original time series metadata and can provide\ninformation about other types of
↪data",
  "type": "object",
  "properties": {
    "site_name": {
      "title": "Site Name",
      "type": "string"
    },
    "dir_path": {
      "title": "Dir Path",
      "type": "string",
      "format": "path"
    },
    "metadata": {
      "$ref": "#/definitions/TimeMetadata"
    },
    "reader": {
      "$ref": "#/definitions/TimeReader"
    }
  },
  "required": [
    "site_name",
    "dir_path",
    "metadata",
    "reader"
  ],
  "definitions": {
    "ResisticksFile": {
      "title": "ResisticksFile",
      "description": "Required information for writing out a resisticks file",
      "type": "object",
      "properties": {
        "created_on_local": {
          "title": "Created On Local",
          "type": "string",
          "format": "date-time"
        },
        "created_on_utc": {
          "title": "Created On Utc",
          "type": "string",
          "format": "date-time"
        },
        "version": {
          "title": "Version",
          "type": "string"
        }
      }
    },
    "ChanMetadata": {

```

(continues on next page)



(continued from previous page)

```
"title": "ChanMetadata",
"description": "Channel metadata",
"type": "object",
"properties": {
  "name": {
    "title": "Name",
    "type": "string"
  },
  "data_files": {
    "title": "Data Files",
    "type": "array",
    "items": {
      "type": "string"
    }
  },
  "chan_type": {
    "title": "Chan Type",
    "type": "string"
  },
  "chan_source": {
    "title": "Chan Source",
    "type": "string"
  },
  "sensor": {
    "title": "Sensor",
    "default": "",
    "type": "string"
  },
  "serial": {
    "title": "Serial",
    "default": "",
    "type": "string"
  },
  "gain1": {
    "title": "Gain1",
    "default": 1,
    "type": "number"
  },
  "gain2": {
    "title": "Gain2",
    "default": 1,
    "type": "number"
  },
  "scaling": {
    "title": "Scaling",
    "default": 1,
    "type": "number"
  },
  "chopper": {
    "title": "Chopper",
    "default": false,
    "type": "boolean"
  }
}
```

(continues on next page)

(continued from previous page)

```

    },
    "dipole_dist": {
        "title": "Dipole Dist",
        "default": 1,
        "type": "number"
    },
    "sensor_calibration_file": {
        "title": "Sensor Calibration File",
        "default": "",
        "type": "string"
    },
    "instrument_calibration_file": {
        "title": "Instrument Calibration File",
        "default": "",
        "type": "string"
    }
},
"required": [
    "name"
]
},
"Record": {
    "title": "Record",
    "description": "Class to hold a record\n\nA record holds information about
→a process that was run. It is intended to\ntrack processes applied to data,
→allowing a process history to be saved\nalong with any datasets.\n\nExamples\n----
→----\nA simple example of creating a process record\n\n>>> from resistics.common
→import Record\n>>> messages = ["message 1", "message 2"]\n>>> record =
→Record(\n...     creator={"name": "example", "parameter1": 15},\n...     _
→messages=messages,\n...     record_type="example"\n... )\n>>> record.summary()\n
→{\n    'time_local': '...',\n    'time_utc': '...',\n    'creator': {'name':
→'example', 'parameter1': 15},\n    'messages': ['message 1', 'message 2'],\n
→'record_type': 'example'\n}",
    "type": "object",
    "properties": {
        "time_local": {
            "title": "Time Local",
            "type": "string",
            "format": "date-time"
        },
        "time_utc": {
            "title": "Time Utc",
            "type": "string",
            "format": "date-time"
        },
        "creator": {
            "title": "Creator",
            "type": "object"
        },
        "messages": {
            "title": "Messages",
            "type": "array",

```

(continues on next page)

(continued from previous page)

```

        "items": {
            "type": "string"
        }
    },
    "record_type": {
        "title": "Record Type",
        "type": "string"
    }
},
"required": [
    "creator",
    "messages",
    "record_type"
]
},
"History": {
    "title": "History",
    "description": "Class for storing processing history\n\nParameters\n-----
↪----\nrecords : List[Record], optional\n    List of records, by default []\n\
↪nExamples\n-----\n>>> from resistics.testing import record_example1, record_
↪example2\n>>> from resistics.common import History\n>>> record1 = record_
↪example1()\n>>> record2 = record_example2()\n>>> history =
↪History(records=[record1, record2])\n>>> history.summary()\n{\n    'records': [\n
↪    {\n        'time_local': '...',\n        'time_utc': '...',\n
↪    'creator': {\n        'name': 'example1',\n        'a': 5,\n
↪    'b': -7.0\n    },\n    'messages': ['Message 1',
↪'Message 2'],\n    'record_type': 'process'\n    },\n    {\n
↪    'time_local': '...',\n    'time_utc': '...',\n    'creator
↪': {\n        'name': 'example2',\n        'a': 'parzen',\n
↪    'b': -21\n    },\n    'messages': ['Message 5', 'Message
↪6'],\n    'record_type': 'process'\n    }\n    ]\n}",
    "type": "object",
    "properties": {
        "records": {
            "title": "Records",
            "default": [],
            "type": "array",
            "items": {
                "$ref": "#/definitions/Record"
            }
        }
    }
},
},
"TimeMetadata": {
    "title": "TimeMetadata",
    "description": "Time metadata",
    "type": "object",
    "properties": {
        "file_info": {
            "$ref": "#/definitions/ResisticsFile"
        },
        "fs": {

```

(continues on next page)

(continued from previous page)

```

        "title": "Fs",
        "type": "number"
    },
    "chans": {
        "title": "Chans",
        "type": "array",
        "items": {
            "type": "string"
        }
    },
    "n_chans": {
        "title": "N Chans",
        "type": "integer"
    },
    "n_samples": {
        "title": "N Samples",
        "type": "integer"
    },
    "first_time": {
        "title": "First Time",
        "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
        "examples": [
            "2021-01-01 00:00:00.000061_035156_250000_000000"
        ]
    },
    "last_time": {
        "title": "Last Time",
        "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
        "examples": [
            "2021-01-01 00:00:00.000061_035156_250000_000000"
        ]
    },
    "system": {
        "title": "System",
        "default": "",
        "type": "string"
    },
    "serial": {
        "title": "Serial",
        "default": "",
        "type": "string"
    },
    "wgs84_latitude": {
        "title": "Wgs84 Latitude",
        "default": -999.0,
        "type": "number"
    },
    "wgs84_longitude": {
        "title": "Wgs84 Longitude",
        "default": -999.0,
        "type": "number"
    },
    },

```

(continues on next page)

(continued from previous page)

```

    "easting": {
      "title": "Easting",
      "default": -999.0,
      "type": "number"
    },
    "northing": {
      "title": "Northing",
      "default": -999.0,
      "type": "number"
    },
    "elevation": {
      "title": "Elevation",
      "default": -999.0,
      "type": "number"
    },
    "chans_metadata": {
      "title": "Chans Metadata",
      "type": "object",
      "additionalProperties": {
        "$ref": "#/definitions/ChanMetadata"
      }
    },
    "history": {
      "title": "History",
      "default": {
        "records": []
      },
      "allOf": [
        {
          "$ref": "#/definitions/History"
        }
      ]
    },
  },
  "required": [
    "fs",
    "chans",
    "n_samples",
    "first_time",
    "last_time",
    "chans_metadata"
  ],
  "TimeReader": {
    "title": "TimeReader",
    "description": "Base class for resistics processes\n\nResistics processes_
↪perform operations on data (including read and write\noperations). Each time a_
↪ResisticsProcess child class is run, it should add\na process record to the_
↪dataset",
    "type": "object",
    "properties": {
      "name": {

```

(continues on next page)

(continued from previous page)

```

        "title": "Name",
        "type": "string"
    },
    "apply_scalings": {
        "title": "Apply Scalings",
        "default": true,
        "type": "boolean"
    },
    "extension": {
        "title": "Extension",
        "type": "string"
    }
}
}
}
}

```

field site\_name: `str` [Required]

field dir\_path: `Path` [Required]

field metadata: `TimeMetadata` [Required]

field reader: `TimeReader` [Required]

property name: `str`

Get the name of the measurement

**pydantic model** `resistics.project.Site`

Bases: `ResisticsModel`

Class for describing Sites

---

**Note:** This should essentially describe a single instrument setup. If the same site is re-occupied later with a different instrument setup, it is suggested to split this into a different site.

---

```

{
  "title": "Site",
  "description": "Class for describing Sites\n\n.. note::\n\n    This should_\n↪essentially describe a single instrument setup. If the same_\n↪site is re-\n↪occupied later with a different instrument setup, it is_\n↪suggested to split_\n↪this into a different site.",
  "type": "object",
  "properties": {
    "dir_path": {
      "title": "Dir Path",
      "type": "string",
      "format": "path"
    },
    "measurements": {
      "title": "Measurements",
      "type": "object",

```

(continues on next page)

(continued from previous page)

```

    "additionalProperties": {
      "$ref": "#/definitions/Measurement"
    }
  },
  "begin_time": {
    "title": "Begin Time",
    "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
    "examples": [
      "2021-01-01 00:00:00.000061_035156_250000_000000"
    ]
  },
  "end_time": {
    "title": "End Time",
    "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
    "examples": [
      "2021-01-01 00:00:00.000061_035156_250000_000000"
    ]
  }
},
"required": [
  "dir_path",
  "measurements",
  "begin_time",
  "end_time"
],
"definitions": {
  "ResisticksFile": {
    "title": "ResisticksFile",
    "description": "Required information for writing out a resisticks file",
    "type": "object",
    "properties": {
      "created_on_local": {
        "title": "Created On Local",
        "type": "string",
        "format": "date-time"
      },
      "created_on_utc": {
        "title": "Created On Utc",
        "type": "string",
        "format": "date-time"
      },
      "version": {
        "title": "Version",
        "type": "string"
      }
    }
  }
},
"ChanMetadata": {
  "title": "ChanMetadata",
  "description": "Channel metadata",
  "type": "object",
  "properties": {

```

(continues on next page)

(continued from previous page)

```
"name": {
  "title": "Name",
  "type": "string"
},
"data_files": {
  "title": "Data Files",
  "type": "array",
  "items": {
    "type": "string"
  }
},
"chan_type": {
  "title": "Chan Type",
  "type": "string"
},
"chan_source": {
  "title": "Chan Source",
  "type": "string"
},
"sensor": {
  "title": "Sensor",
  "default": "",
  "type": "string"
},
"serial": {
  "title": "Serial",
  "default": "",
  "type": "string"
},
"gain1": {
  "title": "Gain1",
  "default": 1,
  "type": "number"
},
"gain2": {
  "title": "Gain2",
  "default": 1,
  "type": "number"
},
"scaling": {
  "title": "Scaling",
  "default": 1,
  "type": "number"
},
"chopper": {
  "title": "Chopper",
  "default": false,
  "type": "boolean"
},
"dipole_dist": {
  "title": "Dipole Dist",
  "default": 1,
```

(continues on next page)



(continued from previous page)

```

        "type": "number"
    },
    "sensor_calibration_file": {
        "title": "Sensor Calibration File",
        "default": "",
        "type": "string"
    },
    "instrument_calibration_file": {
        "title": "Instrument Calibration File",
        "default": "",
        "type": "string"
    }
},
"required": [
    "name"
]
},
"Record": {
    "title": "Record",
    "description": "Class to hold a record\n\nA record holds information about
→a process that was run. It is intended to\ntrack processes applied to data,
→allowing a process history to be saved\nalong with any datasets.\n\nExamples\n----
→----\nA simple example of creating a process record\n\n>>> from resistics.common
→import Record\n>>> messages = ["message 1", "message 2"]\n>>> record =
→Record(\n...     creator={"name": "example", "parameter1": 15},\n...
→messages=messages,\n...     record_type="example"\n... )\n>>> record.summary()\n
→{\n  'time_local': '...',\n  'time_utc': '...',\n  'creator': {'name':
→'example', 'parameter1': 15},\n  'messages': ['message 1', 'message 2'],\n
→'record_type': 'example'\n}",
    "type": "object",
    "properties": {
        "time_local": {
            "title": "Time Local",
            "type": "string",
            "format": "date-time"
        },
        "time_utc": {
            "title": "Time Utc",
            "type": "string",
            "format": "date-time"
        },
        "creator": {
            "title": "Creator",
            "type": "object"
        },
        "messages": {
            "title": "Messages",
            "type": "array",
            "items": {
                "type": "string"
            }
        }
    }
},

```

(continues on next page)

(continued from previous page)

```

        "record_type": {
            "title": "Record Type",
            "type": "string"
        }
    },
    "required": [
        "creator",
        "messages",
        "record_type"
    ]
},
"History": {
    "title": "History",
    "description": "Class for storing processing history\n\nParameters\n-----
↪---\nrecords : List[Record], optional\n    List of records, by default []\n\
↪nExamples\n-----\n>>> from resistics.testing import record_example1, record_
↪example2\n>>> from resistics.common import History\n>>> record1 = record_
↪example1()\n>>> record2 = record_example2()\n>>> history =
↪History(records=[record1, record2])\n>>> history.summary()\n{\n    'records': [\n
↪    {\n        'time_local': '...',\n        'time_utc': '...',\n
↪    'creator': {\n        'name': 'example1',\n        'a': 5,\n
↪    'b': -7.0\n        },\n        'messages': ['Message 1',
↪'Message 2'],\n        'record_type': 'process'\n        },\n        {\n
↪    'time_local': '...',\n        'time_utc': '...',\n        'creator
↪': {\n        'name': 'example2',\n        'a': 'parzen',\n
↪    'b': -21\n        },\n        'messages': ['Message 5', 'Message
↪6'],\n        'record_type': 'process'\n        }\n    ]\n}",
    "type": "object",
    "properties": {
        "records": {
            "title": "Records",
            "default": [],
            "type": "array",
            "items": {
                "$ref": "#/definitions/Record"
            }
        }
    }
},
"TimeMetadata": {
    "title": "TimeMetadata",
    "description": "Time metadata",
    "type": "object",
    "properties": {
        "file_info": {
            "$ref": "#/definitions/ResisticsFile"
        },
        "fs": {
            "title": "Fs",
            "type": "number"
        },
        "chans": {

```

(continues on next page)

(continued from previous page)

```

        "title": "Chans",
        "type": "array",
        "items": {
            "type": "string"
        }
    },
    "n_chans": {
        "title": "N Chans",
        "type": "integer"
    },
    "n_samples": {
        "title": "N Samples",
        "type": "integer"
    },
    "first_time": {
        "title": "First Time",
        "pattern": "%Y-%m-%d %H:%M:%S.%f_o_%q_%v",
        "examples": [
            "2021-01-01 00:00:00.000061_035156_250000_000000"
        ]
    },
    "last_time": {
        "title": "Last Time",
        "pattern": "%Y-%m-%d %H:%M:%S.%f_o_%q_%v",
        "examples": [
            "2021-01-01 00:00:00.000061_035156_250000_000000"
        ]
    },
    "system": {
        "title": "System",
        "default": "",
        "type": "string"
    },
    "serial": {
        "title": "Serial",
        "default": "",
        "type": "string"
    },
    "wgs84_latitude": {
        "title": "Wgs84 Latitude",
        "default": -999.0,
        "type": "number"
    },
    "wgs84_longitude": {
        "title": "Wgs84 Longitude",
        "default": -999.0,
        "type": "number"
    },
    "easting": {
        "title": "Easting",
        "default": -999.0,
        "type": "number"
    }

```

(continues on next page)

(continued from previous page)

```

    },
    "northing": {
      "title": "Northing",
      "default": -999.0,
      "type": "number"
    },
    "elevation": {
      "title": "Elevation",
      "default": -999.0,
      "type": "number"
    },
    "chans_metadata": {
      "title": "Chans Metadata",
      "type": "object",
      "additionalProperties": {
        "$ref": "#/definitions/ChanMetadata"
      }
    },
    "history": {
      "title": "History",
      "default": {
        "records": []
      },
      "allOf": [
        {
          "$ref": "#/definitions/History"
        }
      ]
    },
  ],
  "required": [
    "fs",
    "chans",
    "n_samples",
    "first_time",
    "last_time",
    "chans_metadata"
  ],
},
"TimeReader": {
  "title": "TimeReader",
  "description": "Base class for resistics processes\n\nResistivity processes_
↪ perform operations on data (including read and write\noperations). Each time a_
↪ ResistivityProcess child class is run, it should add\na process record to the_
↪ dataset",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
  },
  "apply_scalings": {

```

(continues on next page)

(continued from previous page)

```

        "title": "Apply Scalings",
        "default": true,
        "type": "boolean"
    },
    "extension": {
        "title": "Extension",
        "type": "string"
    }
}
},
"Measurement": {
    "title": "Measurement",
    "description": "Class for interfacing with a measurement\n\nThe class
→holds the original time series metadata and can provide\ninformation about other
→types of data",
    "type": "object",
    "properties": {
        "site_name": {
            "title": "Site Name",
            "type": "string"
        },
        "dir_path": {
            "title": "Dir Path",
            "type": "string",
            "format": "path"
        },
        "metadata": {
            "$ref": "#/definitions/TimeMetadata"
        },
        "reader": {
            "$ref": "#/definitions/TimeReader"
        }
    },
    "required": [
        "site_name",
        "dir_path",
        "metadata",
        "reader"
    ]
}
}
}

```

field `dir_path`: `Path` [Required]

field `measurements`: `Dict[str, Measurement]` [Required]

field `begin_time`: `HighResDateTime` [Required]

#### Constraints

- `pattern` = `%Y-%m-%d %H:%M:%S.%f_%o_%q_%v`
- `examples` = `['2021-01-01 00:00:00.000061_035156_250000_000000']`

field **end\_time**: *HighResDateTime* [Required]

**Constraints**

- **pattern** = %Y-%m-%d %H:%M:%S.%f\_%o\_%q\_%v
- **examples** = ['2021-01-01 00:00:00.000061\_035156\_250000\_000000']

property **name**: *str*

The Site name

property **n\_meas**: *int*

Get the number of measurements

**fs()** → *List[float]*

Get the sampling frequencies in the Site

**get\_measurement**(*meas\_name: str*) → *Measurement*

Get a measurement

**get\_measurements**(*fs: float | None = None*) → *Dict[str, Measurement]*

Get dictionary of measurements with optional filter by sampling frequency

**plot()** → *Figure*

Plot the site timeline

**to\_dataframe()** → *DataFrame*

Get measurements list in a pandas DataFrame

---

**Note:** Measurement first and last times are converted to pandas Timestamps as these are more universally useful in a pandas DataFrame. However, this may result in a loss of precision, especially at high sampling frequencies.

---

**Returns**

Site measurement DataFrame

**Return type**

pd.DataFrame

**pydantic model** `resistics.project.ProjectMetadata`

Bases: *WriteableMetadata*

Project metadata

```
{
  "title": "ProjectMetadata",
  "description": "Project metadata",
  "type": "object",
  "properties": {
    "file_info": {
      "$ref": "#/definitions/ResisticsFile"
    },
    "ref_time": {
      "title": "Ref Time",
      "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
      "examples": [
```

(continues on next page)

(continued from previous page)

```

        "2021-01-01 00:00:00.000061_035156_250000_000000"
    ]
},
"location": {
    "title": "Location",
    "default": "",
    "type": "string"
},
"country": {
    "title": "Country",
    "default": "",
    "type": "string"
},
"year": {
    "title": "Year",
    "default": -999,
    "type": "integer"
},
"description": {
    "title": "Description",
    "default": "",
    "type": "string"
},
"contributors": {
    "title": "Contributors",
    "default": [],
    "type": "array",
    "items": {
        "type": "string"
    }
}
},
"required": [
    "ref_time"
],
"definitions": {
    "ResisticsFile": {
        "title": "ResisticsFile",
        "description": "Required information for writing out a resistics file",
        "type": "object",
        "properties": {
            "created_on_local": {
                "title": "Created On Local",
                "type": "string",
                "format": "date-time"
            },
            "created_on_utc": {
                "title": "Created On Utc",
                "type": "string",
                "format": "date-time"
            },
            "version": {

```

(continues on next page)

(continued from previous page)

```

        "title": "Version",
        "type": "string"
    }
}
}
}
}

```

field `ref_time`: *HighResDateTime* [Required]

#### Constraints

- `pattern` = %Y-%m-%d %H:%M:%S.%f\_%o\_%q\_%v
- `examples` = ['2021-01-01 00:00:00.000061\_035156\_250000\_000000']

field `location`: `str` = ''

field `country`: `str` = ''

field `year`: `int` = -999

field `description`: `str` = ''

field `contributors`: `List[str]` = []

pydantic model `resistics.project.Project`

Bases: *ResisticsModel*

Class to describe a resistics project

The resistics Project Class connects all resistics data. It is an essential part of processing data with resistics.

Resistics projects are in directory with several sub-directories. Project metadata is saved in the `resistics.json` file at the top level directory.

```

{
  "title": "Project",
  "description": "Class to describe a resistics project\n\nThe resistics Project_\n↪Class connects all resistics data. It is an essential\npart of processing data_\n↪with resistics.\n\nResistics projects are in directory with several sub-\n↪directories. Project\nmetadata is saved in the resistics.json file at the top_\n↪level directory.",
  "type": "object",
  "properties": {
    "dir_path": {
      "title": "Dir Path",
      "type": "string",
      "format": "path"
    },
    "begin_time": {
      "title": "Begin Time",
      "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
      "examples": [
        "2021-01-01 00:00:00.000061_035156_250000_000000"
      ]
    }
  }
}

```

(continues on next page)



(continued from previous page)

```

    },
    "end_time": {
      "title": "End Time",
      "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
      "examples": [
        "2021-01-01 00:00:00.000061_035156_250000_000000"
      ]
    },
    "metadata": {
      "$ref": "#/definitions/ProjectMetadata"
    },
    "sites": {
      "title": "Sites",
      "default": {},
      "type": "object",
      "additionalProperties": {
        "$ref": "#/definitions/Site"
      }
    }
  },
  "required": [
    "dir_path",
    "begin_time",
    "end_time",
    "metadata"
  ],
  "definitions": {
    "ResisticsFile": {
      "title": "ResisticsFile",
      "description": "Required information for writing out a resistics file",
      "type": "object",
      "properties": {
        "created_on_local": {
          "title": "Created On Local",
          "type": "string",
          "format": "date-time"
        },
        "created_on_utc": {
          "title": "Created On Utc",
          "type": "string",
          "format": "date-time"
        },
        "version": {
          "title": "Version",
          "type": "string"
        }
      }
    },
    "ProjectMetadata": {
      "title": "ProjectMetadata",
      "description": "Project metadata",
      "type": "object",

```

(continues on next page)

(continued from previous page)

```

"properties": {
  "file_info": {
    "$ref": "#/definitions/ResisticsFile"
  },
  "ref_time": {
    "title": "Ref Time",
    "pattern": "%Y-%m-%d %H:%M:%S.%f_o_%q_%v",
    "examples": [
      "2021-01-01 00:00:00.000061_035156_250000_000000"
    ]
  },
  "location": {
    "title": "Location",
    "default": "",
    "type": "string"
  },
  "country": {
    "title": "Country",
    "default": "",
    "type": "string"
  },
  "year": {
    "title": "Year",
    "default": -999,
    "type": "integer"
  },
  "description": {
    "title": "Description",
    "default": "",
    "type": "string"
  },
  "contributors": {
    "title": "Contributors",
    "default": [],
    "type": "array",
    "items": {
      "type": "string"
    }
  }
},
"required": [
  "ref_time"
],
"ChanMetadata": {
  "title": "ChanMetadata",
  "description": "Channel metadata",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    }
  }
}

```

(continues on next page)

(continued from previous page)

```

    },
    "data_files": {
      "title": "Data Files",
      "type": "array",
      "items": {
        "type": "string"
      }
    },
    "chan_type": {
      "title": "Chan Type",
      "type": "string"
    },
    "chan_source": {
      "title": "Chan Source",
      "type": "string"
    },
    "sensor": {
      "title": "Sensor",
      "default": "",
      "type": "string"
    },
    "serial": {
      "title": "Serial",
      "default": "",
      "type": "string"
    },
    "gain1": {
      "title": "Gain1",
      "default": 1,
      "type": "number"
    },
    "gain2": {
      "title": "Gain2",
      "default": 1,
      "type": "number"
    },
    "scaling": {
      "title": "Scaling",
      "default": 1,
      "type": "number"
    },
    "chopper": {
      "title": "Chopper",
      "default": false,
      "type": "boolean"
    },
    "dipole_dist": {
      "title": "Dipole Dist",
      "default": 1,
      "type": "number"
    },
    "sensor_calibration_file": {

```

(continues on next page)

(continued from previous page)

```

        "title": "Sensor Calibration File",
        "default": "",
        "type": "string"
    },
    "instrument_calibration_file": {
        "title": "Instrument Calibration File",
        "default": "",
        "type": "string"
    }
},
"required": [
    "name"
]
},
"Record": {
    "title": "Record",
    "description": "Class to hold a record\n\nA record holds information about
↪ a process that was run. It is intended to\ntrack processes applied to data,
↪ allowing a process history to be saved\nalong with any datasets.\n\nExamples\n----
↪ ----\nA simple example of creating a process record\n\n>>> from resistics.common
↪ import Record\n>>> messages = ["message 1", "message 2"]\n>>> record =
↪ Record(\n...     creator={"name": "example", "parameter1": 15},\n...     ↪
↪ messages=messages,\n...     record_type="example"\n... )\n>>> record.summary()\n
↪ {\n    'time_local': '...',\n    'time_utc': '...',\n    'creator': {'name':
↪ 'example', 'parameter1': 15},\n    'messages': ['message 1', 'message 2'],\n
↪ 'record_type': 'example'\n}",
    "type": "object",
    "properties": {
        "time_local": {
            "title": "Time Local",
            "type": "string",
            "format": "date-time"
        },
        "time_utc": {
            "title": "Time Utc",
            "type": "string",
            "format": "date-time"
        },
        "creator": {
            "title": "Creator",
            "type": "object"
        },
        "messages": {
            "title": "Messages",
            "type": "array",
            "items": {
                "type": "string"
            }
        },
        "record_type": {
            "title": "Record Type",
            "type": "string"
        }
    }
}

```

(continues on next page)

(continued from previous page)

```

    }
  },
  "required": [
    "creator",
    "messages",
    "record_type"
  ],
  "History": {
    "title": "History",
    "description": "Class for storing processing history\n\nParameters\n-----
↪---\nrecords : List[Record], optional\n    List of records, by default []\n\n
↪nExamples\n-----\n>>> from resistics.testing import record_example1, record_
↪example2\n>>> from resistics.common import History\n>>> record1 = record_
↪example1()\n>>> record2 = record_example2()\n>>> history =
↪History(records=[record1, record2])\n>>> history.summary()\n{\n    'records': [\n
↪    {\n        'time_local': '...',\n        'time_utc': '...',\n
↪    'creator': {\n        'name': 'example1',\n        'a': 5,\n
↪    'b': -7.0\n    },\n    'messages': ['Message 1',
↪'Message 2'],\n    'record_type': 'process'\n    },\n    {\n
↪    'time_local': '...',\n    'time_utc': '...',\n    'creator
↪': {\n        'name': 'example2',\n        'a': 'parzen',\n
↪    'b': -21\n    },\n    'messages': ['Message 5', 'Message
↪6'],\n    'record_type': 'process'\n    }\n    ]\n}",
    "type": "object",
    "properties": {
      "records": {
        "title": "Records",
        "default": [],
        "type": "array",
        "items": {
          "$ref": "#/definitions/Record"
        }
      }
    }
  },
  "TimeMetadata": {
    "title": "TimeMetadata",
    "description": "Time metadata",
    "type": "object",
    "properties": {
      "file_info": {
        "$ref": "#/definitions/ResisticsFile"
      },
      "fs": {
        "title": "Fs",
        "type": "number"
      },
      "chans": {
        "title": "Chans",
        "type": "array",
        "items": {

```

(continues on next page)

(continued from previous page)

```

        "type": "string"
    },
    "n_chans": {
        "title": "N Chans",
        "type": "integer"
    },
    "n_samples": {
        "title": "N Samples",
        "type": "integer"
    },
    "first_time": {
        "title": "First Time",
        "pattern": "%Y-%m-%d %H:%M:%S.%f_o_%q_%v",
        "examples": [
            "2021-01-01 00:00:00.000061_035156_250000_000000"
        ]
    },
    "last_time": {
        "title": "Last Time",
        "pattern": "%Y-%m-%d %H:%M:%S.%f_o_%q_%v",
        "examples": [
            "2021-01-01 00:00:00.000061_035156_250000_000000"
        ]
    },
    "system": {
        "title": "System",
        "default": "",
        "type": "string"
    },
    "serial": {
        "title": "Serial",
        "default": "",
        "type": "string"
    },
    "wgs84_latitude": {
        "title": "Wgs84 Latitude",
        "default": -999.0,
        "type": "number"
    },
    "wgs84_longitude": {
        "title": "Wgs84 Longitude",
        "default": -999.0,
        "type": "number"
    },
    "easting": {
        "title": "Easting",
        "default": -999.0,
        "type": "number"
    },
    "northing": {
        "title": "Northing",

```

(continues on next page)

(continued from previous page)

```

        "default": -999.0,
        "type": "number"
    },
    "elevation": {
        "title": "Elevation",
        "default": -999.0,
        "type": "number"
    },
    "chans_metadata": {
        "title": "Chans Metadata",
        "type": "object",
        "additionalProperties": {
            "$ref": "#/definitions/ChanMetadata"
        }
    },
    "history": {
        "title": "History",
        "default": {
            "records": []
        },
        "allOf": [
            {
                "$ref": "#/definitions/History"
            }
        ]
    },
    ],
    "required": [
        "fs",
        "chans",
        "n_samples",
        "first_time",
        "last_time",
        "chans_metadata"
    ],
    "TimeReader": {
        "title": "TimeReader",
        "description": "Base class for resistics processes\n\nResistics processes_
↪perform operations on data (including read and write\noperations). Each time a_
↪ResisticsProcess child class is run, it should add\na process record to the_
↪dataset",
        "type": "object",
        "properties": {
            "name": {
                "title": "Name",
                "type": "string"
            },
            "apply_scalings": {
                "title": "Apply Scalings",
                "default": true,
                "type": "boolean"
            }
        }
    }
}

```

(continues on next page)

(continued from previous page)

```

    },
    "extension": {
      "title": "Extension",
      "type": "string"
    }
  },
  "Measurement": {
    "title": "Measurement",
    "description": "Class for interfacing with a measurement\n\nThe class_
↪holds the original time series metadata and can provide\ninformation about other_
↪types of data",
    "type": "object",
    "properties": {
      "site_name": {
        "title": "Site Name",
        "type": "string"
      },
      "dir_path": {
        "title": "Dir Path",
        "type": "string",
        "format": "path"
      },
      "metadata": {
        "$ref": "#/definitions/TimeMetadata"
      },
      "reader": {
        "$ref": "#/definitions/TimeReader"
      }
    },
    "required": [
      "site_name",
      "dir_path",
      "metadata",
      "reader"
    ]
  },
  "Site": {
    "title": "Site",
    "description": "Class for describing Sites\n\n.. note::\n\n    This should_
↪essentially describe a single instrument setup. If the same\n    site is re-
↪occupied later with a different instrument setup, it is\n    suggested to split_
↪this into a different site.",
    "type": "object",
    "properties": {
      "dir_path": {
        "title": "Dir Path",
        "type": "string",
        "format": "path"
      },
      "measurements": {
        "title": "Measurements",

```

(continues on next page)



(continued from previous page)

```

        "type": "object",
        "additionalProperties": {
            "$ref": "#/definitions/Measurement"
        }
    },
    "begin_time": {
        "title": "Begin Time",
        "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
        "examples": [
            "2021-01-01 00:00:00.000061_035156_250000_000000"
        ]
    },
    "end_time": {
        "title": "End Time",
        "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
        "examples": [
            "2021-01-01 00:00:00.000061_035156_250000_000000"
        ]
    },
    "required": [
        "dir_path",
        "measurements",
        "begin_time",
        "end_time"
    ]
}

```

field `dir_path`: `Path` [Required]

field `begin_time`: `HighResDateTime` [Required]

#### Constraints

- `pattern` = `%Y-%m-%d %H:%M:%S.%f_%o_%q_%v`
- `examples` = `['2021-01-01 00:00:00.000061_035156_250000_000000']`

field `end_time`: `HighResDateTime` [Required]

#### Constraints

- `pattern` = `%Y-%m-%d %H:%M:%S.%f_%o_%q_%v`
- `examples` = `['2021-01-01 00:00:00.000061_035156_250000_000000']`

field `metadata`: `ProjectMetadata` [Required]

field `sites`: `Dict[str, Site]` = {}

property `n_sites`: `int`

The number of sites

`fs()` → `List[float]`

Get sampling frequencies in the Project

**get\_site**(*site\_name: str*) → *Site*

Get a Site object given the Site name

**get\_sites**(*fs: float | None = None*) → *Dict[str, Site]*

Get sites

**Parameters**

**fs** (*Optional[float]*, *optional*) – Filter by sites which have at least a single recording at a specified sampling frequency, by default None

**Returns**

Dictionary of site name to Site

**Return type**

*Dict[str, Site]*

**get\_concurrent**(*site\_name: str*) → *List[Site]*

Find sites that recorded concurrently to a specified site

**Parameters**

**site\_name** (*str*) – Search for sites recording concurrently to this site

**Returns**

List of Site instances which were recording concurrently

**Return type**

*List[Site]*

**plot**() → *Figure*

Plot a timeline of the project

**to\_dataframe**() → *DataFrame*

Detail Project recordings in a DataFrame

## resistics.regression module

The regression module provides functions and classes for the following:

- Preparing gathered data for regression
- Performing the linear regression

Resistics has built in solvers that use scikit learn models, namely

- Ordinary least squares
- RANSAC
- TheilSen

These will perform well in many scenarios. However, the functionality available in resistics makes it possible to use custom solvers if required.

**pydantic model** `resistics.regression.RegressionInputMetadata`

Bases: *Metadata*

Metadata for regression input data, mainly to track processing history

```

{
  "title": "RegressionInputMetadata",
  "description": "Metadata for regression input data, mainly to track processing.↵
↵history",
  "type": "object",
  "properties": {
    "contributors": {
      "title": "Contributors",
      "type": "object",
      "additionalProperties": {
        "anyOf": [
          {
            "$ref": "#/definitions/SiteCombinedMetadata"
          },
          {
            "$ref": "#/definitions/SpectraMetadata"
          }
        ]
      }
    },
    "history": {
      "title": "History",
      "default": {
        "records": []
      },
      "allOf": [
        {
          "$ref": "#/definitions/History"
        }
      ]
    }
  },
  "required": [
    "contributors"
  ],
  "definitions": {
    "ResisticsFile": {
      "title": "ResisticsFile",
      "description": "Required information for writing out a resistics file",
      "type": "object",
      "properties": {
        "created_on_local": {
          "title": "Created On Local",
          "type": "string",
          "format": "date-time"
        },
        "created_on_utc": {
          "title": "Created On Utc",
          "type": "string",
          "format": "date-time"
        },
        "version": {

```

(continues on next page)

(continued from previous page)

```

        "title": "Version",
        "type": "string"
    }
},
"Record": {
    "title": "Record",
    "description": "Class to hold a record\n\nA record holds information about
↪a process that was run. It is intended to\ntrack processes applied to data,
↪allowing a process history to be saved\nalong with any datasets.\n\nExamples\n----
↪----\nA simple example of creating a process record\n\n>>> from resistics.common
↪import Record\n>>> messages = [\"message 1\", \"message 2\"]\n>>> record =
↪Record(\n...     creator={\"name\": \"example\", \"parameter1\": 15},\n...
↪messages=messages,\n...     record_type=\"example\"\n... )\n>>> record.summary()\n
↪{\n  'time_local': '...',\n  'time_utc': '...',\n  'creator': {'name':
↪'example', 'parameter1': 15},\n  'messages': ['message 1', 'message 2'],\n
↪'record_type': 'example'\n}",
    "type": "object",
    "properties": {
        "time_local": {
            "title": "Time Local",
            "type": "string",
            "format": "date-time"
        },
        "time_utc": {
            "title": "Time Utc",
            "type": "string",
            "format": "date-time"
        },
        "creator": {
            "title": "Creator",
            "type": "object"
        },
        "messages": {
            "title": "Messages",
            "type": "array",
            "items": {
                "type": "string"
            }
        },
        "record_type": {
            "title": "Record Type",
            "type": "string"
        }
    },
    "required": [
        "creator",
        "messages",
        "record_type"
    ]
},
"History": {

```

(continues on next page)

(continued from previous page)

```

        "title": "History",
        "description": "Class for storing processing history\n\nParameters\n-----
↪---\nrecords : List[Record], optional\n    List of records, by default []\n\
↪nExamples\n-----\n>>> from resistics.testing import record_example1, record_
↪example2\n>>> from resistics.common import History\n>>> record1 = record_
↪example1()\n>>> record2 = record_example2()\n>>> history =
↪History(records=[record1, record2])\n>>> history.summary()\n{\n    'records': [\n
↪    {\n        'time_local': '...',\n        'time_utc': '...',\n
↪    'creator': {\n        'name': 'example1',\n        'a': 5,\n
↪    'b': -7.0\n    },\n    'messages': ['Message 1',
↪'Message 2'],\n    'record_type': 'process'\n    },\n    {\n
↪    'time_local': '...',\n    'time_utc': '...',\n    'creator
↪': {\n        'name': 'example2',\n        'a': 'parzen',\n
↪    'b': -21\n    },\n    'messages': ['Message 5', 'Message
↪6'],\n    'record_type': 'process'\n    }\n    ]\n}",
        "type": "object",
        "properties": {
            "records": {
                "title": "Records",
                "default": [],
                "type": "array",
                "items": {
                    "$ref": "#/definitions/Record"
                }
            }
        }
    },
    "SiteCombinedMetadata": {
        "title": "SiteCombinedMetadata",
        "description": "Metadata for combined data\n\nCombined metadata stores
↪metadata for measurements that are combined from\na single site.",
        "type": "object",
        "properties": {
            "file_info": {
                "$ref": "#/definitions/ResisticsFile"
            },
            "site_name": {
                "title": "Site Name",
                "type": "string"
            },
            "fs": {
                "title": "Fs",
                "type": "number"
            },
            "system": {
                "title": "System",
                "default": "",
                "type": "string"
            },
            "serial": {
                "title": "Serial",
                "default": "",

```

(continues on next page)

(continued from previous page)

```

        "type": "string"
    },
    "wgs84_latitude": {
        "title": "Wgs84 Latitude",
        "default": -999.0,
        "type": "number"
    },
    "wgs84_longitude": {
        "title": "Wgs84 Longitude",
        "default": -999.0,
        "type": "number"
    },
    "easting": {
        "title": "Easting",
        "default": -999.0,
        "type": "number"
    },
    "northing": {
        "title": "Northing",
        "default": -999.0,
        "type": "number"
    },
    "elevation": {
        "title": "Elevation",
        "default": -999.0,
        "type": "number"
    },
    "measurements": {
        "title": "Measurements",
        "type": "array",
        "items": {
            "type": "string"
        }
    },
    "chans": {
        "title": "Chans",
        "type": "array",
        "items": {
            "type": "string"
        }
    },
    "n_evals": {
        "title": "N Evals",
        "type": "integer"
    },
    "eval_freqs": {
        "title": "Eval Freqs",
        "type": "array",
        "items": {
            "type": "number"
        }
    },
    },

```

(continues on next page)

(continued from previous page)

```

    "histories": {
      "title": "Histories",
      "type": "object",
      "additionalProperties": {
        "$ref": "#/definitions/History"
      }
    },
    "required": [
      "site_name",
      "fs",
      "chans",
      "n_evals",
      "eval_freqs",
      "histories"
    ],
    "ChanMetadata": {
      "title": "ChanMetadata",
      "description": "Channel metadata",
      "type": "object",
      "properties": {
        "name": {
          "title": "Name",
          "type": "string"
        },
        "data_files": {
          "title": "Data Files",
          "type": "array",
          "items": {
            "type": "string"
          }
        },
        "chan_type": {
          "title": "Chan Type",
          "type": "string"
        },
        "chan_source": {
          "title": "Chan Source",
          "type": "string"
        },
        "sensor": {
          "title": "Sensor",
          "default": "",
          "type": "string"
        },
        "serial": {
          "title": "Serial",
          "default": "",
          "type": "string"
        },
        "gain1": {

```

(continues on next page)

(continued from previous page)

```

        "title": "Gain1",
        "default": 1,
        "type": "number"
    },
    "gain2": {
        "title": "Gain2",
        "default": 1,
        "type": "number"
    },
    "scaling": {
        "title": "Scaling",
        "default": 1,
        "type": "number"
    },
    "chopper": {
        "title": "Chopper",
        "default": false,
        "type": "boolean"
    },
    "dipole_dist": {
        "title": "Dipole Dist",
        "default": 1,
        "type": "number"
    },
    "sensor_calibration_file": {
        "title": "Sensor Calibration File",
        "default": "",
        "type": "string"
    },
    "instrument_calibration_file": {
        "title": "Instrument Calibration File",
        "default": "",
        "type": "string"
    }
},
"required": [
    "name"
],
"SpectraLevelMetadata": {
    "title": "SpectraLevelMetadata",
    "description": "Metadata for spectra of a windowed decimation level",
    "type": "object",
    "properties": {
        "fs": {
            "title": "Fs",
            "type": "number"
        },
        "n_wins": {
            "title": "N Wins",
            "type": "integer"
        }
    }
},

```

(continues on next page)



(continued from previous page)

```

    "win_size": {
      "title": "Win Size",
      "exclusiveMinimum": 0,
      "type": "integer"
    },
    "olap_size": {
      "title": "Olap Size",
      "exclusiveMinimum": 0,
      "type": "integer"
    },
    "index_offset": {
      "title": "Index Offset",
      "type": "integer"
    },
    "n_freqs": {
      "title": "N Freqs",
      "type": "integer"
    },
    "freqs": {
      "title": "Freqs",
      "type": "array",
      "items": {
        "type": "number"
      }
    }
  },
  "required": [
    "fs",
    "n_wins",
    "win_size",
    "olap_size",
    "index_offset",
    "n_freqs",
    "freqs"
  ],
  "SpectraMetadata": {
    "title": "SpectraMetadata",
    "description": "Metadata for spectra data",
    "type": "object",
    "properties": {
      "file_info": {
        "$ref": "#/definitions/ResisticsFile"
      },
      "fs": {
        "title": "Fs",
        "type": "array",
        "items": {
          "type": "number"
        }
      }
    },
    "chans": {

```

(continues on next page)

(continued from previous page)

```

        "title": "Chans",
        "type": "array",
        "items": {
            "type": "string"
        }
    },
    "n_chans": {
        "title": "N Chans",
        "type": "integer"
    },
    "n_levels": {
        "title": "N Levels",
        "type": "integer"
    },
    "first_time": {
        "title": "First Time",
        "pattern": "%Y-%m-%d %H:%M:%S.%f_o_%q_%v",
        "examples": [
            "2021-01-01 00:00:00.000061_035156_250000_000000"
        ]
    },
    "last_time": {
        "title": "Last Time",
        "pattern": "%Y-%m-%d %H:%M:%S.%f_o_%q_%v",
        "examples": [
            "2021-01-01 00:00:00.000061_035156_250000_000000"
        ]
    },
    "system": {
        "title": "System",
        "default": "",
        "type": "string"
    },
    "serial": {
        "title": "Serial",
        "default": "",
        "type": "string"
    },
    "wgs84_latitude": {
        "title": "Wgs84 Latitude",
        "default": -999.0,
        "type": "number"
    },
    "wgs84_longitude": {
        "title": "Wgs84 Longitude",
        "default": -999.0,
        "type": "number"
    },
    "easting": {
        "title": "Easting",
        "default": -999.0,
        "type": "number"
    }

```

(continues on next page)

(continued from previous page)

```

    },
    "northing": {
      "title": "Northing",
      "default": -999.0,
      "type": "number"
    },
    "elevation": {
      "title": "Elevation",
      "default": -999.0,
      "type": "number"
    },
    "chans_metadata": {
      "title": "Chans Metadata",
      "type": "object",
      "additionalProperties": {
        "$ref": "#/definitions/ChanMetadata"
      }
    },
    "levels_metadata": {
      "title": "Levels Metadata",
      "type": "array",
      "items": {
        "$ref": "#/definitions/SpectraLevelMetadata"
      }
    },
    "ref_time": {
      "title": "Ref Time",
      "pattern": "%Y-%m-%d %H:%M:%S.%f_o_%q_%v",
      "examples": [
        "2021-01-01 00:00:00.000061_035156_250000_000000"
      ]
    },
    "history": {
      "title": "History",
      "default": {
        "records": []
      },
      "allOf": [
        {
          "$ref": "#/definitions/History"
        }
      ]
    },
  },
  "required": [
    "fs",
    "chans",
    "n_levels",
    "first_time",
    "last_time",
    "chans_metadata",
    "levels_metadata",
  ]

```

(continues on next page)

(continued from previous page)

```

        "ref_time"
    ]
}
}
}

```

**field contributors:** `Dict[str, SiteCombinedMetadata | SpectraMetadata]` [Required]

Details about the data contributing to the regression input data

**field history:** `History = History(records=[])`

The processing history

**class** `resistics.regression.RegressionInputData`(*metadata: RegressionInputMetadata, tf: TransferFunction, freqs: List[float], obs: List[Dict[str, ndarray]], preds: List[ndarray]*)

Bases: `ResisticsData`

Class to hold data that will be input into a solver

The purpose of regression input data is to provision for many different solvers and user written solvers.

The regression input data has the following key attributes:

- `freqs`
- `obs`
- `preds`

The `freqs` attribute is a 1-D array of evaluation frequencies.

The `obs` attribute is a dictionary of dictionaries. The parent dictionary has a key of the evaluation frequency index. The secondary dictionary has key of output channel. The values in the secondary dictionary are the observations for that output channel and have 1-D size:

(`n_wins` x `n_cross_chans` x 2).

The factor of 2 is because the real and complex parts of each equation are separated into two equations to allow use of solvers that work exclusively on real data.

The `preds` attribute is a single level dictionary with key of evaluation frequency index and value of the predictors for the evaluation frequency. The predictors have 2-D shape:

(`n_wins` x `n_cross_chans` x 2) x (`n_input_channels` x 2).

The number of windows is multiplied by 2 for the same reason as the observations. The doubling of the input channels is because one is the predictor for the real part of that transfer function component and one is the predictor for the complex part of the transfer function component.

Considering the impedance tensor as an example with:

- output channels `Ex`, `Ey`
- input channels `Hx`, `Hy`
- cross channels `Hx`, `Hy`

The below shows the arrays for the 0 index evaluation frequency:

Observations

- `Ex`: [`w1_crossHx_RE`, `w1_crossHx_IM`, `w1_crossHy_RE`, `w1_crossHy_IM`]

- Ey: [w1\_crossHx\_RE, w1\_crossHx\_IM, w1\_crossHy\_RE, w1\_crossHy\_IM]

Predictors Ex

- w1\_crossHx\_RE: Zxx\_RE Zxx\_IM Zxy\_RE Zxy\_IM
- w1\_crossHx\_IM: Zxx\_RE Zxx\_IM Zxy\_RE Zxy\_IM
- w1\_crossHy\_RE: Zxx\_RE Zxx\_IM Zxy\_RE Zxy\_IM
- w1\_crossHy\_IM: Zxx\_RE Zxx\_IM Zxy\_RE Zxy\_IM

Predictors Ey

- w1\_crossHx\_RE: Zyx\_RE Zyx\_IM Zyy\_RE Zyy\_IM
- w1\_crossHx\_IM: Zyx\_RE Zyx\_IM Zyy\_RE Zyy\_IM
- w1\_crossHy\_RE: Zyx\_RE Zyx\_IM Zyy\_RE Zyy\_IM
- w1\_crossHy\_IM: Zyx\_RE Zyx\_IM Zyy\_RE Zyy\_IM

Note that the predictors are the same regardless of the output channel, only the observations change.

**property n\_freqs:** `int`

Get the number of frequencies

**get\_inputs**(*freq\_idx: int, out\_chan: str*) → `Tuple[ndarray, ndarray]`

Get observations and predictions

#### Parameters

- **freq\_idx** (`int`) – The evaluation frequency index
- **out\_chan** (`str`) – The output channel

#### Returns

Observations and predictions

#### Return type

`Tuple[np.ndarray, np.ndarray]`

**pydantic model** `resistics.regression.RegressionPreparerSpectra`

Bases: `ResisticsProcess`

Prepare regression data directly from spectra data

This can be useful for running a single measurement

```
{
  "title": "RegressionPreparerSpectra",
  "description": "Prepare regression data directly from spectra data\n\nThis can_
↪be useful for running a single measurement",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    }
  }
}
```

**run**(*tf*: *TransferFunction*, *spec\_data*: *SpectraData*) → *RegressionInputData*

Construct the linear equation for solving

**pydantic model** `resisticks.regression.RegressionPreparerGathered`

Bases: *ResisticksProcess*

Regression preparer for gathered data

In nearly all cases, this is the regresson preparer to use. As input, it requires GatheredData.

```
{
  "title": "RegressionPreparerGathered",
  "description": "Regression preparer for gathered data\n\nIn nearly all cases,\n→ this is the regresson preparer to use. As input, it\nrequires GatheredData.",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    }
  }
}
```

**run**(*tf*: *TransferFunction*, *gathered\_data*: *GatheredData*) → *RegressionInputData*

Create the RegressionInputData

#### Parameters

- **tf** (*TransferFunction*) – The transfer function
- **gathered\_data** (*GatheredData*) – The gathered data

#### Returns

Data that can be used as input into a solver

#### Return type

*RegressionInputData*

**pydantic model** `resisticks.regression.Solution`

Bases: *WriteableMetadata*

Class to hold a transfer function solution

## Examples

```
>>> from resisticks.testing import solution_mt
>>> solution = solution_mt()
>>> print(solution.tf.to_string())
| Ex | = | Ex_Hx Ex_Hy | | Hx |
| Ey |   | Ey_Hx Ey_Hy | | Hy |
>>> solution.n_freqs
6
>>> solution.freqs
[100.0, 80.0, 60.0, 40.0, 20.0, 10.0]
>>> solution.periods.tolist()
[0.01, 0.0125, 0.016666666666666666, 0.025, 0.05, 0.1]
```

(continues on next page)

(continued from previous page)

```
>>> solution.components["ExHx"]
Component(real=[1.0, 1.0, 2.0, 2.0, 3.0, 3.0], imag=[5.0, 5.0, 4.0, 4.0, 3.0, 3.0])
>>> solution.components["ExHy"]
Component(real=[1.0, 2.0, 3.0, 4.0, 5.0, 6.0], imag=[-5.0, -4.0, -3.0, -2.0, -1.0, ↵
↵1.0])
```

To get the components as an array, either `get_component` or subscripting be used

```
>>> solution["ExHy"]
array([1.-5.j, 2.-4.j, 3.-3.j, 4.-2.j, 5.-1.j, 6.+1.j])
>>> solution["ab"]
Traceback (most recent call last):
...
ValueError: Component ab not found in ['ExHx', 'ExHy', 'EyHx', 'EyHy']
```

It is also possible to get the tensor values at a particular evaluation frequency

```
>>> solution.get_tensor(2)
array([[ 2.+4.j,  3.-3.j],
       [-3.+3.j, -2.-4.j]])
```

```
{
  "title": "Solution",
  "description": "Class to hold a transfer function solution\n\nExamples\n-----\n
↵>>> from resistics.testing import solution_mt\n>>> solution = solution_mt()\n>>> ↵
↵print(solution.tf.to_string())\n| Ex | = | Ex_Hx Ex_Hy | | Hx | \n| Ey |   | Ey_Hx ↵
↵Ey_Hy | | Hy | \n>>> solution.n_freqs\n6\n>>> solution.freqs\n[100.0, 80.0, 60.0, ↵
↵40.0, 20.0, 10.0]\n>>> solution.periods.tolist()\n[0.01, 0.0125, 0.
↵0.16666666666666666, 0.025, 0.05, 0.1]\n>>> solution.components["ExHx"]\n
↵Component(real=[1.0, 1.0, 2.0, 2.0, 3.0, 3.0], imag=[5.0, 5.0, 4.0, 4.0, 3.0, 3.
↵0.0])\n>>> solution.components["ExHy"]\nComponent(real=[1.0, 2.0, 3.0, 4.0, 5.0, ↵
↵6.0], imag=[-5.0, -4.0, -3.0, -2.0, -1.0, 1.0])\n\nTo get the components as an ↵
↵array, either get_component or subscripting\nbe used\n\n>>> solution["ExHy"]\n
↵array([1.-5.j, 2.-4.j, 3.-3.j, 4.-2.j, 5.-1.j, 6.+1.j])\n>>> solution["ab"]\n
↵Traceback (most recent call last):\n...\nValueError: Component ab not found in [
↵'ExHx', 'ExHy', 'EyHx', 'EyHy']\n\nIt is also possible to get the tensor values. ↵
↵at a particular evaluation\nfrequency\n\n>>> solution.get_tensor(2)\narray([[ 2.
↵+4.j,  3.-3.j],\n          [-3.+3.j, -2.-4.j]])",
  "type": "object",
  "properties": {
    "file_info": {
      "$ref": "#/definitions/ResisticsFile"
    },
    "tf": {
      "$ref": "#/definitions/TransferFunction"
    },
    "freqs": {
      "title": "Freqs",
      "type": "array",
      "items": {
        "type": "number"
      }
    }
  }
}
```

(continues on next page)

(continued from previous page)

```

    },
    "components": {
      "title": "Components",
      "type": "object",
      "additionalProperties": {
        "$ref": "#/definitions/Component"
      }
    },
    "history": {
      "$ref": "#/definitions/History"
    },
    "contributors": {
      "title": "Contributors",
      "type": "object",
      "additionalProperties": {
        "anyOf": [
          {
            "$ref": "#/definitions/SiteCombinedMetadata"
          },
          {
            "$ref": "#/definitions/SpectraMetadata"
          }
        ]
      }
    }
  },
  "required": [
    "tf",
    "freqs",
    "components",
    "history",
    "contributors"
  ],
  "definitions": {
    "ResisticsFile": {
      "title": "ResisticsFile",
      "description": "Required information for writing out a resistics file",
      "type": "object",
      "properties": {
        "created_on_local": {
          "title": "Created On Local",
          "type": "string",
          "format": "date-time"
        },
        "created_on_utc": {
          "title": "Created On Utc",
          "type": "string",
          "format": "date-time"
        },
        "version": {
          "title": "Version",
          "type": "string"
        }
      }
    }
  }
}

```

(continues on next page)



(continued from previous page)

```

    }
  },
  "TransferFunction": {
    "title": "TransferFunction",
    "description": "Define a generic transfer function\n\nThis class is a
→describes generic transfer function, including:\n\n- The output channels for the
→transfer function\n- The input channels for the transfer function\n- The cross
→channels for the transfer function\n\nThe cross channels are the channels that
→will be used to calculate out the\ncross powers for the regression.\n\nThis
→generic parent class has no implemented plotting function. However,\nchild
→classes may have a plotting function as different transfer functions\nmay need
→different types of plots.\n\n.. note::\n\n    Users interested in writing a
→custom transfer function should inherit\n    from this generic Transfer function\
→\n\nSee Also\n-----\nImpandanceTensor : Transfer function for the MT impedance
→tensor\nTipper : Transfer function for the MT tipper\n\nExamples\n-----\nA
→generic example\n\n>>> from resistics.transfunc import TransferFunction\n>>> tf =
→TransferFunction(variation=\"example\", out_chans=[\"bye\", \"see you\", \"ciao\
→\"], in_chans=[\"hello\", \"hi_there\"])\n>>> print(tf.to_string())\n| bye
→| | bye_hello      bye_hi_there      | | hello      |\n| see you | = | see you_
→hello      see you_hi_there | | hi_there |\n| ciao      | | ciao_hello
→ciao_hi_there      |\n\nCombining the impedance tensor and the tipper into one
→TransferFunction\n\n>>> tf = TransferFunction(variation=\"combined\", out_chans=[
→\"Ex\", \"Ey\"], in_chans=[\"Hx\", \"Hy\", \"Hz\"])\n>>> print(tf.to_string())\n|
→Ex |      | Ex_Hx Ex_Hy Ex_Hz | | Hx | \n| Ey | = | Ey_Hx Ey_Hy Ey_Hz | | Hy | \n
→      | Hz |\",
    "type": "object",
    "properties": {
      "name": {
        "title": "Name",
        "type": "string"
      },
      "variation": {
        "title": "Variation",
        "default": "generic",
        "maxLength": 16,
        "type": "string"
      },
      "out_chans": {
        "title": "Out Chans",
        "type": "array",
        "items": {
          "type": "string"
        }
      },
      "in_chans": {
        "title": "In Chans",
        "type": "array",
        "items": {
          "type": "string"
        }
      }
    }
  },

```

(continues on next page)

(continued from previous page)

```

        "cross_chans": {
            "title": "Cross Chans",
            "type": "array",
            "items": {
                "type": "string"
            }
        },
        "n_out": {
            "title": "N Out",
            "type": "integer"
        },
        "n_in": {
            "title": "N In",
            "type": "integer"
        },
        "n_cross": {
            "title": "N Cross",
            "type": "integer"
        }
    },
    "required": [
        "out_chans",
        "in_chans"
    ]
},
"Component": {
    "title": "Component",
    "description": "Data class for a single component in a Transfer function\n\
→nExample\n-----\n>>> from resistics.transfunc import Component\n>>> component = \
→Component(real=[1, 2, 3, 4, 5], imag=[-5, -4, -3, -2, -1])\n>>> component.get_ \
→value(0)\n(1-5j)\n>>> component.to_numpy()\narray([1.-5.j, 2.-4.j, 3.-3.j, 4.-2.j, \
→ 5.-1.j])",
    "type": "object",
    "properties": {
        "real": {
            "title": "Real",
            "type": "array",
            "items": {
                "type": "number"
            }
        },
        "imag": {
            "title": "Imag",
            "type": "array",
            "items": {
                "type": "number"
            }
        }
    },
    "required": [
        "real",
        "imag"
    ]
}

```

(continues on next page)

(continued from previous page)

```

    ]
    },
    "Record": {
        "title": "Record",
        "description": "Class to hold a record\n\nA record holds information about
→a process that was run. It is intended to\ntrack processes applied to data,
→allowing a process history to be saved\nalong with any datasets.\n\nExamples\n----
→----\nA simple example of creating a process record\n\n>>> from resistics.common
→import Record\n\n>>> messages = ["message 1", "message 2"]\n\n>>> record =
→Record(\n...     creator={"name": "example", "parameter1": 15},\n...     \n
→messages=messages,\n...     record_type="example"\n... )\n\n>>> record.summary()\n
→{\n    'time_local': '...',\n    'time_utc': '...',\n    'creator': {'name':
→'example', 'parameter1': 15},\n    'messages': ['message 1', 'message 2'],\n
→'record_type': 'example'\n}",
        "type": "object",
        "properties": {
            "time_local": {
                "title": "Time Local",
                "type": "string",
                "format": "date-time"
            },
            "time_utc": {
                "title": "Time Utc",
                "type": "string",
                "format": "date-time"
            },
            "creator": {
                "title": "Creator",
                "type": "object"
            },
            "messages": {
                "title": "Messages",
                "type": "array",
                "items": {
                    "type": "string"
                }
            },
            "record_type": {
                "title": "Record Type",
                "type": "string"
            }
        },
        "required": [
            "creator",
            "messages",
            "record_type"
        ]
    },
    "History": {
        "title": "History",
        "description": "Class for storing processing history\n\nParameters\n-----
→----\nnrecords : List[Record], optional\n    List of records, by default []\n\n

```

(continues on next page)

(continued from previous page)

```

→nExamples\n-----\n>>> from resistics.testing import record_example1, record_
→example2\n>>> from resistics.common import History\n>>> record1 = record_
→example1()\n>>> record2 = record_example2()\n>>> history =
→History(records=[record1, record2])\n>>> history.summary()\n{\n    'records': [\n
→        {\n
→            'time_local': '...',\n
→            'time_utc': '...',\n
→            'creator': {\n
→                'name': 'example1',\n
→                'a': 5,\n
→                'b': -7.0\n
→            },\n
→            'messages': ['Message 1',
→'Message 2'],\n
→            'record_type': 'process'\n
→        },\n
→        {\n
→            'time_local': '...',\n
→            'time_utc': '...',\n
→            'creator': {\n
→                'name': 'example2',\n
→                'a': 'parzen',\n
→                'b': -21\n
→            },\n
→            'messages': ['Message 5', 'Message
→6'],\n
→            'record_type': 'process'\n
→        }\n
→    ],\n
→    "type": "object",
→    "properties": {\n
→        "records": {\n
→            "title": "Records",
→            "default": [],
→            "type": "array",
→            "items": {\n
→                "$ref": "#/definitions/Record"
→            }\n
→        }\n
→    },\n
→    "SiteCombinedMetadata": {\n
→        "title": "SiteCombinedMetadata",
→        "description": "Metadata for combined data\n\nCombined metadata stores
→metadata for measurements that are combined from\na single site.",
→        "type": "object",
→        "properties": {\n
→            "file_info": {\n
→                "$ref": "#/definitions/ResisticsFile"
→            },\n
→            "site_name": {\n
→                "title": "Site Name",
→                "type": "string"
→            },\n
→            "fs": {\n
→                "title": "Fs",
→                "type": "number"
→            },\n
→            "system": {\n
→                "title": "System",
→                "default": "",
→                "type": "string"
→            },\n
→            "serial": {\n
→                "title": "Serial",
→                "default": "",
→                "type": "string"
→            },\n
→            "wgs84_latitude": {\n

```

(continues on next page)

(continued from previous page)

```

        "title": "Wgs84 Latitude",
        "default": -999.0,
        "type": "number"
    },
    "wgs84_longitude": {
        "title": "Wgs84 Longitude",
        "default": -999.0,
        "type": "number"
    },
    "easting": {
        "title": "Easting",
        "default": -999.0,
        "type": "number"
    },
    "northing": {
        "title": "Northing",
        "default": -999.0,
        "type": "number"
    },
    "elevation": {
        "title": "Elevation",
        "default": -999.0,
        "type": "number"
    },
    "measurements": {
        "title": "Measurements",
        "type": "array",
        "items": {
            "type": "string"
        }
    },
    "chans": {
        "title": "Chans",
        "type": "array",
        "items": {
            "type": "string"
        }
    },
    "n_evals": {
        "title": "N Evals",
        "type": "integer"
    },
    "eval_freqs": {
        "title": "Eval Freqs",
        "type": "array",
        "items": {
            "type": "number"
        }
    },
    "histories": {
        "title": "Histories",
        "type": "object",

```

(continues on next page)

(continued from previous page)

```

        "additionalProperties": {
            "$ref": "#/definitions/History"
        }
    },
    "required": [
        "site_name",
        "fs",
        "chans",
        "n_evals",
        "eval_freqs",
        "histories"
    ],
    "ChanMetadata": {
        "title": "ChanMetadata",
        "description": "Channel metadata",
        "type": "object",
        "properties": {
            "name": {
                "title": "Name",
                "type": "string"
            },
            "data_files": {
                "title": "Data Files",
                "type": "array",
                "items": {
                    "type": "string"
                }
            },
            "chan_type": {
                "title": "Chan Type",
                "type": "string"
            },
            "chan_source": {
                "title": "Chan Source",
                "type": "string"
            },
            "sensor": {
                "title": "Sensor",
                "default": "",
                "type": "string"
            },
            "serial": {
                "title": "Serial",
                "default": "",
                "type": "string"
            },
            "gain1": {
                "title": "Gain1",
                "default": 1,
                "type": "number"
            }
        }
    }
}

```

(continues on next page)

(continued from previous page)

```

    },
    "gain2": {
      "title": "Gain2",
      "default": 1,
      "type": "number"
    },
    "scaling": {
      "title": "Scaling",
      "default": 1,
      "type": "number"
    },
    "chopper": {
      "title": "Chopper",
      "default": false,
      "type": "boolean"
    },
    "dipole_dist": {
      "title": "Dipole Dist",
      "default": 1,
      "type": "number"
    },
    "sensor_calibration_file": {
      "title": "Sensor Calibration File",
      "default": "",
      "type": "string"
    },
    "instrument_calibration_file": {
      "title": "Instrument Calibration File",
      "default": "",
      "type": "string"
    }
  },
  "required": [
    "name"
  ]
},
"SpectraLevelMetadata": {
  "title": "SpectraLevelMetadata",
  "description": "Metadata for spectra of a windowed decimation level",
  "type": "object",
  "properties": {
    "fs": {
      "title": "Fs",
      "type": "number"
    },
    "n_wins": {
      "title": "N Wins",
      "type": "integer"
    },
    "win_size": {
      "title": "Win Size",
      "exclusiveMinimum": 0,

```

(continues on next page)

(continued from previous page)

```

        "type": "integer"
    },
    "olap_size": {
        "title": "Olap Size",
        "exclusiveMinimum": 0,
        "type": "integer"
    },
    "index_offset": {
        "title": "Index Offset",
        "type": "integer"
    },
    "n_freqs": {
        "title": "N Freqs",
        "type": "integer"
    },
    "freqs": {
        "title": "Freqs",
        "type": "array",
        "items": {
            "type": "number"
        }
    }
},
"required": [
    "fs",
    "n_wins",
    "win_size",
    "olap_size",
    "index_offset",
    "n_freqs",
    "freqs"
],
"SpectraMetadata": {
    "title": "SpectraMetadata",
    "description": "Metadata for spectra data",
    "type": "object",
    "properties": {
        "file_info": {
            "$ref": "#/definitions/ResisticsFile"
        },
        "fs": {
            "title": "Fs",
            "type": "array",
            "items": {
                "type": "number"
            }
        },
        "chans": {
            "title": "Chans",
            "type": "array",
            "items": {

```

(continues on next page)



(continued from previous page)

```

        "type": "string"
    },
    "n_chans": {
        "title": "N Chans",
        "type": "integer"
    },
    "n_levels": {
        "title": "N Levels",
        "type": "integer"
    },
    "first_time": {
        "title": "First Time",
        "pattern": "%Y-%m-%d %H:%M:%S.%f_o_%q_%v",
        "examples": [
            "2021-01-01 00:00:00.000061_035156_250000_000000"
        ]
    },
    "last_time": {
        "title": "Last Time",
        "pattern": "%Y-%m-%d %H:%M:%S.%f_o_%q_%v",
        "examples": [
            "2021-01-01 00:00:00.000061_035156_250000_000000"
        ]
    },
    "system": {
        "title": "System",
        "default": "",
        "type": "string"
    },
    "serial": {
        "title": "Serial",
        "default": "",
        "type": "string"
    },
    "wgs84_latitude": {
        "title": "Wgs84 Latitude",
        "default": -999.0,
        "type": "number"
    },
    "wgs84_longitude": {
        "title": "Wgs84 Longitude",
        "default": -999.0,
        "type": "number"
    },
    "easting": {
        "title": "Easting",
        "default": -999.0,
        "type": "number"
    },
    "northing": {
        "title": "Northing",

```

(continues on next page)

(continued from previous page)

```

        "default": -999.0,
        "type": "number"
    },
    "elevation": {
        "title": "Elevation",
        "default": -999.0,
        "type": "number"
    },
    "chans_metadata": {
        "title": "Chans Metadata",
        "type": "object",
        "additionalProperties": {
            "$ref": "#/definitions/ChanMetadata"
        }
    },
    "levels_metadata": {
        "title": "Levels Metadata",
        "type": "array",
        "items": {
            "$ref": "#/definitions/SpectraLevelMetadata"
        }
    },
    "ref_time": {
        "title": "Ref Time",
        "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
        "examples": [
            "2021-01-01 00:00:00.000061_035156_250000_000000"
        ]
    },
    "history": {
        "title": "History",
        "default": {
            "records": []
        },
        "allOf": [
            {
                "$ref": "#/definitions/History"
            }
        ]
    },
    "required": [
        "fs",
        "chans",
        "n_levels",
        "first_time",
        "last_time",
        "chans_metadata",
        "levels_metadata",
        "ref_time"
    ]
}

```

(continues on next page)

(continued from previous page)

```

    }
}

```

**field** `tf`: [TransferFunction](#) [Required]

The transfer function that was solved

**field** `freqs`: [List\[float\]](#) [Required]

The evaluation frequencies

**field** `components`: [Dict\[str, Component\]](#) [Required]

The solution

**field** `history`: [History](#) [Required]

The processing history

**field** `contributors`: [Dict\[str, SiteCombinedMetadata | SpectraMetadata\]](#) [Required]

The contributors to the solution with their respective details

**property** `n_freqs`

Get the number of evaluation frequencies

**property** `periods`: [ndarray](#)

Get the periods

**get\_component**(*key*: [str](#)) → [ndarray](#)

Get the solution for a single component for all the evaluation frequencies

**Parameters**

**key** ([str](#)) – The component key

**Returns**

The component data in an array

**Return type**

[np.ndarray](#)

**Raises**

[ValueError](#) – If the component does not exist in the solution

**get\_tensor**(*eval\_idx*: [int](#)) → [ndarray](#)

Get the tensor at a single evaluation frequency. This has shape:

`n_out_chans x n_in_chans`

**Parameters**

**eval\_idx** ([int](#)) – The index of the evaluation frequency

**Returns**

The tensor as a numpy array

**Return type**

[np.ndarray](#)

**to\_dataframe**() → [DataFrame](#)

Get the solution as a pandas DataFrame

**pydantic model** `resistics.regression.Solver`

Bases: [ResisticsProcess](#)

General resistics solver

```
{
  "title": "Solver",
  "description": "General resistics solver",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    }
  }
}
```

**run**(*regression\_input*: *RegressionInputData*) → *Solution*

Every solver should have a run method

**pydantic model** `resistics.regression.SolverScikit`

Bases: *Solver*

Base class for Scikit learn solvers

```
{
  "title": "SolverScikit",
  "description": "Base class for Scikit learn solvers",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "fit_intercept": {
      "title": "Fit Intercept",
      "default": false,
      "type": "boolean"
    },
    "normalize": {
      "title": "Normalize",
      "default": false,
      "type": "boolean"
    }
  }
}
```

**field** `fit_intercept`: `bool` = `False`

Flag for adding an intercept term

**field** `normalize`: `bool` = `False`

Flag for normalizing, only used if `fit_intercept` is `True`

**pydantic model** `resistics.regression.SolverScikitOLS`

Bases: *SolverScikit*

Ordinary least squares solver

This is simply a wrapper around the scikit learn least squares regression [https://scikit-learn.org/stable/modules/generated/sklearn.linear\\_model.LinearRegression.html](https://scikit-learn.org/stable/modules/generated/sklearn.linear_model.LinearRegression.html)

```
{
  "title": "SolverScikitOLS",
  "description": "Ordinary least squares solver\n\nThis is simply a wrapper around_\n↪the scikit learn least squares regression\nhttps://scikit-learn.org/stable/\n↪modules/generated/sklearn.linear_model.LinearRegression.html",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "fit_intercept": {
      "title": "Fit Intercept",
      "default": false,
      "type": "boolean"
    },
    "normalize": {
      "title": "Normalize",
      "default": false,
      "type": "boolean"
    },
    "n_jobs": {
      "title": "N Jobs",
      "default": -2,
      "type": "integer"
    }
  }
}
```

**field** `n_jobs`: `int` = -2

Number of jobs to run

**run**(*regression\_input*: `RegressionInputData`) → `Solution`

Run ordinary least squares regression on the `RegressionInputData`

**pydantic model** `resistics.regression.SolverScikitHuber`

Bases: `SolverScikit`

Scikit Huber solver

This is simply a wrapper around the scikit learn Huber Regressor. For more information, please see [https://scikit-learn.org/stable/modules/generated/sklearn.linear\\_model.HuberRegressor.html](https://scikit-learn.org/stable/modules/generated/sklearn.linear_model.HuberRegressor.html)

```
{
  "title": "SolverScikitHuber",
  "description": "Scikit Huber solver\n\nThis is simply a wrapper around the_\n↪scikit learn Huber Regressor. For\nmore information, please see\nhttps://scikit-\n↪learn.org/stable/modules/generated/sklearn.linear_model.HuberRegressor.html",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    }
  },
}
```

(continues on next page)

(continued from previous page)

```

    "fit_intercept": {
        "title": "Fit Intercept",
        "default": false,
        "type": "boolean"
    },
    "normalize": {
        "title": "Normalize",
        "default": false,
        "type": "boolean"
    },
    "epsilon": {
        "title": "Epsilon",
        "default": 1,
        "type": "number"
    }
}

```

**field epsilon:** float = 1

The smaller the epsilon, the more robust it is to outliers.

**run**(*regression\_input*: RegressionInputData) → Solution

Run Huber Regressor regression on the RegressionInputData

**pydantic model** resistics.regression.SolverScikitTheilSen

Bases: SolverScikit

Scikit Theil Sen solver

This is simply a wrapper around the scikit learn Theil Sen Regressor. For more information, please see [https://scikit-learn.org/stable/modules/generated/sklearn.linear\\_model.TheilSenRegressor.html](https://scikit-learn.org/stable/modules/generated/sklearn.linear_model.TheilSenRegressor.html)

```

{
    "title": "SolverScikitTheilSen",
    "description": "Scikit Theil Sen solver\n\nThis is simply a wrapper around the_\n↪scikit learn Theil Sen Regressor. For\nmore information, please see\nhttps://\n↪scikit-learn.org/stable/modules/generated/sklearn.linear_model.TheilSenRegressor.\n↪html",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        },
        "fit_intercept": {
            "title": "Fit Intercept",
            "default": false,
            "type": "boolean"
        },
        "normalize": {
            "title": "Normalize",
            "default": false,
            "type": "boolean"
        }
    }
}

```

(continues on next page)

(continued from previous page)

```

    },
    "n_jobs": {
        "title": "N Jobs",
        "default": -2,
        "type": "integer"
    },
    "max_subpopulation": {
        "title": "Max Subpopulation",
        "default": 2000,
        "type": "integer"
    },
    "n_subsamples": {
        "title": "N Subsamples",
        "type": "number"
    }
}

```

**field n\_jobs:** `int` = -2

Number of jobs to run

**field max\_subpopulation:** `int` = 2000

Maximum population. Reduce this if the process is taking a long time

**field n\_subsamples:** `float` | `None` = None

Number of rows to use for each solution

**run**(*regression\_input*: `RegressionInputData`) → *Solution*

Run TheilSen regression on the RegressionInputData

**pydantic model** `resistics.regression.SolverScikitRANSAC`

Bases: `SolverScikit`

Run a RANSAC solver with LinearRegression as Base Estimator

This is a wrapper around the scikit learn RANSAC regressor. More information can be found here [https://scikit-learn.org/stable/modules/generated/sklearn.linear\\_model.RANSACRegressor.html](https://scikit-learn.org/stable/modules/generated/sklearn.linear_model.RANSACRegressor.html)

```

{
    "title": "SolverScikitRANSAC",
    "description": "Run a RANSAC solver with LinearRegression as Base Estimator\n\
    ↪ This is a wrapper around the scikit learn RANSAC regressor. More information\n\
    ↪ can be found here\nhttps://scikit-learn.org/stable/modules/generated/sklearn.\
    ↪ linear_model.RANSACRegressor.html",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        },
        "fit_intercept": {
            "title": "Fit Intercept",
            "default": false,
            "type": "boolean"
        }
    }
}

```

(continues on next page)

(continued from previous page)

```

    },
    "normalize": {
        "title": "Normalize",
        "default": false,
        "type": "boolean"
    },
    "min_samples": {
        "title": "Min Samples",
        "default": 0.8,
        "type": "number"
    },
    "max_trials": {
        "title": "Max Trials",
        "default": 20,
        "type": "integer"
    }
}

```

**field min\_samples:** float = 0.8

Minimum number of samples in each solution as a proportion of total

**field max\_trials:** int = 20

The maximum number of trials to run

**run**(regression\_input: RegressionInputData) → Solution

Run RANSAC regression on the RegressionInputData

**pydantic model** resistics.regression.SolverScikitWLS

Bases: SolverScikitOLS

Weighted least squares solver

**Warning:** This is homespun and is currently only experimental

This is simply a wrapper around the scikit learn least squares regression using the sample\_weight option [https://scikit-learn.org/stable/modules/generated/sklearn.linear\\_model.LinearRegression.html](https://scikit-learn.org/stable/modules/generated/sklearn.linear_model.LinearRegression.html)

```

{
    "title": "SolverScikitWLS",
    "description": "Weighted least squares solver\n\n.. warning::\n\n    This is_\n↪homespun and is currently only experimental\n\nThis is simply a wrapper around_\n↪the scikit learn least squares regression\nusing the sample_weight option\nhttps://\n↪scikit-learn.org/stable/modules/generated/sklearn.linear_model.LinearRegression.\n↪html",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        },
        "fit_intercept": {

```

(continues on next page)



(continued from previous page)

```

        "title": "Fit Intercept",
        "default": false,
        "type": "boolean"
    },
    "normalize": {
        "title": "Normalize",
        "default": false,
        "type": "boolean"
    },
    "n_jobs": {
        "title": "N Jobs",
        "default": -2,
        "type": "integer"
    },
    "n_iter": {
        "title": "N Iter",
        "default": 50,
        "type": "integer"
    }
}

```

**field n\_jobs:** `int = -2`

Number of jobs to run

**field n\_iter:** `int = 50`

Number of iterations before quitting if residual is not low enough

**bisquare**(*r*: `ndarray`, *k*: `float = 4.685`) → `ndarray`

Bisquare location weights

#### Parameters

- *r* (`np.ndarray`) – Residuals
- *k* (`float`, `None`) – Tuning parameter. If `None`, a standard value will be used.

#### Returns

**weights** – The robust weights

#### Return type

`np.ndarray`

**huber**(*r*: `ndarray`, *k*: `float = 1.345`) → `ndarray`

Huber location weights

#### Parameters

- *r* (`np.ndarray`) – Residuals
- *k* (`float`) – Tuning parameter. If `None`, a standard value will be used.

#### Returns

**weights** – The robust weights

#### Return type

`np.ndarray`

**trimmed\_mean**(*r*: *ndarray*, *k*: *float* = 2) → *ndarray*

Trimmed mean location weights

**Parameters**

- **r** (*np.ndarray*) – Residuals
- **k** (*float*) – Tuning parameter. If None, a standard value will be used.

**Returns**

**weights** – The robust weights

**Return type**

*np.ndarray*

## resistics.sampling module

Module for dealing with sampling and dates including:

- Converting from samples to datetimes
- Converting from datetimes to samples
- All datetime, timedelta types are aliased as *RSDatetime* and *RSTimeDelta*
- This is to ease type hinting if the base datetime and timedelta classes change
- Currently, resistics uses *attodatetime* and *attotimedelta* from *attotime*
- *attotime* is a high precision datetime library

**class** *resistics.sampling.HighResDateTime*(*year*, *month*, *day*, *hour*=0, *minute*=0, *second*=0, *microsecond*=0, *nanosecond*=0, *tzinfo*=None)

Bases: *attodatetime*

Wrapper around *RSDatetime* to use for pydantic

**classmethod** **validate**(*val*: *attodatetime* | *str* | *Timestamp* | *datetime*)

Validator to be used by pydantic

*resistics.sampling.datetime\_to\_string*(*time*: *attodatetime*) → *str*

Convert a datetime to a string.

**Parameters**

**time** (*RSDatetime*) – Resistics datetime

**Returns**

String representation

**Return type**

*str*

## Examples

```
>>> from resisticks.sampling import to_datetime, to_timedelta, datetime_to_string
>>> time = to_datetime("2021-01-01") + to_timedelta(1/16384)
>>> datetime_to_string(time)
'2021-01-01 00:00:00.000061_035156_250000_000000'
```

`resisticks.sampling.datetime_from_string(time: str)` → `attodatetime`

Convert a string back to a datetime.

Only a fixed format is allowed `%Y-%m-%d %H:%M:%S.%f_%o_%q_%v`

### Parameters

**time** (*str*) – time as a string

### Returns

The resisticks datetime

### Return type

`RSDatetime`

## Examples

```
>>> from resisticks.sampling import to_datetime, to_timedelta
>>> from resisticks.sampling import datetime_to_string, datetime_from_string
>>> time = to_datetime("2021-01-01") + to_timedelta(1/16384)
>>> time_str = datetime_to_string(time)
>>> time_str
'2021-01-01 00:00:00.000061_035156_250000_000000'
>>> datetime_from_string(time_str)
attotime.objects.attodatetime(2021, 1, 1, 0, 0, 0, 61, 35.15625)
```

`resisticks.sampling.to_datetime(time: str | Timestamp | datetime)` → `attodatetime`

Convert a string, `pd.Timestamp` or `datetime` object to a `RSDatetime`.

`RSDatetime` uses `attodatetime` which is a high precision datetime format helpful for high sampling frequencies.

### Parameters

**time** (*DateTimeLike*) – Input time as either a string, `pd.Timestamp` or native python `datetime`

### Returns

High precision datetime object

### Return type

`RSDatetime`

## Examples

```
>>> import pandas as pd
>>> from resistics.sampling import to_datetime
>>> a = "2021-01-01 00:00:00"
>>> to_datetime(a)
attotime.objects.attodatetime(2021, 1, 1, 0, 0, 0, 0, 0)
>>> str(to_datetime(a))
'2021-01-01 00:00:00'
>>> b = pd.Timestamp(a)
>>> str(to_datetime(b))
'2021-01-01 00:00:00'
>>> c = pd.Timestamp(a).to_pydatetime()
>>> str(to_datetime(c))
'2021-01-01 00:00:00'
```

`resistics.sampling.to_timestamp(time: attodatetime) → Timestamp`

Convert a RSDateTime to a pandas Timestamp

### Parameters

**time** (*RSDateTime*) – An RSDateTime instance

### Returns

RSDateTime converted to Timestamp

### Return type

pd.Timestamp

## Examples

```
>>> from resistics.sampling import to_datetime, to_timestamp
>>> time = to_datetime("2021-01-01 00:30:00.345")
>>> print(time)
2021-01-01 00:30:00.345
>>> to_timestamp(time)
Timestamp('2021-01-01 00:30:00.345000')
```

`resistics.sampling.to_timedelta(delta: float | timedelta | Timedelta) → attotimedelta`

Get a RSTimeDelta object by providing seconds as a float or a pd.Timedelta.

RSTimeDelta uses attotimedelta, a high precision timedelta object. This can be useful for high sampling frequencies.

**Warning:** At high time resolutions, there are machine precision errors that come into play. Therefore, if nanoseconds < 0.0001, it will be zeroed out

### Parameters

**delta** (*TimeDeltaLike*) – Timedelta as a float (assumed to be seconds), timedelta or pd.Timedelta

### Returns

High precision timedelta

**Return type**

RSTimeDelta

**Examples**

```
>>> import pandas as pd
>>> from resistics.sampling import to_timedelta
```

Low frequency sampling

```
>>> fs = 0.0000125
>>> to_timedelta(1/fs)
attotime.objects.attotimedelta(0, 80000)
>>> str(to_timedelta(1/fs))
'22:13:20'
>>> fs = 0.004
>>> to_timedelta(1/fs)
attotime.objects.attotimedelta(0, 250)
>>> str(to_timedelta(1/fs))
'0:04:10'
>>> fs = 0.3125
>>> str(to_timedelta(1/fs))
'0:00:03.2'
```

Higher frequency sampling

```
>>> fs = 4096
>>> to_timedelta(1/fs)
attotime.objects.attotimedelta(0, 0, 244, 140.625)
>>> str(to_timedelta(1/fs))
'0:00:00.000244140625'
>>> fs = 65_536
>>> str(to_timedelta(1/fs))
'0:00:00.0000152587890625'
>>> fs = 524_288
>>> str(to_timedelta(1/fs))
'0:00:00.0000019073486328125'
```

to\_timedelta can also accept pandas Timedelta objects

```
>>> str(to_timedelta(pd.Timedelta(1, "s")))
'0:00:01'
```

**resistics.sampling.to\_seconds(delta: attotimedelta) → Tuple[float, float]**

Convert a timedelta to seconds as a float.

Returns a Tuple, the first value being the days in the delta converted to seconds, the second entry in the Tuple is the remaining amount of time converted to seconds.

**Parameters**

**delta** (*RSTimeDelta*) – timedelta

**Returns**

- *days\_in\_seconds* – The days in the delta converted to seconds

- *remaining\_in\_seconds* – The remaining amount of time in the delta converted to seconds

## Examples

Example with a small timedelta

```
>>> from resistics.sampling import to_datetime, to_timedelta, to_seconds
>>> a = to_timedelta(1/4_096)
>>> str(a)
'0:00:00.000244140625'
>>> days_in_seconds, remaining_in_seconds = to_seconds(a)
>>> days_in_seconds
0
>>> remaining_in_seconds
0.000244140625
```

Example with a larger timedelta

```
>>> a = to_datetime("2021-01-01 00:00:00")
>>> b = to_datetime("2021-02-01 08:24:30")
>>> days_in_seconds, remaining_in_seconds = to_seconds(b-a)
>>> days_in_seconds
2678400
>>> remaining_in_seconds
30270.0
```

`resistics.sampling.to_n_samples(delta: attotimedelta, fs: float, method: str = 'round') → int`

Convert a timedelta to number of samples

This method is inclusive of start and end sample.

### Parameters

- **delta** (*RSTimeDelta*) – The timedelta
- **fs** (*float*) – The sampling frequency
- **method** (*str*) – Method to deal with floats, default is 'round'. Other options include 'ceil' and 'floor'

### Returns

The number of samples in the timedelta

### Return type

*int*

## Examples

With sampling frequency of 4096 Hz

```
>>> from resistics.sampling import to_timedelta, to_n_samples
>>> fs = 4096
>>> delta = to_timedelta(8*3600 + (21/fs))
>>> str(delta)
'8:00:00.005126953125'
```

(continues on next page)

(continued from previous page)

```
>>> to_n_samples(delta, fs=fs)
117964822
>>> check = (8*3600)*fs + 21
>>> check
117964821
>>> check_inclusive = check + 1
>>> check_inclusive
117964822
```

With a sampling frequency of 65536 Hz

```
>>> fs = 65_536
>>> delta = to_timedelta(2*3600 + (40_954/fs))
>>> str(delta)
'2:00:00.624908447265625'
>>> to_n_samples(delta, fs=fs)
471900155
>>> check = 2*3600*fs + 40_954
>>> check
471900154
>>> check_inclusive = check + 1
>>> check_inclusive
471900155
```

`resistics.sampling.check_sample(n_samples: int, sample: int) → bool`

Check sample is between  $0 \leq \text{from\_sample} < n\_samples$

#### Parameters

- **n\_samples** (*int*) – Number of samples
- **sample** (*int*) – Sample to check

#### Returns

Return True if no errors

#### Return type

`bool`

#### Raises

- **ValueError** – If sample < 0
- **ValueError** – If sample > n\_samples

### Examples

```
>>> from resistics.sampling import check_sample
>>> check_sample(100, 45)
True
>>> check_sample(100, 100)
Traceback (most recent call last):
...
ValueError: Sample 100 must be < 100
>>> check_sample(100, -1)
```

(continues on next page)

(continued from previous page)

Traceback (most recent call last):

...

ValueError: Sample -1 must be &gt;= 0

`resistics.sampling.sample_to_datetime(fs: float, first_time: attodatetime, sample: int, n_samples: int | None = None) → attodatetime`

Convert a sample to a pandas Timestamp.

**Parameters**

- **fs** (*float*) – The sampling frequency
- **first\_time** (*RSDatetime*) – The first time
- **sample** (*int*) – The sample
- **n\_samples** (*Optional[int]*, *optional*) – The number of samples, used for checking, by default None. If provided, the sample is checked to make sure it's not out of bounds.

**Returns**

The timestamp of the sample

**Return type**

*RSDatetime*

**Raises**

**ValueError** – If `n_samples` is provided and `sample` is `< 0` or `>= n_samples`

**Examples**

```
>>> import pandas as pd
>>> from resistics.sampling import to_datetime, sample_to_datetime
>>> fs = 512
>>> first_time = to_datetime("2021-01-02 00:00:00")
>>> sample = 512
>>> sample_datetime = sample_to_datetime(fs, first_time, sample)
>>> str(sample_datetime)
'2021-01-02 00:00:01'
```

`resistics.sampling.samples_to_datetimes(fs: float, first_time: attodatetime, from_sample: int, to_sample: int) → Tuple[attodatetime, attodatetime]`

Convert from and to samples to datetimes.

The first sample is assumed to be 0.

**Parameters**

- **fs** (*float*) – The sampling frequency in seconds
- **first\_time** (*RSDatetime*) – The time of the first sample
- **from\_sample** (*int*) – The sample to read data from
- **to\_sample** (*int*) – The sample to read data to

**Returns**

- **from\_time** (*RSDatetime*) – The timestamp to read data from



- **to\_time** (*RSDatetime*) – The timestamp to read data to

**Raises**

**ValueError** – If from sample is greater than or equal to to sample

**Examples**

```
>>> import pandas as pd
>>> from resistics.sampling import to_datetime, samples_to_datetimes
>>> fs = 512
>>> first_time = to_datetime("2021-01-02 00:00:00")
>>> from_sample = 512
>>> to_sample = 1024
>>> from_time, to_time = samples_to_datetimes(fs, first_time, from_sample, to_
↳sample)
>>> str(from_time)
'2021-01-02 00:00:01'
>>> str(to_time)
'2021-01-02 00:00:02'
```

`resistics.sampling.check_from_time`(*first\_time: attodatetime, last\_time: attodatetime, from\_time: attodatetime*) → *attodatetime*

Check a from time.

- If first time ≤ from\_time ≤ last\_time, it will be returned unchanged.
- If from\_time < first time, then first time will be returned.
- If from\_time > last time, it will raise a ValueError.

**Parameters**

- **first\_time** (*RSDatetime*) – The time of the first sample
- **last\_time** (*RSDatetime*) – The time of the last sample
- **from\_time** (*RSDatetime*) – Time to get the data from

**Returns**

A from time adjusted as needed given the first and last sample time

**Return type**

*RSDatetime*

**Raises**

**ValueError** – If the from time is after the time of the last sample

**Examples**

With a from time between first and last time. This should be the normal use case.

```
>>> from resistics.sampling import to_datetime, check_from_time
>>> first_time = to_datetime("2021-01-02 00:00:00")
>>> last_time = to_datetime("2021-01-02 23:00:00")
>>> from_time = to_datetime("2021-01-02 03:00:00")
>>> from_time = check_from_time(first_time, last_time, from_time)
```

(continues on next page)

(continued from previous page)

```
>>> str(from_time)
'2021-01-02 03:00:00'
```

An alternative scenario when from time is before the time of the first sample

```
>>> from_time = to_datetime("2021-01-01 23:00:00")
>>> from_time = check_from_time(first_time, last_time, from_time)
>>> str(from_time)
'2021-01-02 00:00:00'
```

An error will be raised when from time is after the time of the last sample

```
>>> from_time = to_datetime("2021-01-02 23:30:00")
>>> from_time = check_from_time(first_time, last_time, from_time)
Traceback (most recent call last):
...
ValueError: From time 2021-01-02 23:30:00 greater than time of last sample 2021-01-
↪ 02 23:00:00
```

`resistics.sampling.check_to_time`(*first\_time: attodatetime, last\_time: attodatetime, to\_time: attodatetime*)  
→ attodatetime

Check a to time.

- If first time ≤ to time ≤ last time, it will be returned unchanged.
- If to time > last time, then last time will be returned.
- If to time < first time, it will raise a ValueError.

#### Parameters

- **first\_time** (*RSDatetime*) – The time of the first sample
- **last\_time** (*RSDatetime*) – The time of the last sample
- **to\_time** (*RSDatetime*) – Time to get the data to

#### Returns

A to time adjusted as needed

#### Return type

*RSDatetime*

#### Raises

**ValueError** – If the to time is before the time of the first sample

### Examples

With a to time between first and last time. This should be the normal use case.

```
>>> from resistics.sampling import to_datetime, check_to_time
>>> first_time = to_datetime("2021-01-02 00:00:00")
>>> last_time = to_datetime("2021-01-02 23:00:00")
>>> to_time = to_datetime("2021-01-02 20:00:00")
>>> to_time = check_to_time(to_time, last_time, to_time)
```

(continues on next page)

(continued from previous page)

```
>>> str(to_time)
'2021-01-02 20:00:00'
```

An alternative scenario when to time is after the time of the last sample

```
>>> to_time = to_datetime("2021-01-02 23:30:00")
>>> to_time = check_to_time(first_time, last_time, to_time)
>>> str(to_time)
'2021-01-02 23:00:00'
```

An error will be raised when to time is before the time of the first sample

```
>>> to_time = to_datetime("2021-01-01 23:30:00")
>>> to_time = check_to_time(first_time, last_time, to_time)
Traceback (most recent call last):
...
ValueError: To time 2021-01-01 23:30:00 less than time of first sample 2021-01-02_
↪ 00:00:00
```

`resistics.sampling.from_time_to_sample(fs: float, first_time: attodatetime, last_time: attodatetime, from_time: attodatetime) → int`

Get the sample for the from time.

#### Parameters

- **fs** (*float*) – Sampling frequency Hz
- **first\_time** (*RSDatetime*) – Time of first sample
- **last\_time** (*RSDatetime*) – Time of last sample
- **from\_time** (*RSDatetime*) – From time

#### Returns

The sample coincident with or after the from time

#### Return type

*int*

### Examples

```
>>> from resistics.sampling import to_datetime, from_time_to_sample
>>> first_time = to_datetime("2021-01-01 00:00:00")
>>> last_time = to_datetime("2021-01-02 00:00:00")
>>> fs = 128
>>> fs * 60 * 60
460800
>>> from_time = to_datetime("2021-01-01 01:00:00")
>>> from_time_to_sample(fs, first_time, last_time, from_time)
460800
>>> from_time = to_datetime("2021-01-01 01:00:00.0078125")
>>> from_time_to_sample(fs, first_time, last_time, from_time)
460801
```

`resistics.sampling.to_time_to_sample(fs: float, first_time: attodatetime, last_time: attodatetime, to_time: attodatetime) → int`

Get the to time sample.

**Warning:** This will return the sample of the to time. In cases where this will be used for a range, 1 should be added to it to ensure it is included.

#### Parameters

- **fs** (*float*) – Sampling frequency Hz
- **first\_time** (*RSDatetime*) – Time of first sample
- **last\_time** (*RSDatetime*) – Time of last sample
- **to\_time** (*RSDatetime*) – The to time

#### Returns

The sample coincident with or immediately before the to time

#### Return type

`int`

#### Examples

```
>>> from resistics.sampling import to_time_to_sample
>>> first_time = to_datetime("2021-01-01 04:00:00")
>>> last_time = to_datetime("2021-01-01 13:00:00")
>>> fs = 4096
>>> fs * 60 * 60
14745600
>>> to_time = to_datetime("2021-01-01 05:00:00")
>>> to_time_to_sample(fs, first_time, last_time, to_time)
14745600
>>> fs * 70 * 60
17203200
>>> to_time = to_datetime("2021-01-01 05:10:00")
>>> to_time_to_sample(fs, first_time, last_time, to_time)
17203200
```

`resistics.sampling.datetimes_to_samples(fs: float, first_time: attodatetime, last_time: attodatetime, from_time: attodatetime, to_time: attodatetime) → Tuple[int, int]`

Convert from and to time to samples.

**Warning:** If using these samples in ranging, the from sample can be left unchanged but one should be added to the to sample to ensure it is included.

---

**Note:** If from\_time is not a sample timestamp, the next sample is taken If to\_time is not a sample timestamp, the previous sample is taken

---

**Parameters**

- **fs** (*float*) – The sampling frequency in Hz
- **first\_time** (*RSDatetime*) – The time of the first sample
- **last\_time** (*RSDatetime*) – The time of the last sample
- **from\_time** (*RSDatetime*) – A from time
- **to\_time** (*RSDatetime*) – A to time

**Returns**

- **from\_sample** (*int*) – Sample to read data from
- **to\_sample** (*int*) – Sample to read data to

**Examples**

```
>>> from resistics.sampling import to_datetime, datetimes_to_samples
>>> first_time = to_datetime("2021-01-01 04:00:00")
>>> last_time = to_datetime("2021-01-01 05:30:00")
>>> from_time = to_datetime("2021-01-01 05:00:00")
>>> to_time = to_datetime("2021-01-01 05:10:00")
>>> fs = 16_384
>>> fs * 60 * 60
58982400
>>> fs * 70 * 60
68812800
>>> from_sample, to_sample = datetimes_to_samples(fs, first_time, last_time, from_
↳ time, to_time)
>>> from_sample
58982400
>>> to_sample
68812800
```

`resistics.sampling.datetime_array`(*first\_time: attodatetime*, *fs: float*, *n\_samples: int | None = None*, *samples: ndarray | None = None*) → *ndarray*

Get a datetime array in high resolution.

This will return a high resolution datetime array. This method is more computationally demanding than a pandas `date_range`. As a result, in cases where exact datetimes are not required, it is suggested to use `datetime_array_estimate` instead.

**Parameters**

- **first\_time** (*RSDatetime*) – The first time
- **fs** (*float*) – The sampling frequency
- **n\_samples** (*Optional[int]*, *optional*) – The number of samples, by default `None`
- **samples** (*Optional[np.ndarray]*, *optional*) – The samples for which to return a date-time, by default `None`

**Returns**

Numpy array of *RSDatetime*s

**Return type**

`np.ndarray`

**Raises**

**ValueError** – If both `n_samples` and `samples` is None

**Examples**

This examples shows the value of using higher resolution datetimes, however this is computationally more expensive.

```
>>> import pandas as pd
>>> from resistics.sampling import to_datetime, datetime_array
>>> first_time = to_datetime("2021-01-01 00:00:00")
>>> fs = 4096
>>> n_samples = 100
>>> arr = datetime_array(first_time, fs, n_samples=n_samples)
>>> str(arr[-1])
'2021-01-01 00:00:00.024169921875'
>>> pdarr = pd.date_range(start="2021-01-01 00:00:00", freq=pd.Timedelta(1/4096, "s",
→), periods=n_samples)
>>> pdarr[-1]
Timestamp('2021-01-01 00:00:00.024169959')
```

`resistics.sampling.datetime_array_estimate`(*first\_time: attodatetime | str | Timestamp | datetime*, *fs: float*, *n\_samples: int | None = None*, *samples: ndarray | None = None*) → `DatetimeIndex`

Estimate datetime array with lower precision but much faster performance.

**Parameters**

- **first\_time** (`Union[RSDateTime, datetime, str, pd.Timestamp]`) – The first time
- **fs** (`float`) – The sampling frequency
- **n\_samples** (`Optional[int]`, *optional*) – The number of samples, by default None
- **samples** (`Optional[np.ndarray]`, *optional*) – An array of samples to return datetimes for, by default None

**Returns**

A pandas `DatetimeIndex`

**Return type**

`pd.DatetimeIndex`

**Raises**

**ValueError** – If both `n_samples` and `samples` are None

**Examples**

```
>>> import pandas as pd
>>> from resistics.sampling import to_datetime, datetime_array_estimate
>>> first_time = to_datetime("2021-01-01 00:00:00")
>>> fs = 128
>>> n_samples = 1_000
>>> arr = datetime_array_estimate(first_time, fs, n_samples=n_samples)
>>> print(f"{arr[0]} - {arr[-1]}")
2021-01-01 00:00:00 - 2021-01-01 00:00:07.804687500
```

## resistics.spectra module

Module containing functions and classes related to Spectra calculation and manipulation

Spectra are calculated from the windowed, decimated time data. The inbuilt Fourier transform implementation is inspired by the implementation of the `scipy stft` function.

### pydantic model `resistics.spectra.SpectraLevelMetadata`

Bases: `Metadata`

Metadata for spectra of a windowed decimation level

```
{
  "title": "SpectraLevelMetadata",
  "description": "Metadata for spectra of a windowed decimation level",
  "type": "object",
  "properties": {
    "fs": {
      "title": "Fs",
      "type": "number"
    },
    "n_wins": {
      "title": "N Wins",
      "type": "integer"
    },
    "win_size": {
      "title": "Win Size",
      "exclusiveMinimum": 0,
      "type": "integer"
    },
    "olap_size": {
      "title": "Olap Size",
      "exclusiveMinimum": 0,
      "type": "integer"
    },
    "index_offset": {
      "title": "Index Offset",
      "type": "integer"
    },
    "n_freqs": {
      "title": "N Freqs",
      "type": "integer"
    },
    "freqs": {
      "title": "Freqs",
      "type": "array",
      "items": {
        "type": "number"
      }
    }
  },
  "required": [
    "fs",
    "n_wins",
    "win_size",

```

(continues on next page)

(continued from previous page)

```

        "olap_size",
        "index_offset",
        "n_freqs",
        "freqs"
    ]
}

```

**field fs:** `float` [Required]

The sampling frequency of the decimation level

**field n\_wins:** `int` [Required]

The number of windows

**field win\_size:** `PositiveInt` [Required]

The window size in samples

#### Constraints

- `exclusiveMinimum` = 0

**field olap\_size:** `PositiveInt` [Required]

The overlap size in samples

#### Constraints

- `exclusiveMinimum` = 0

**field index\_offset:** `int` [Required]

The global window offset for local window 0

**field n\_freqs:** `int` [Required]

The number of frequencies in the frequency data

**field freqs:** `List[float]` [Required]

List of frequencies

**property nyquist:** `float`

Get the nyquist frequency

**pydantic model** `resistics.spectra.SpectraMetadata`

Bases: `WriteableMetadata`

Metadata for spectra data

```

{
  "title": "SpectraMetadata",
  "description": "Metadata for spectra data",
  "type": "object",
  "properties": {
    "file_info": {
      "$ref": "#/definitions/ResisticsFile"
    },
    "fs": {
      "title": "Fs",
      "type": "array",
      "items": {

```

(continues on next page)



(continued from previous page)

```

        "type": "number"
    },
    "chans": {
        "title": "Chans",
        "type": "array",
        "items": {
            "type": "string"
        }
    },
    "n_chans": {
        "title": "N Chans",
        "type": "integer"
    },
    "n_levels": {
        "title": "N Levels",
        "type": "integer"
    },
    "first_time": {
        "title": "First Time",
        "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
        "examples": [
            "2021-01-01 00:00:00.000061_035156_250000_000000"
        ]
    },
    "last_time": {
        "title": "Last Time",
        "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
        "examples": [
            "2021-01-01 00:00:00.000061_035156_250000_000000"
        ]
    },
    "system": {
        "title": "System",
        "default": "",
        "type": "string"
    },
    "serial": {
        "title": "Serial",
        "default": "",
        "type": "string"
    },
    "wgs84_latitude": {
        "title": "Wgs84 Latitude",
        "default": -999.0,
        "type": "number"
    },
    "wgs84_longitude": {
        "title": "Wgs84 Longitude",
        "default": -999.0,
        "type": "number"
    },
    },

```

(continues on next page)

(continued from previous page)

```

    "easting": {
      "title": "Easting",
      "default": -999.0,
      "type": "number"
    },
    "northing": {
      "title": "Northing",
      "default": -999.0,
      "type": "number"
    },
    "elevation": {
      "title": "Elevation",
      "default": -999.0,
      "type": "number"
    },
    "chans_metadata": {
      "title": "Chans Metadata",
      "type": "object",
      "additionalProperties": {
        "$ref": "#/definitions/ChanMetadata"
      }
    },
    "levels_metadata": {
      "title": "Levels Metadata",
      "type": "array",
      "items": {
        "$ref": "#/definitions/SpectralLevelMetadata"
      }
    },
    "ref_time": {
      "title": "Ref Time",
      "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
      "examples": [
        "2021-01-01 00:00:00.000061_035156_250000_000000"
      ]
    },
    "history": {
      "title": "History",
      "default": {
        "records": []
      },
      "allOf": [
        {
          "$ref": "#/definitions/History"
        }
      ]
    },
  },
  "required": [
    "fs",
    "chans",
    "n_levels",

```

(continues on next page)

(continued from previous page)

```

    "first_time",
    "last_time",
    "chans_metadata",
    "levels_metadata",
    "ref_time"
  ],
  "definitions": {
    "ResisticsFile": {
      "title": "ResisticsFile",
      "description": "Required information for writing out a resistics file",
      "type": "object",
      "properties": {
        "created_on_local": {
          "title": "Created On Local",
          "type": "string",
          "format": "date-time"
        },
        "created_on_utc": {
          "title": "Created On Utc",
          "type": "string",
          "format": "date-time"
        },
        "version": {
          "title": "Version",
          "type": "string"
        }
      }
    },
    "ChanMetadata": {
      "title": "ChanMetadata",
      "description": "Channel metadata",
      "type": "object",
      "properties": {
        "name": {
          "title": "Name",
          "type": "string"
        },
        "data_files": {
          "title": "Data Files",
          "type": "array",
          "items": {
            "type": "string"
          }
        },
        "chan_type": {
          "title": "Chan Type",
          "type": "string"
        },
        "chan_source": {
          "title": "Chan Source",
          "type": "string"
        }
      }
    }
  }
}

```

(continues on next page)

(continued from previous page)

```

    "sensor": {
      "title": "Sensor",
      "default": "",
      "type": "string"
    },
    "serial": {
      "title": "Serial",
      "default": "",
      "type": "string"
    },
    "gain1": {
      "title": "Gain1",
      "default": 1,
      "type": "number"
    },
    "gain2": {
      "title": "Gain2",
      "default": 1,
      "type": "number"
    },
    "scaling": {
      "title": "Scaling",
      "default": 1,
      "type": "number"
    },
    "chopper": {
      "title": "Chopper",
      "default": false,
      "type": "boolean"
    },
    "dipole_dist": {
      "title": "Dipole Dist",
      "default": 1,
      "type": "number"
    },
    "sensor_calibration_file": {
      "title": "Sensor Calibration File",
      "default": "",
      "type": "string"
    },
    "instrument_calibration_file": {
      "title": "Instrument Calibration File",
      "default": "",
      "type": "string"
    }
  },
  "required": [
    "name"
  ],
  "SpectraLevelMetadata": {
    "title": "SpectraLevelMetadata",

```

(continues on next page)

(continued from previous page)

```

    "description": "Metadata for spectra of a windowed decimation level",
    "type": "object",
    "properties": {
      "fs": {
        "title": "Fs",
        "type": "number"
      },
      "n_wins": {
        "title": "N Wins",
        "type": "integer"
      },
      "win_size": {
        "title": "Win Size",
        "exclusiveMinimum": 0,
        "type": "integer"
      },
      "olap_size": {
        "title": "Olap Size",
        "exclusiveMinimum": 0,
        "type": "integer"
      },
      "index_offset": {
        "title": "Index Offset",
        "type": "integer"
      },
      "n_freqs": {
        "title": "N Freqs",
        "type": "integer"
      },
      "freqs": {
        "title": "Freqs",
        "type": "array",
        "items": {
          "type": "number"
        }
      }
    },
    "required": [
      "fs",
      "n_wins",
      "win_size",
      "olap_size",
      "index_offset",
      "n_freqs",
      "freqs"
    ],
    "Record": {
      "title": "Record",
      "description": "Class to hold a record\n\nA record holds information about
↪ a process that was run. It is intended to\ntrack processes applied to data,
↪ allowing a process history to be saved\nalong with any datasets.\n\nExamples\n----"
    }
  },
  "Record": {
    "title": "Record",
    "description": "Class to hold a record\n\nA record holds information about
↪ a process that was run. It is intended to\ntrack processes applied to data,
↪ allowing a process history to be saved\nalong with any datasets.\n\nExamples\n----"
  }
}

```

(continues on next page)

(continued from previous page)

```

<->----\nA simple example of creating a process record\n\n>>> from resistics.common
<->import Record\n\n>>> messages = ["message 1", "message 2"]\n\n>>> record =
<->Record(\n...      creator={"name": "example", "parameter1": 15},\n...
<->messages=messages,\n...      record_type="example"\n... )\n\n>>> record.summary()\n
<->{\n  'time_local': '...',\n  'time_utc': '...',\n  'creator': {'name':
<->'example', 'parameter1': 15},\n  'messages': ['message 1', 'message 2'],\n
<->'record_type': 'example'\n},
    "type": "object",
    "properties": {
        "time_local": {
            "title": "Time Local",
            "type": "string",
            "format": "date-time"
        },
        "time_utc": {
            "title": "Time Utc",
            "type": "string",
            "format": "date-time"
        },
        "creator": {
            "title": "Creator",
            "type": "object"
        },
        "messages": {
            "title": "Messages",
            "type": "array",
            "items": {
                "type": "string"
            }
        },
        "record_type": {
            "title": "Record Type",
            "type": "string"
        }
    },
    "required": [
        "creator",
        "messages",
        "record_type"
    ]
},
    "History": {
        "title": "History",
        "description": "Class for storing processing history\n\nParameters\n-----
<->----\nrecords : List[Record], optional\n    List of records, by default []\n\
<->nExamples\n-----\n\n>>> from resistics.testing import record_example1, record_
<->example2\n\n>>> from resistics.common import History\n\n>>> record1 = record_
<->example1()\n\n>>> record2 = record_example2()\n\n>>> history =
<->History(records=[record1, record2])\n\n>>> history.summary()\n{\n  'records': [\n
<->    {\n      'time_local': '...',\n      'time_utc': '...',\n
<->    'creator': {\n      'name': 'example1',\n      'a': 5,\n
<->n      'b': -7.0\n      },\n      'messages': ['Message 1',

```

(continues on next page)

(continued from previous page)

```

↪ 'Message 2'],\n          'record_type': 'process'\n          },\n          {\n
↪ 'time_local': '...',\n          'time_utc': '...',\n          'creator
↪ ': {\n          'name': 'example2',\n          'a': 'parzen',\n
↪ 'b': -21\n          },\n          'messages': ['Message 5', 'Message
↪ 6'],\n          'record_type': 'process'\n          }\n          ]\n        },
    "type": "object",
    "properties": {
      "records": {
        "title": "Records",
        "default": [],
        "type": "array",
        "items": {
          "$ref": "#/definitions/Record"
        }
      }
    }
  }
}

```

field fs: `List[float]` [Required]

field chans: `List[str]` [Required]

field n\_chans: `int | None = None`

Validated by

- `validate_n_chans`

field n\_levels: `int` [Required]

field first\_time: `HighResDateTime` [Required]

Constraints

- `pattern = %Y-%m-%d %H:%M:%S.%f_%o_%q_%v`
- `examples = ['2021-01-01 00:00:00.000061_035156_250000_000000']`

field last\_time: `HighResDateTime` [Required]

Constraints

- `pattern = %Y-%m-%d %H:%M:%S.%f_%o_%q_%v`
- `examples = ['2021-01-01 00:00:00.000061_035156_250000_000000']`

field system: `str = ''`

field serial: `str = ''`

field wgs84\_latitude: `float = -999.0`

field wgs84\_longitude: `float = -999.0`

field easting: `float = -999.0`

field northing: `float = -999.0`

field elevation: `float` = -999.0

field chans\_metadata: `Dict[str, ChanMetadata]` [Required]

field levels\_metadata: `List[SpectraLevelMetadata]` [Required]

field ref\_time: `HighResDateTime` [Required]

#### Constraints

- `pattern` = `%Y-%m-%d %H:%M:%S.%f_%o_%q_%v`
- `examples` = [`'2021-01-01 00:00:00.000061_035156_250000_000000'`]

field history: `History` = `History(records=[])`

**class** `resistics.spectra.SpectraData(metadata: SpectraMetadata, data: Dict[int, ndarray])`

Bases: `ResisticsData`

Class for holding spectra data

The spectra data is stored in the class as a dictionary mapping decimation level to numpy array. The shape of the array for each decimation level is:

`n_wins x n_chans x n_freqs`

**get\_level**(*level: int*) → `ndarray`

Get the spectra data for a decimation level

**get\_chan**(*level: int, chan: str*) → `ndarray`

Get the channel spectra data for a decimation level

**get\_chans**(*level: int, chans: List[str]*) → `ndarray`

Get the channels spectra data for a decimation level

**get\_freq**(*level: int, idx: int*) → `ndarray`

Get the spectra data at a frequency index for a decimation level

**get\_mag\_phs**(*level: int, unwrap: bool = False*) → `Tuple[ndarray, ndarray]`

Get magnitude and phase for a decimation level

**get\_timestamps**(*level: int*) → `DatetimeIndex`

Get the start time of each window

Note that this does not use high resolution timestamps

#### Parameters

**level** (*int*) – The decimation level

#### Returns

The starts of each window

#### Return type

`pd.DatetimeIndex`

#### Raises

**ValueError** – If the level is out of range

**plot**(*max\_pts: int | None = 10000*) → `Figure`

Stack spectra data for all decimation levels



**Parameters**

**max\_pts** (*Optional*[*int*], *optional*) – The maximum number of points in any individual plot before applying lttbc downsampling, by default 10\_000. If set to None, no downsampling will be applied.

**Returns**

The plotly figure

**Return type**

go.Figure

**plot\_level\_stack**(*level*: *int*, *max\_pts*: *int* = 10000, *grouping*: *str* | *None* = None, *offset*: *str* = '0h') → Figure

Stack the spectra for a decimation level with optional time grouping

**Parameters**

- **level** (*int*) – The decimation level
- **max\_pts** (*int*, *optional*) – The maximum number of points in any individual plot before applying lttbc downsampling, by default 10\_000
- **grouping** (*Optional*[*str*], *optional*) – A grouping interval as a pandas freq string, by default None
- **offset** (*str*, *optional*) – A time offset to add to the grouping, by default “0h”. For instance, to plot night time and day time spectra, set grouping to “12h” and offset to “6h”

**Returns**

The plotly figure

**Return type**

go.Figure

**plot\_level\_section**(*level*: *int*, *grouping*=‘30T’) → Figure

Plot a spectra section

**Parameters**

- **level** (*int*) – The decimation level to plot
- **grouping** (*str*, *optional*) – The time domain resolution, by default “30T”

**Returns**

A plotly figure

**Return type**

go.Figure

**pydantic model** `resistics.spectra.FourierTransform`

Bases: `ResisticsProcess`

Perform a Fourier transform of the windowed data

The processor is inspired by the `scipy.signal.stft` function which performs a similar process and involves a Fourier transform along the last axis of the windowed data.

**Parameters**

- **win\_fnc** (*Union*[*str*, *Tuple*[*str*, *float*]]) – The window to use before performing the FFT, by default (“kaiser”, 14)

- **detrend** (*Union[str, None]*) – Type of detrending to apply before performing FFT, by default linear detrend. Setting to None will not apply any detrending to the data prior to the FFT
- **workers** (*int*) – The number of CPUs to use, by default max - 2

## Examples

This example will get periodic decimated data, perform windowing and run the Fourier transform on the windowed data.

```
>>> import matplotlib.pyplot as plt
>>> import numpy as np
>>> from resistics.testing import decimated_data_periodic
>>> from resistics.window import WindowSetup, Windower
>>> from resistics.spectra import FourierTransform
>>> frequencies = {"chan1": [870, 590, 110, 32, 12], "chan2": [480, 375, 210, 60, 45]}
>>> dec_data = decimated_data_periodic(frequencies, fs=128)
>>> dec_data.metadata.chans
['chan1', 'chan2']
>>> print(dec_data.to_string())
<class 'resistics.decimate.DecimatedData'>
           fs      dt  n_samples      first_time      last_
time
level
0      2048.0  0.000488      16384  2021-01-01 00:00:00  2021-01-01 00:00:07.
→ 99951171875
1       512.0  0.001953       4096  2021-01-01 00:00:00  2021-01-01 00:00:07.
→ 998046875
2       128.0  0.007812       1024  2021-01-01 00:00:00  2021-01-01 00:00:07.
→ 9921875
```

Perform the windowing

```
>>> win_params = WindowSetup().run(dec_data.metadata.n_levels, dec_data.metadata.fs)
>>> win_data = Windower().run(dec_data.metadata.first_time, win_params, dec_data)
```

And then the Fourier transform. By default, the data will be (linearly) detrended and multiplied by a Kaiser window prior to the Fourier transform

```
>>> spec_data = FourierTransform().run(win_data)
```

For plotting of magnitude, let's stack the spectra


```
>>> freqs_0 = spec_data.metadata.levels_metadata[0].freqs
>>> data_0 = np.absolute(spec_data.data[0]).mean(axis=0)
>>> freqs_1 = spec_data.metadata.levels_metadata[1].freqs
>>> data_1 = np.absolute(spec_data.data[1]).mean(axis=0)
>>> freqs_2 = spec_data.metadata.levels_metadata[2].freqs
>>> data_2 = np.absolute(spec_data.data[2]).mean(axis=0)
```

Now plot

```

>>> plt.subplot(3,1,1)
>>> plt.plot(freqs_0, data_0[0], label="chan1")
>>> plt.plot(freqs_0, data_0[1], label="chan2")
>>> plt.grid()
>>> plt.title("Decimation level 0")
>>> plt.legend()
>>> plt.subplot(3,1,2)
>>> plt.plot(freqs_1, data_1[0], label="chan1")
>>> plt.plot(freqs_1, data_1[1], label="chan2")
>>> plt.grid()
>>> plt.title("Decimation level 1")
>>> plt.legend()
>>> plt.subplot(3,1,3)
>>> plt.plot(freqs_2, data_2[0], label="chan1")
>>> plt.plot(freqs_2, data_2[1], label="chan2")
>>> plt.grid()
>>> plt.title("Decimation level 2")
>>> plt.legend()
>>> plt.xlabel("Frequency")
>>> plt.tight_layout()
>>> plt.show()

```



```

{
  "title": "FourierTransform",

```

(continues on next page)

(continued from previous page)

```

"description": "Perform a Fourier transform of the windowed data\n\nThe processor is inspired by the scipy.signal.stft function which performs a similar process and involves a Fourier transform along the last axis of the windowed data.\n\nParameters\n-----\nnwin_fnc : Union[str, Tuple[str, float]]\n    The window to use before performing the FFT, by default ('kaiser', 14)\ndetrend : Union[str, None]\n    Type of detrending to apply before performing FFT, by default linear\ndetrend : Setting to None will not apply any detrending to the data prior to the FFT\nworkers : int\n    The number of CPUs to use, by default max - 2\nExamples\n-----\nThis example will get periodic decimated data, perform windowing and run the Fourier transform on the windowed data.\n\n.. plot::\n    width: 90%\n\n    >>> import matplotlib.pyplot as plt\n    >>> import numpy as np\n    >>> from resistics.testing import decimated_data_periodic\n    >>> from resistics.window import WindowSetup, Windower\n    >>> from resistics.spectra import FourierTransform\n    >>> frequencies = {'chan1': [870, 590, 110, 32, 12], 'chan2': [480, 375, 210, 60, 45]}\n    >>> dec_data = decimated_data_periodic(frequencies, fs=128)\n    >>> dec_data.metadata.chans\n    ['chan1', 'chan2']\n    >>> print(dec_data.to_string())\n    <class 'resistics.Decimate.DecimatedData'\n\n        fs      dt n_samples      first_time\n        last_time\n        level\n    0          2048.0 0.000488\n    16384 2021-01-01 00:00:00 2021-01-01 00:00:07.99951171875\n    1          512.0\n    0.001953      4096 2021-01-01 00:00:00 2021-01-01 00:00:07.998046875\n    2          128.0 0.007812      1024 2021-01-01 00:00:00 2021-01-01 00:00:07.9921875\n\n    Perform the windowing\n\n    >>> win_params = WindowSetup().run(dec_data.metadata.n_levels, dec_data.metadata.fs)\n    >>> win_data = Windower().run(dec_data.metadata.first_time, win_params, dec_data)\n\n    And then the Fourier transform. By default, the data will be (linearly) detrended and multiplied by a Kaiser window prior to the Fourier transform\n\n    >>> spec_data = FourierTransform().run(win_data)\n\n    For plotting of magnitude, let's stack the spectra\n\n    >>> freqs_0 = spec_data.metadata.levels_metadata[0].freqs\n    >>> data_0 = np.absolute(spec_data.data[0]).mean(axis=0)\n\n    >>> freqs_1 = spec_data.metadata.levels_metadata[1].freqs\n    >>> data_1 = np.absolute(spec_data.data[1]).mean(axis=0)\n\n    >>> freqs_2 = spec_data.metadata.levels_metadata[2].freqs\n    >>> data_2 = np.absolute(spec_data.data[2]).mean(axis=0)\n\n    Now plot\n\n    >>> plt.subplot(3,1,1) # doctest: +SKIP\n    >>> plt.plot(freqs_0, data_0[0], label='\"chan1\"') # doctest: +SKIP\n    >>> plt.plot(freqs_0, data_0[1], label='\"chan2\"') # doctest: +SKIP\n    >>> plt.grid()\n\n    >>> plt.title('\"Decimation level 0\"') # doctest: +SKIP\n    >>> plt.legend() # doctest: +SKIP\n\n    >>> plt.subplot(3,1,2) # doctest: +SKIP\n    >>> plt.plot(freqs_1, data_1[0], label='\"chan1\"') # doctest: +SKIP\n    >>> plt.plot(freqs_1, data_1[1], label='\"chan2\"') # doctest: +SKIP\n    >>> plt.grid()\n\n    >>> plt.title('\"Decimation level 1\"') # doctest: +SKIP\n    >>> plt.legend() # doctest: +SKIP\n\n    >>> plt.subplot(3,1,3) # doctest: +SKIP\n    >>> plt.plot(freqs_2, data_2[0], label='\"chan1\"') # doctest: +SKIP\n    >>> plt.plot(freqs_2, data_2[1], label='\"chan2\"') # doctest: +SKIP\n    >>> plt.grid()\n\n    >>> plt.title('\"Decimation level 2\"') # doctest: +SKIP\n    >>> plt.legend() # doctest: +SKIP\n    >>> plt.xlabel('\"Frequency\"') # doctest: +SKIP\n    >>> plt.tight_layout() # doctest: +SKIP\n    >>> plt.show() # doctest: +SKIP",
"type": "object",
"properties": {
  "name": {
    "title": "Name",
    "type": "string"

```

(continues on next page)

(continued from previous page)

```

    },
    "win_fnc": {
      "title": "Win Fnc",
      "default": [
        "kaiser",
        14
      ],
      "anyOf": [
        {
          "type": "string"
        },
        {
          "type": "array",
          "minItems": 2,
          "maxItems": 2,
          "items": [
            {
              "type": "string"
            },
            {
              "type": "number"
            }
          ]
        }
      ]
    },
    "detrend": {
      "title": "Detrend",
      "default": "linear",
      "type": "string"
    },
    "workers": {
      "title": "Workers",
      "default": -2,
      "type": "integer"
    }
  }
}

```

**field win\_fnc:** `str | Tuple[str, float] = ('kaiser', 14)`

**field detrend:** `str | None = 'linear'`

**field workers:** `int = -2`

**run**(*win\_data*: `WindowedData`) → `SpectraData`

Perform the FFT

Data is padded to the next fast length before performing the FFT to speed up processing. Therefore, the output length may not be as expected.

#### Parameters

**win\_data** (`WindowedData`) – The input windowed data

**Returns**

The Fourier transformed output

**Return type**

*SpectraData*

**pydantic model** `resistics.spectra.EvaluationFreqs`

Bases: *ResisticsProcess*

Calculate the spectra values at the evaluation frequencies

This is done using linear interpolation in the complex domain

**Example**

The example will show interpolation to evaluation frequencies on a very simple example. Begin by generating some example spectra data.

```
>>> from resistics.decimate import DecimationSetup
>>> from resistics.spectra import EvaluationFreqs
>>> from resistics.testing import spectra_data_basic
>>> spec_data = spectra_data_basic()
>>> spec_data.metadata.n_levels
1
>>> spec_data.metadata.chans
['chan1']
>>> spec_data.metadata.levels_metadata[0].summary()
{
  'fs': 180.0,
  'n_wins': 2,
  'win_size': 20,
  'olap_size': 5,
  'index_offset': 0,
  'n_freqs': 10,
  'freqs': [0.0, 10.0, 20.0, 30.0, 40.0, 50.0, 60.0, 70.0, 80.0, 90.0]
}
```

The spectra data has only a single channel and a single level which has 2 windows. Now define our evaluation frequencies.

```
>>> eval_freqs = [1, 12, 23, 34, 45, 56, 67, 78, 89]
>>> dec_setup = DecimationSetup(n_levels=1, per_level=9, eval_freqs=eval_freqs)
>>> dec_params = dec_setup.run(spec_data.metadata.fs[0])
>>> dec_params.summary()
{
  'fs': 180.0,
  'n_levels': 1,
  'per_level': 9,
  'min_samples': 256,
  'eval_freqs': [1.0, 12.0, 23.0, 34.0, 45.0, 56.0, 67.0, 78.0, 89.0],
  'dec_factors': [1],
  'dec_increments': [1],
  'dec_fs': [180.0]
}
```

Now calculate the spectra at the evaluation frequencies

```
>>> eval_data = EvaluationFreqs().run(dec_params, spec_data)
>>> eval_data.metadata.levels_metadata[0].summary()
{
  'fs': 180.0,
  'n_wins': 2,
  'win_size': 20,
  'olap_size': 5,
  'index_offset': 0,
  'n_freqs': 9,
  'freqs': [1.0, 12.0, 23.0, 34.0, 45.0, 56.0, 67.0, 78.0, 89.0]
}
```

To double check everything is as expected, let's compare the data. Comparing window 1 gives

```
>>> print(spec_data.data[0][0, 0])
[0.+0.j 1.+1.j 2.+2.j 3.+3.j 4.+4.j 5.+5.j 6.+6.j 7.+7.j 8.+8.j 9.+9.j]
>>> print(eval_data.data[0][0, 0])
[0.1+0.1j 1.2+1.2j 2.3+2.3j 3.4+3.4j 4.5+4.5j 5.6+5.6j 6.7+6.7j 7.8+7.8j
 8.9+8.9j]
```

And window 2

```
>>> print(spec_data.data[0][1, 0])
[-1. +1.j 0. +2.j 1. +3.j 2. +4.j 3. +5.j 4. +6.j 5. +7.j 6. +8.j
 7. +9.j 8.+10.j]
>>> print(eval_data.data[0][1, 0])
[-0.9+1.1j 0.2+2.2j 1.3+3.3j 2.4+4.4j 3.5+5.5j 4.6+6.6j 5.7+7.7j
 6.8+8.8j 7.9+9.9j]
```

```
{
  "title": "EvaluationFreqs",
  "description": "Calculate the spectra values at the evaluation frequencies\n\
  ↳ This is done using linear interpolation in the complex domain\n\nExample\n-----\n\
  ↳ The example will show interpolation to evaluation frequencies on a very\nsimple_\n\
  ↳ example. Begin by generating some example spectra data.\n\n>>> from resistics.\n\
  ↳ decimate import DecimationSetup\n>>> from resistics.spectra import_\n\
  ↳ EvaluationFreqs\n>>> from resistics.testing import spectra_data_basic\n>>> spec_\n\
  ↳ data = spectra_data_basic()\n>>> spec_data.metadata.n_levels\n1\n>>> spec_data.\n\
  ↳ metadata.chans\n['chan1']\n>>> spec_data.metadata.levels_metadata[0].summary()\n{\n\
  ↳ 'fs': 180.0,\n    'n_wins': 2,\n    'win_size': 20,\n    'olap_size': 5,\n    '\n\
  ↳ 'index_offset': 0,\n    'n_freqs': 10,\n    'freqs': [0.0, 10.0, 20.0, 30.0, 40.\n\
  ↳ 0, 50.0, 60.0, 70.0, 80.0, 90.0]\n}\n\nThe spectra data has only a single channel_\n\
  ↳ and a single level which has 2\nwindows. Now define our evaluation frequencies.\n\
  ↳ \n>>> eval_freqs = [1, 12, 23, 34, 45, 56, 67, 78, 89]\n>>> dec_setup =_\n\
  ↳ DecimationSetup(n_levels=1, per_level=9, eval_freqs=eval_freqs)\n>>> dec_params =_\n\
  ↳ dec_setup.run(spec_data.metadata.fs[0])\n>>> dec_params.summary()\n{\n    'fs':_\n\
  ↳ 180.0,\n    'n_levels': 1,\n    'per_level': 9,\n    'min_samples': 256,\n\
  ↳ 'eval_freqs': [1.0, 12.0, 23.0, 34.0, 45.0, 56.0, 67.0, 78.0, 89.0],\n    'dec_\n\
  ↳ factors': [1],\n    'dec_increments': [1],\n    'dec_fs': [180.0]\n}\n\nNow_\n\
  ↳ calculate the spectra at the evaluation frequencies\n\n>>> eval_data =_\n\
  ↳ EvaluationFreqs().run(dec_params, spec_data)\n>>> eval_data.metadata.levels_
```

(continues on next page)

(continued from previous page)

```

↪ metadata[0].summary()\n{\n    'fs': 180.0,\n    'n_wins': 2,\n    'win_size': 20,\n    'olap_size': 5,\n    'index_offset': 0,\n    'n_freqs': 9,\n    'freqs': [1.\n↪ 0, 12.0, 23.0, 34.0, 45.0, 56.0, 67.0, 78.0, 89.0]\n}\n\nTo double check_\n↪ everything is as expected, let's compare the data. Comparing\nwindow 1 gives\n\n>> print(spec_data.data[0][0, 0])\n[0.+0.j 1.+1.j 2.+2.j 3.+3.j 4.+4.j 5.+5.j 6.+6.\n↪ j 7.+7.j 8.+8.j 9.+9.j]\n>> print(eval_data.data[0][0, 0])\n[0.1+0.1j 1.2+1.2j 2.\n↪ 3+2.3j 3.4+3.4j 4.5+4.5j 5.6+5.6j 6.7+6.7j 7.8+7.8j\n8.9+8.9j]\n\nAnd window 2\n\n>> print(spec_data.data[0][1, 0])\n[-1. +1.j 0. +2.j 1. +3.j 2. +4.j 3. +5.\n↪ j 4. +6.j 5. +7.j 6. +8.j\n7. +9.j 8.+10.j]\n>> print(eval_data.data[0][1,\n↪ 0])\n[-0.9+1.1j 0.2+2.2j 1.3+3.3j 2.4+4.4j 3.5+5.5j 4.6+6.6j 5.7+7.7j\n6.\n↪ 8+8.8j 7.9+9.9j]",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        }
    }
}

```

**run**(*dec\_params*: [DecimationParameters](#), *spec\_data*: [SpectraData](#)) → [SpectraData](#)

Interpolate spectra data to the evaluation frequencies

This is a simple linear interpolation.

#### Parameters

- **dec\_params** ([DecimationParameters](#)) – The decimation parameters which have the evaluation frequencies for each decimation level
- **spec\_data** ([SpectraData](#)) – The spectra data

#### Returns

The spectra data at the evaluation frequencies

#### Return type

[SpectraData](#)

**pydantic model** `resistics.spectra.SpectraDataWriter`

Bases: [ResisticsWriter](#)

Writer of resistics spectra data

```

{
    "title": "SpectraDataWriter",
    "description": "Writer of resistics spectra data",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        },
        "overwrite": {
            "title": "Overwrite",
            "default": true,

```

(continues on next page)



(continued from previous page)

```

        "type": "boolean"
    }
}

```

**run**(*dir\_path*: *Path*, *spec\_data*: *SpectraData*) → *None*

Write out SpectraData

#### Parameters

- **dir\_path** (*Path*) – The directory path to write to
- **spec\_data** (*SpectraData*) – Spectra data to write out

#### Raises

**WriteError** – If unable to write to the directory

**pydantic model** *resistics.spectra.SpectraDataReader*

Bases: *ResisticsProcess*

Reader of resistics spectra data

```

{
  "title": "SpectraDataReader",
  "description": "Reader of resistics spectra data",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    }
  }
}

```

**run**(*dir\_path*: *Path*, *metadata\_only*: *bool* = *False*) → *SpectraMetadata* | *SpectraData*

Read SpectraData

#### Parameters

- **dir\_path** (*Path*) – The directory path to read from
- **metadata\_only** (*bool*, *optional*) – Flag for getting metadata only, by default *False*

#### Returns

The *SpectraData* or *SpectraMetadata* if *metadata\_only* is *True*

#### Return type

Union[*SpectraMetadata*, *SpectraData*]

#### Raises

**ReadError** – If the directory does not exist

**pydantic model** *resistics.spectra.SpectraProcess*

Bases: *ResisticsProcess*

Parent class for spectra processes

```
{
  "title": "SpectraProcess",
  "description": "Parent class for spectra processes",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    }
  }
}
```

**run**(*spec\_data*: *SpectraData*) → *SpectraData*

Run a spectra processor

**pydantic model** `resistics.spectra.SpectraSmootherUniform`

Bases: *SpectraProcess*

Smooth a spectra with a uniform filter

For more information, please refer to: [https://docs.scipy.org/doc/scipy/reference/generated/scipy.ndimage.uniform\\_filter1d.html](https://docs.scipy.org/doc/scipy/reference/generated/scipy.ndimage.uniform_filter1d.html)

## Examples

Smooth a simple spectra data instance

```
>>> from resistics.spectra import SpectraSmootherUniform
>>> from resistics.testing import spectra_data_basic
>>> spec_data = spectra_data_basic()
>>> smooth_data = SpectraSmootherUniform(length_proportion=0.5).run(spec_data)
```

Look at the results for the two windows

```
>>> spec_data.data[0][0,0]
array([0.+0.j, 1.+1.j, 2.+2.j, 3.+3.j, 4.+4.j, 5.+5.j, 6.+6.j, 7.+7.j,
       8.+8.j, 9.+9.j])
>>> smooth_data.data[0][0,0]
array([0.8+0.8j, 1.2+1.2j, 2. +2.j , 3. +3.j , 4. +4.j , 5. +5.j ,
       6. +6.j , 7. +7.j , 7.8+7.8j, 8.2+8.2j])
```

```
{
  "title": "SpectraSmootherUniform",
  "description": "Smooth a spectra with a uniform filter\n\nFor more information,\n↪ please refer to:\n↪ https://docs.scipy.org/doc/scipy/reference/generated/scipy.\n↪ ndimage.uniform_filter1d.html\n↪ \nExamples\n-----\n↪ Smooth a simple spectra data\n↪ instance\n\n>>> from resistics.spectra import SpectraSmootherUniform\n↪ >>> from_\n↪ resistics.testing import spectra_data_basic\n↪ >>> spec_data = spectra_data_basic()\n↪ >>> smooth_data = SpectraSmootherUniform(length_proportion=0.5).run(spec_data)\n↪ \nLook at the results for the two windows\n\n>>> spec_data.data[0][0,0]\n↪ \narray([0.\n↪ +0.j, 1.+1.j, 2.+2.j, 3.+3.j, 4.+4.j, 5.+5.j, 6.+6.j, 7.+7.j,\n↪ \n      8.+8.j, 9.\n↪ +9.j])\n\n>>> smooth_data.data[0][0,0]\n↪ \narray([0.8+0.8j, 1.2+1.2j, 2. +2.j , 3. +3.\n↪ j , 4. +4.j , 5. +5.j ,\n↪ \n      6. +6.j , 7. +7.j , 7.8+7.8j, 8.2+8.2j])",
```

(continues on next page)

(continued from previous page)

```

    "type": "object",
    "properties": {
      "name": {
        "title": "Name",
        "type": "string"
      },
      "length_proportion": {
        "title": "Length Proportion",
        "default": 0.1,
        "type": "number"
      }
    }
  }
}

```

**field** `length_proportion`: `float = 0.1`

**run**(*spec\_data*: *SpectraData*) → *SpectraData*

Smooth spectra data with a uniform smoother

**Parameters**

**spec\_data** (*SpectraData*) – The input spectra data

**Returns**

The output spectra data

**Return type**

*SpectraData*

**pydantic model** `resistics.spectra.SpectraSmootherGaussian`

Bases: *SpectraProcess*

Smooth a spectra with a gaussian filter

For more information, please refer to: [https://docs.scipy.org/doc/scipy/reference/generated/scipy.ndimage.gaussian\\_filter1d.html](https://docs.scipy.org/doc/scipy/reference/generated/scipy.ndimage.gaussian_filter1d.html)

## Examples

Smooth a simple spectra data instance

```

>>> from resistics.spectra import SpectraSmootherGaussian
>>> from resistics.testing import spectra_data_basic
>>> spec_data = spectra_data_basic()
>>> smooth_data = SpectraSmootherGaussian().run(spec_data)

```

Look at the results for the two windows

```

>>> spec_data.data[0][0,0]
array([0.+0.j, 1.+1.j, 2.+2.j, 3.+3.j, 4.+4.j, 5.+5.j, 6.+6.j, 7.+7.j,
       8.+8.j, 9.+9.j])
>>> smooth_data.data[0][0,0]
array([1.93603671+1.93603671j, 2.1921536 +2.1921536j ,
       2.67507336+2.67507336j, 3.33255376+3.33255376j,
       4.09862656+4.09862656j, 4.90137344+4.90137344j,

```

(continues on next page)

(continued from previous page)

```
5.66744624+5.66744624j, 6.32492664+6.32492664j,
6.8078464 +6.8078464j , 7.06396329+7.06396329j))
```

```
{
  "title": "SpectraSmootherGaussian",
  "description": "Smooth a spectra with a gaussian filter\n\nFor more information,\n→please refer to:\nhttps://docs.scipy.org/doc/scipy/reference/generated/scipy.\n→ndimage.gaussian_filter1d.html\n\nExamples\n-----\nSmooth a simple spectra_\n→data instance\n\n>>> from resistics.spectra import SpectraSmootherGaussian\n>>>\n→from resistics.testing import spectra_data_basic\n>>> spec_data = spectra_data_\n→basic()\n>>> smooth_data = SpectraSmootherGaussian().run(spec_data)\n\nLook at_\n→the results for the two windows\n>>> spec_data.data[0][0,0]\n→\narray([0.+0.j, 1.\n→+1.j, 2.+2.j, 3.+3.j, 4.+4.j, 5.+5.j, 6.+6.j, 7.+7.j,\n→8.+8.j, 9.+9.j])\n>>\n→smooth_data.data[0][0,0]\n→\narray([1.93603671+1.93603671j, 2.1921536 +2.1921536j ,\n→\n→2.67507336+2.67507336j, 3.33255376+3.33255376j,\n→4.09862656+4.\n→09862656j, 4.90137344+4.90137344j,\n→5.66744624+5.66744624j, 6.32492664+6.\n→32492664j,\n→6.8078464 +6.8078464j , 7.06396329+7.06396329j])",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "sigma": {
      "title": "Sigma",
      "default": 3,
      "type": "number"
    }
  }
}
```

**field sigma:** `float = 3`

**run**(*spec\_data: SpectraData*) → *SpectraData*

Run Gaussian filtering of spectra data

#### Parameters

**spec\_data** (*SpectraData*) – Input spectra data

#### Returns

Output spectra data

#### Return type

*SpectraData*

## resistics.testing module

Module for producing testing data for resistics and helper functions to compare instances of the same object.

This includes testing data for:

- Record
- History
- TimeMetadata
- TimeData
- DecimatedData
- SpectraData
- Evaluation frequency SpectraData
- RegressionInputMetadata
- Solution

`resistics.testing.record_example1()` → *Record*

Get an example Record

`resistics.testing.record_example2()` → *Record*

Get an example Record

`resistics.testing.history_example()` → *History*

Get a History example

`resistics.testing.time_metadata_1chan(fs: float = 10, first_time: str = '2021-01-01 00:00:00', n_samples: int = 11)` → *TimeMetadata*

Get TimeMetadata for a single channel, “chan1”

### Parameters

- **fs** (*float*, *optional*) – The sampling frequency, by default 10
- **first\_time** (*str*, *optional*) – The first time, by default “2021-01-01 00:00:00”
- **n\_samples** (*int*, *optional*) – The number of samples, by default 11

### Returns

TimeMetadata

### Return type

*TimeMetadata*

`resistics.testing.time_metadata_2chan(fs: float = 10, first_time: str = '2021-01-01 00:00:00', n_samples: int = 11)` → *TimeMetadata*

Get a TimeMetadata instance with two channels, “chan1” and “chan2”

### Parameters

- **fs** (*float*, *optional*) – The sampling frequency, by default 10
- **first\_time** (*str*, *optional*) – The first time, by default “2021-01-01 00:00:00”
- **n\_samples** (*int*, *optional*) – The number of samples, by default 11

### Returns

TimeMetadata

**Return type***TimeMetadata*

```
resistics.testing.time_metadata_general(chans: List[str], fs: float = 10, first_time: str = '2020-01-01 00:00:00', n_samples: int = 11) → TimeMetadata
```

Get general time metadata

**Parameters**

- **chans** (*List[str]*) – The channels in the time data
- **fs** (*float*, *optional*) – The sampling frequency, by default 10
- **first\_time** (*\_type\_*, *optional*) – The time of the first sample, by default “2020-01-01 00:00:00”
- **n\_samples** (*int*, *optional*) – The number of samples, by default 11

**Returns**

An instance of TimeMetadata with the appropriate properties

**Return type***TimeMetadata*

```
resistics.testing.time_metadata_mt(fs: float = 10, first_time: str = '2020-01-01 00:00:00', n_samples: int = 11) → TimeMetadata
```

Get a magnetotelluric time metadata with four channels “Ex”, “Ey”, “Hx”, “Hy”

**Parameters**

- **fs** (*float*, *optional*) – The sampling frequency, by default 10
- **first\_time** (*str*, *optional*) – The first time, by default “2020-01-01 00:00:00”
- **n\_samples** (*int*, *optional*) – The number of samples, by default 11

**Returns**

TimeMetadata

**Return type***TimeMetadata*

```
resistics.testing.time_data_ones(fs: float = 10, first_time: str = '2020-01-01 00:00:00', n_samples: int = 10, dtype: Type | None = None) → TimeData
```

TimeData with all ones

**Parameters**

- **fs** (*float*, *optional*) – The sampling frequency, by default 10
- **first\_time** (*str*, *optional*) – The time of the first sample, by default “2020-01-01 00:00:00”
- **n\_samples** (*int*, *optional*) – The number of samples, by default 10
- **dtype** (*Optional[Type]*, *optional*) – The data type for the values, by default None

**Returns**

The TimeData

**Return type***TimeData*

```
resistics.testing.time_data_simple(fs: float = 10, first_time: str = '2020-01-01 00:00:00', dtype: Type |
None = None) → TimeData
```

Time data with 16 samples

#### Parameters

- **fs** (*float*, *optional*) – The sampling frequency, by default 10
- **first\_time** (*str*, *optional*) – The time of the first sample, by default “2020-01-01 00:00:00”
- **dtype** (*Optional[Type]*, *optional*) – The data type for the values, by default None

#### Returns

The TimeData

#### Return type

*TimeData*

```
resistics.testing.time_data_with_nans(fs: float = 10, first_time: str = '2020-01-01 00:00:00', dtype: Type |
None = None) → TimeData
```

TimeData with 16 samples and some nan values

#### Parameters

- **fs** (*float*, *optional*) – Sampling frequency, by default 10
- **first\_time** (*str*, *optional*) – The time of the first sample, by default “2020-01-01 00:00:00”
- **dtype** (*Optional[Type]*, *optional*) – The data type for the values, by default None

#### Returns

The TimeData

#### Return type

*TimeData*

```
resistics.testing.time_data_linear(fs: float = 10, first_time: str = '2020-01-01 00:00:00', n_samples: int
= 10, dtype: Type | None = None) → TimeData
```

Get TimeData with linear data

#### Parameters

- **fs** (*float*, *optional*) – The sampling frequency, by default 10
- **first\_time** (*str*, *optional*) – Time of first sample, by default “2020-01-01 00:00:00”
- **n\_samples** (*int*, *optional*) – The number of samples, by default 10
- **dtype** (*Optional[Type]*, *optional*) – The data type for the values, by default None

#### Returns

TimeData with linear values

#### Return type

*TimeData*

```
resistics.testing.time_data_random(fs: float = 10, first_time: str = '2020-01-01 00:00:00', n_samples: int
= 10, dtype: Type | None = None) → TimeData
```

TimeData with random values and specifiable number of samples

#### Parameters

- **fs** (*float*, *optional*) – The sampling frequency, by default 10

- **first\_time** (*str*, *optional*) – Time of first sample, by default “2020-01-01 00:00:00”
- **n\_samples** (*int*, *optional*) – The number of samples, by default 10
- **dtype** (*Optional*[*Type*], *optional*) – The data type for the values, by default None

**Returns**

The TimeData

**Return type**

*TimeData*

```
resistics.testing.time_data_periodic(frequencies: List[float], fs: float = 50, first_time: str = '2020-01-01
00:00:00', n_samples: int = 100, dtype: Type | None = None) →
TimeData
```

Get period TimeData

**Parameters**

- **frequencies** (*List*[*float*]) – Frequencies to include
- **fs** (*float*, *optional*) – Sampling frequency, by default 50
- **first\_time** (*str*, *optional*) – The first time, by default “2020-01-01 00:00:00”
- **n\_samples** (*int*, *optional*) – The number of samples, by default 100
- **dtype** (*Optional*[*Type*], *optional*) – The data type for the values, by default None

**Returns**

Periodic TimeData

**Return type**

*TimeData*

```
resistics.testing.time_data_with_offset(offset=0.05, fs: float = 10, first_time: str = '2020-01-01
00:00:00', n_samples: int = 11, dtype: Type | None = None) →
TimeData
```

Get TimeData with an offset on the sampling

**Parameters**

- **offset** (*float*, *optional*) – The offset on the sampling in seconds, by default 0.05
- **fs** (*float*, *optional*) – The sampling frequency, by default 10
- **first\_time** (*str*, *optional*) – The first time of the TimeData, by default “2020-01-01 00:00:00”
- **n\_samples** (*int*, *optional*) – The number of samples, by default 11
- **dtype** (*Optional*[*Type*], *optional*) – The data type for the values, by default None

**Returns**

The TimeData

**Return type**

*TimeData*

```
resistics.testing.decimated_metadata(fs: float = 0.25, first_time: str = '2021-01-01 00:00:00', n_samples:
int = 1024, n_levels: int = 3, factor: int = 4) → DecimatedMetadata
```

Get example decimated metadata

The final level has n\_samples. The number of samples for all other levels is calculated using a decimation factor of 4.



Similarly for the sampling frequencies, the final level is assumed to have a sample frequency of `fs` and all other levels sampling frequencies are calculated from there.

#### Parameters

- **fs** (*float*, *optional*) – The sampling frequency of the last level, by default 0.25
- **first\_time** (*str*, *optional*) – The time of the first sample, by default “2021-01-01 00:00:00”
- **n\_samples** (*int*, *optional*) – The number of samples, by default 1024
- **n\_levels** (*int*, *optional*) – The number of decimation levels, by default 3
- **factor** (*int*, *optional*) – The decimation factor for each level, by default 4

#### Returns

DecimatedMetadata

#### Return type

*DecimatedMetadata*

```
resistics.testing.decimated_data_random(fs: float = 0.25, first_time: str = '2021-01-01 00:00:00',
                                       n_samples: int = 1024, n_levels: int = 3, factor: int = 4) →
                                       DecimatedData
```

Get random decimated data

#### Parameters

- **fs** (*float*, *optional*) – Sampling frequency, by default 10
- **first\_time** (*str*, *optional*) – The time of the first sample, by default “2021-01-01 00:00:00”
- **n\_samples** (*int*, *optional*) – The number of samples, by default 1024
- **n\_levels** (*int*, *optional*) – The number of levels, by default 3
- **factor** (*int*, *optional*) – The decimation factor for each level, by default 4

#### Returns

The decimated data

#### Return type

*DecimatedData*

```
resistics.testing.decimated_data_linear(fs: float = 0.25, first_time: str = '2021-01-01 00:00:00',
                                       n_samples: int = 1024, n_levels: int = 3, factor: int = 4)
```

Get linear decimated data

#### Parameters

- **fs** (*float*, *optional*) – Sampling frequency, by default 10
- **first\_time** (*str*, *optional*) – The time of the first sample, by default “2021-01-01 00:00:00”
- **n\_samples** (*int*, *optional*) – The number of samples, by default 1024
- **n\_levels** (*int*, *optional*) – The number of levels, by default 3
- **factor** (*int*, *optional*) – The decimation factor for each level, by default 4

#### Returns

The decimated data

**Return type***DecimatedData*

```
resistics.testing.decimated_data_periodic(frequencies: Dict[str, List[float]], fs: float = 0.25, first_time: str = '2021-01-01 00:00:00', n_samples: int = 1024, n_levels: int = 3, factor: int = 4)
```

Get periodic decimated data

**Parameters**

- **frequencies** (*Dict[str, List[float]]*) – Mapping from channel to list of frequencies to add
- **fs** (*float, optional*) – Sampling frequency, by default 10
- **first\_time** (*str, optional*) – The time of the first sample, by default “2021-01-01 00:00:00”
- **n\_samples** (*int, optional*) – The number of samples, by default 1024
- **n\_levels** (*int, optional*) – The number of levels, by default 3
- **factor** (*int, optional*) – The decimation factor for each level, by default 4

**Returns**

The decimated data

**Return type***DecimatedData*

```
resistics.testing.spectra_metadata_multilevel(fs: float = 128, n_levels: int = 3, n_wins: List[int] | int = 2, index_offset: List[int] | int = 0, chans: List[str] | None = None) → SpectraMetadata
```

Get spectra metadata with multiple levels and two channels

**Parameters**

- **fs** (*float, optional*) – The original sampling frequency, by default 128
- **n\_levels** (*int, optional*) – The number of levels, by default 3
- **n\_wins** (*Union[List[int], int]*) – The number of windows for each level
- **index\_offset** (*Union[List[int], int], optional*) – The index offset vs. the reference time, by default 0
- **chans** (*Optional[List[str]]*) – The channels in the data, by default None. If None, the channels will be chan1 and chan2

**Returns**

SpectraMetadata with n\_levels

**Return type***SpectraMetadata***Raises**

**ValueError** – If the number of user input channels does not equal two

```
resistics.testing.spectra_data_basic() → SpectraData
```

Spectra data with a single decimation level

**Returns**

Spectra data with a single level, a single channel and two windows

**Return type***SpectraData*

`resistics.testing.generate_evaluation_data(chans: List[str], soln: Solution, n_wins: int) → ndarray`

Generate evaluation frequency data that satisfies a provided solution

The returned array has the shape: `n_wins x n_chans x n_evals` Which is close to the shape required for spectra data

There is an extra check provided to check if a channel appears in both the input and output channels, which could be a tricky scenario.

The data is produced randomly using `np.random.randn`, meaning that it is sampled from a standard normal distribution

**Parameters**

- **chans** (*List[str]*) – The channels in the data
- **soln** (*Solution*) – The Solution that needs to be satisfied
- **n\_wins** (*int*) – The number of windows to generate

**Returns**

The evaluation frequency data array

**Return type**

`np.ndarray`

`resistics.testing.evaluation_data(fs: float, dec_params: DecimationParameters, n_wins: int, soln: Solution) → SpectraData`

Generate evaluation frequency data that will satisfy a given solution. This will generate random data between the low and high values

**Parameters**

- **fs** (*float*) – The sampling frequency of the original data
- **dec\_params** (*DecimationParameters*) – The data decimation information
- **n\_wins** (*int*) – The number of windows to generate
- **soln** (*Solution*) – The solution that the generated data should satisfy

**Returns**

The evaluation frequency data

**Return type***SpectraData***Raises**

**ValueError** – If the number of evaluation frequencies is not exactly divisible by the number of levels

`resistics.testing.transfer_function_random(n_in: int, n_out: int) → TransferFunction`

Generate a random transfer function

`n_in` and `n_out` must be less than or equal to 26 as the random samples are taken from the alphabet

**Parameters**

- **n\_in** (*int*) – Number of input channels
- **n\_out** (*int*) – Number of output channels

**Returns**

A randomly generated transfer function

**Return type**

*TransferFunction*

**Raises**

**ValueError** – If any of the channel names is duplicated

```
resistics.testing.regression_input_metadata_single_site(fs: float, freqs: List[float], tf:
                                                    TransferFunction) →
                                                    RegressionInputMetadata
```

Given a transfer function, get example regression input metadata assuming a single site

**Parameters**

- **fs** (*float*) – The sampling frequency
- **freqs** (*List[float]*) – The evaluation frequencies
- **tf** (*TransferFunction*) – The transfer function for which to create RegressionInputMetadata

**Returns**

Example regression input metadata with fs=128 and 5 evaluation frequencies

**Return type**

*RegressionInputMetadata*

```
resistics.testing.components_mt() → Dict[str, Component]
```

Get example components for the Impedance Tensor

**Returns**

Dictionary of component values (ExHx, ExHy, EyHx, EyHy)

**Return type**

*Dict[str, Component]*

```
resistics.testing.solution_mt() → Solution
```

Get an example impedance tensor solution

**Returns**

The solution for an MT dataset

**Return type**

*Solution*

```
resistics.testing.solution_general(fs: float, tf: TransferFunction, n_evals: int, components: Dict[str,
                                                                                               Component]) → Solution
```

Create a Solution instance from the specified components

**Parameters**

- **fs** (*float*) – The sampling frequency of the original data
- **tf** (*TransferFunction*) – The transfer function to be solved
- **n\_evals** (*int*) – The number of evaluation frequencies
- **components** (*Dict[str, Component]*) – The components of the solution

**Returns**

The Solution instance

**Return type***Solution*

`resistics.testing.solution_random_int(fs: float, tf: TransferFunction, n_evals=10, low: int = -10, high: int = 10) → Solution`

Generate a set of random integer components for a solution

**Parameters**

- **fs** (*float*) – The original sampling frequency of the data
- **tf** (*TransferFunction*) – The transfer function
- **n\_evals** (*int*, *optional*) – The number of evaluation frequencies, by default 10
- **low** (*int*, *optional*) – A low value for the integers, by default -10
- **high** (*int*, *optional*) – A high value for the integers, by default 10

**Returns**

A randomly generated solution for the transfer function

**Return type***Solution*

`resistics.testing.solution_random_float(fs: float, tf: TransferFunction, n_evals=10) → Solution`

Generate a set of random float components for a solution

This uses the numpy `np.random.randn` which generates numbers on a standard distribution and then multiplies that with a random integer between 0 and 10.

**Parameters**

- **fs** (*float*) – The original sampling frequency of the data
- **tf** (*TransferFunction*) – The transfer function
- **n\_evals** (*int*, *optional*) – The number of evaluation frequencies, by default 10

**Returns**

A randomly generated solution for the transfer function

**Return type***Solution*

`resistics.testing.remove_record_times(records: Dict) → Dict`

Remove timestamps from records

Timestamps can make comparison of two data objects harder as processes need to have been run at exactly the same time for equality, which is unlikely to be the case in tests

**Parameters**

**records** (*Dict*) – The history records

**Returns**

The history records with timestamps removed

**Return type***Dict*

`resistics.testing.assert_time_data_equal(time_data1: TimeData, time_data2: TimeData, history_times: bool = True)`

Assert that two time data instances are equal

**Parameters**

- **time\_data1** ([TimeData](#)) – Time data 1
- **time\_data2** ([TimeData](#)) – Time data 2
- **history\_times** (*bool*, *optional*) – Flag to include history timestamps in the comparison, by default True. Including timestamps will cause a failure if processes were not run at exactly the same time.

`resisticks.testing.assert_soln_equal(soln1: Solution, soln2: Solution)`

Check that two solutions are nearly the same

#### Parameters

- **soln1** ([Solution](#)) – The first solution
- **soln2** ([Solution](#)) – The second solution

## resisticks.time module

Classes and methods for storing and manipulating time data, including:

- The [TimeMetadata](#) model for defining metadata for [TimeData](#)
- The [TimeData](#) class for storing [TimeData](#)
- Implementations of time data readers for numpy and ascii formatted [TimeData](#)
- [TimeData](#) processors

**pydantic model** `resisticks.time.ChanMetadata`

Bases: [Metadata](#)

Channel metadata

```
{
  "title": "ChanMetadata",
  "description": "Channel metadata",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "data_files": {
      "title": "Data Files",
      "type": "array",
      "items": {
        "type": "string"
      }
    },
    "chan_type": {
      "title": "Chan Type",
      "type": "string"
    },
    "chan_source": {
      "title": "Chan Source",
      "type": "string"
    }
  }
}
```

(continues on next page)

(continued from previous page)

```

    "sensor": {
      "title": "Sensor",
      "default": "",
      "type": "string"
    },
    "serial": {
      "title": "Serial",
      "default": "",
      "type": "string"
    },
    "gain1": {
      "title": "Gain1",
      "default": 1,
      "type": "number"
    },
    "gain2": {
      "title": "Gain2",
      "default": 1,
      "type": "number"
    },
    "scaling": {
      "title": "Scaling",
      "default": 1,
      "type": "number"
    },
    "chopper": {
      "title": "Chopper",
      "default": false,
      "type": "boolean"
    },
    "dipole_dist": {
      "title": "Dipole Dist",
      "default": 1,
      "type": "number"
    },
    "sensor_calibration_file": {
      "title": "Sensor Calibration File",
      "default": "",
      "type": "string"
    },
    "instrument_calibration_file": {
      "title": "Instrument Calibration File",
      "default": "",
      "type": "string"
    }
  },
  "required": [
    "name"
  ]
}

```

field name: `str` [Required]

The name of the channel

**field data\_files:** `List[str] | None = None`

The data files

Validated by

- `validate_data_files`

**field chan\_type:** `str | None = None`

The channel type, electric, magnetic or unknown

Validated by

- `validate_chan_type`

**field chan\_source:** `str | None = None`

The name of channel in the data source, can be ignored if not required

**field sensor:** `str = ''`

The name of the sensor

**field serial:** `str = ''`

The serial number of the sensor

**field gain1:** `float = 1`

Primary channel gain

**field gain2:** `float = 1`

Secondary channel gain

**field scaling:** `float = 1`

Scaling to apply to the data. May include the gains and other scaling

**field chopper:** `bool = False`

Boolean flag for chopper on

**field dipole\_dist:** `float = 1`

Dipole spacing for the channel

**field sensor\_calibration\_file:** `str = ''`

Explicit name of sensor calibration file

**field instrument\_calibration\_file:** `str = ''`

Explicit name of instrument calibration file

**electric()** → `bool`

True if the channel is an electric channel

**magnetic()** → `bool`

True if the channel is a magnetic channel

**pydantic model** `resisticks.time.TimeMetadata`

Bases: `WriteableMetadata`

Time metadata



```

{
  "title": "TimeMetadata",
  "description": "Time metadata",
  "type": "object",
  "properties": {
    "file_info": {
      "$ref": "#/definitions/ResisticsFile"
    },
    "fs": {
      "title": "Fs",
      "type": "number"
    },
    "chans": {
      "title": "Chans",
      "type": "array",
      "items": {
        "type": "string"
      }
    },
    "n_chans": {
      "title": "N Chans",
      "type": "integer"
    },
    "n_samples": {
      "title": "N Samples",
      "type": "integer"
    },
    "first_time": {
      "title": "First Time",
      "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
      "examples": [
        "2021-01-01 00:00:00.000061_035156_250000_000000"
      ]
    },
    "last_time": {
      "title": "Last Time",
      "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
      "examples": [
        "2021-01-01 00:00:00.000061_035156_250000_000000"
      ]
    },
    "system": {
      "title": "System",
      "default": "",
      "type": "string"
    },
    "serial": {
      "title": "Serial",
      "default": "",
      "type": "string"
    },
    "wgs84_latitude": {

```

(continues on next page)

(continued from previous page)

```

        "title": "Wgs84 Latitude",
        "default": -999.0,
        "type": "number"
    },
    "wgs84_longitude": {
        "title": "Wgs84 Longitude",
        "default": -999.0,
        "type": "number"
    },
    "easting": {
        "title": "Easting",
        "default": -999.0,
        "type": "number"
    },
    "northing": {
        "title": "Northing",
        "default": -999.0,
        "type": "number"
    },
    "elevation": {
        "title": "Elevation",
        "default": -999.0,
        "type": "number"
    },
    "chans_metadata": {
        "title": "Chans Metadata",
        "type": "object",
        "additionalProperties": {
            "$ref": "#/definitions/ChanMetadata"
        }
    },
    "history": {
        "title": "History",
        "default": {
            "records": []
        },
        "allOf": [
            {
                "$ref": "#/definitions/History"
            }
        ]
    },
    "required": [
        "fs",
        "chans",
        "n_samples",
        "first_time",
        "last_time",
        "chans_metadata"
    ],
    "definitions": {

```

(continues on next page)

(continued from previous page)

```

"ResisticsFile": {
  "title": "ResisticsFile",
  "description": "Required information for writing out a resistics file",
  "type": "object",
  "properties": {
    "created_on_local": {
      "title": "Created On Local",
      "type": "string",
      "format": "date-time"
    },
    "created_on_utc": {
      "title": "Created On Utc",
      "type": "string",
      "format": "date-time"
    },
    "version": {
      "title": "Version",
      "type": "string"
    }
  }
},
"ChanMetadata": {
  "title": "ChanMetadata",
  "description": "Channel metadata",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "data_files": {
      "title": "Data Files",
      "type": "array",
      "items": {
        "type": "string"
      }
    },
    "chan_type": {
      "title": "Chan Type",
      "type": "string"
    },
    "chan_source": {
      "title": "Chan Source",
      "type": "string"
    },
    "sensor": {
      "title": "Sensor",
      "default": "",
      "type": "string"
    },
    "serial": {
      "title": "Serial",

```

(continues on next page)

(continued from previous page)

```

        "default": "",
        "type": "string"
    },
    "gain1": {
        "title": "Gain1",
        "default": 1,
        "type": "number"
    },
    "gain2": {
        "title": "Gain2",
        "default": 1,
        "type": "number"
    },
    "scaling": {
        "title": "Scaling",
        "default": 1,
        "type": "number"
    },
    "chopper": {
        "title": "Chopper",
        "default": false,
        "type": "boolean"
    },
    "dipole_dist": {
        "title": "Dipole Dist",
        "default": 1,
        "type": "number"
    },
    "sensor_calibration_file": {
        "title": "Sensor Calibration File",
        "default": "",
        "type": "string"
    },
    "instrument_calibration_file": {
        "title": "Instrument Calibration File",
        "default": "",
        "type": "string"
    }
},
"required": [
    "name"
],
"Record": {
    "title": "Record",
    "description": "Class to hold a record\n\nA record holds information about
↪ a process that was run. It is intended to\ntrack processes applied to data,
↪ allowing a process history to be saved\nalong with any datasets.\n\nExamples\n----
↪ ----\nA simple example of creating a process record\n\n>>> from resistics.common
↪ import Record\n>>> messages = ["message 1", "message 2"]\n>>> record =
↪ Record(\n...     creator={"name": "example", "parameter1": 15},\n...
↪ messages=messages,\n...     record_type="example"\n... )\n>>> record.summary()\n

```

(continues on next page)

(continued from previous page)

```

→{\n    'time_local': '...',\n    'time_utc': '...',\n    'creator': {'name':
→'example', 'parameter1': 15},\n    'messages': ['message 1', 'message 2'],\n
→'record_type': 'example'\n}",
    "type": "object",
    "properties": {
        "time_local": {
            "title": "Time Local",
            "type": "string",
            "format": "date-time"
        },
        "time_utc": {
            "title": "Time Utc",
            "type": "string",
            "format": "date-time"
        },
        "creator": {
            "title": "Creator",
            "type": "object"
        },
        "messages": {
            "title": "Messages",
            "type": "array",
            "items": {
                "type": "string"
            }
        },
        "record_type": {
            "title": "Record Type",
            "type": "string"
        }
    },
    "required": [
        "creator",
        "messages",
        "record_type"
    ],
    "History": {
        "title": "History",
        "description": "Class for storing processing history\n\nParameters\n-----
→---\nrecords : List[Record], optional\n    List of records, by default []\n\n
→Examples\n-----\n>>> from resistics.testing import record_example1, record_
→example2\n>>> from resistics.common import History\n>>> record1 = record_
→example1()\n>>> record2 = record_example2()\n>>> history =
→History(records=[record1, record2])\n>>> history.summary()\n{\n    'records': [\n
→    {\n        'time_local': '...',\n        'time_utc': '...',\n
→    'creator': {\n        'name': 'example1',\n        'a': 5,\n
→    'b': -7.0\n    },\n        'messages': ['Message 1',
→'Message 2'],\n        'record_type': 'process'\n    },\n    {\n
→    'time_local': '...',\n        'time_utc': '...',\n        'creator
→': {\n        'name': 'example2',\n        'a': 'parzen',\n
→    'b': -21\n    },\n        'messages': ['Message 5', 'Message

```

(continues on next page)

(continued from previous page)

```

↪6'],\n          'record_type': 'process'\n          }\n    ]\n}",
    "type": "object",
    "properties": {
      "records": {
        "title": "Records",
        "default": [],
        "type": "array",
        "items": {
          "$ref": "#/definitions/Record"
        }
      }
    }
  }
}

```

**field fs:** `float` [Required]

The sampling frequency

**field chans:** `List[str]` [Required]

List of channels

**field n\_chans:** `int | None` = None

The number of channels

Validated by

- `validate_n_chans`

**field n\_samples:** `int` [Required]

The number of samples

**field first\_time:** `HighResDateTime` [Required]

The datetime of the first sample

Constraints

- `pattern` = `%Y-%m-%d %H:%M:%S.%f_%o_%q_%v`
- `examples` = `['2021-01-01 00:00:00.000061_035156_250000_000000']`

**field last\_time:** `HighResDateTime` [Required]

The datetime of the last sample

Constraints

- `pattern` = `%Y-%m-%d %H:%M:%S.%f_%o_%q_%v`
- `examples` = `['2021-01-01 00:00:00.000061_035156_250000_000000']`

**field system:** `str` = ''

The system used for recording

**field serial:** `str` = ''

Serial number of the system

**field wgs84\_latitude:** `float` = -999.0

Latitude in WGS84

**field wgs84\_longitude:** `float` = -999.0  
Longitude in WGS84

**field easting:** `float` = -999.0  
The easting of the site in local cartersian coordinates

**field northing:** `float` = -999.0  
The northing of the site in local cartersian coordinates

**field elevation:** `float` = -999.0  
The elevation of the site

**field chans\_metadata:** `Dict[str, ChanMetadata]` [Required]  
List of channel metadata

**field history:** `History` = `History(records=[])`  
Processing history

**property dt:** `float`  
Get the sampling frequency

**property duration:** `timedelta`  
Get the duration of the recording

**property nyquist:** `float`  
Get the nyquist frequency

**get\_chan\_types()** → `List[str]`  
Get all the different channel types

**Returns**  
A list of different channel types

**Return type**  
`List[str]`

### Examples

```
>>> from resisticks.testing import time_metadata_mt
>>> metadata = time_metadata_mt()
>>> metadata.get_chan_types()
['electric', 'magnetic']
```

**get\_chans\_with\_type**(*chan\_type: str*) → `List[str]`  
Get channels with the given type

**Parameters**  
**chan\_type** (*str*) – The channel type

**Returns**  
A list of channels with the given channel type

**Return type**  
`List[str]`

### Examples

```
>>> from resisticks.testing import time_metadata_mt
>>> metadata = time_metadata_mt()
>>> metadata.get_chans_with_type("magnetic")
['Hx', 'Hy']
```

**get\_electric\_chans()** → `List[str]`

Get list of electric channels

**Returns**

List of electric channels

**Return type**

`List[str]`

### Examples

```
>>> from resisticks.testing import time_metadata_mt
>>> metadata = time_metadata_mt()
>>> metadata.get_electric_chans()
['Ex', 'Ey']
```

**get\_magnetic\_chans()** → `List[str]`

Get list of magnetic channels

**Returns**

List of magnetic channels

**Return type**

`List[str]`

### Examples

```
>>> from resisticks.testing import time_metadata_mt
>>> metadata = time_metadata_mt()
>>> metadata.get_magnetic_chans()
['Hx', 'Hy']
```

**any\_electric()** → `bool`

True if any channels are electric

**any\_magnetic()** → `bool`

True if any channels are magnetic

**resisticks.time.get\_time\_metadata**(*time\_dict: Dict[str, Any], chans\_dict: Dict[str, Dict[str, Any]]*) → *TimeMetadata*

Get metadata for TimeData

The time and channel dictionaries must have the TimeMetadata required fields. For more information about the required fields, see [TimeMetadata](#)

**Parameters**

- **time\_dict** (*Dict[str, Any]*) – Dictionary with metadata for the whole dataset



- **chans\_dict** (*Dict[str, Dict[str, Any]]*) – Dictionary of dictionaries with metadata for each channel

**Returns**

Metadata for TimeData

**Return type**

*TimeMetadata*

See also:

*TimeMetadata*

The TimeMetadata class which is returned

**Examples**

```
>>> from resistics.time import get_time_metadata
>>> time_dict = {
...     "fs": 10,
...     "n_samples": 100,
...     "chans": ["Ex", "Hy"],
...     "n_chans": 2,
...     "first_time": "2021-01-01 00:00:00",
...     "last_time": "2021-01-01 00:01:00"
... }
>>> chans_dict = {
...     "Ex": {"name": "Ex", "data_files": "example.ascii"},
...     "Hy": {"name": "Hy", "data_files": "example2.ascii", "sensor": "MFS"}
... }
>>> metadata = get_time_metadata(time_dict, chans_dict)
>>> metadata.summary()
{
  'file_info': None,
  'fs': 10.0,
  'chans': ['Ex', 'Hy'],
  'n_chans': 2,
  'n_samples': 100,
  'first_time': '2021-01-01 00:00:00.000000_000000_000000_000000',
  'last_time': '2021-01-01 00:01:00.000000_000000_000000_000000',
  'system': '',
  'serial': '',
  'wgs84_latitude': -999.0,
  'wgs84_longitude': -999.0,
  'easting': -999.0,
  'northing': -999.0,
  'elevation': -999.0,
  'chans_metadata': {
    'Ex': {
      'name': 'Ex',
      'data_files': ['example.ascii'],
      'chan_type': 'electric',
      'chan_source': None,
      'sensor': '',
      'serial': '',

```

(continues on next page)

(continued from previous page)

```

        'gain1': 1,
        'gain2': 1,
        'scaling': 1,
        'chopper': False,
        'dipole_dist': 1,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    },
    'Hy': {
        'name': 'Hy',
        'data_files': ['example2.ascii'],
        'chan_type': 'magnetic',
        'chan_source': None,
        'sensor': 'MFS',
        'serial': '',
        'gain1': 1,
        'gain2': 1,
        'scaling': 1,
        'chopper': False,
        'dipole_dist': 1,
        'sensor_calibration_file': '',
        'instrument_calibration_file': ''
    }
},
'history': {'records': []}
}

```

`resistics.time.adjust_time_metadata(metadata: TimeMetadata, fs: float, first_time: attodatetime, n_samples: int) → TimeMetadata`

Adjust time data metadata

This is required if changes have been made to the sampling frequency, the time of the first sample of the number of samples. This might occur in processes such as resampling or decimating.

**Warning:** The metadata passed in will be changed in place. If the original metadata should be retained, pass through a deepcopy

### Parameters

- **metadata** (`TimeMetadata`) – Metadata to adjust
- **fs** (`float`) – The sampling frequency
- **first\_time** (`RSDatetime`) – The first time of the data
- **n\_samples** (`int`) – The number of samples

### Returns

Adjusted metadata

### Return type

`TimeMetadata`

## Examples

```
>>> from resisticks.sampling import to_datetime
>>> from resisticks.time import adjust_time_metadata
>>> from resisticks.testing import time_metadata_2chan
>>> metadata = time_metadata_2chan(fs=10, first_time="2021-01-01 00:00:00", n_
↳ samples=101)
>>> metadata.fs
10.0
>>> metadata.n_samples
101
>>> metadata.first_time
datetime.datetime(2021, 1, 1, 0, 0, 0, 0)
>>> metadata.last_time
datetime.datetime(2021, 1, 1, 0, 0, 10, 0)
>>> metadata = adjust_time_metadata(metadata, 20, to_datetime("2021-03-01 00:01:00
↳"), 50)
>>> metadata.fs
20.0
>>> metadata.n_samples
50
>>> metadata.first_time
datetime.datetime(2021, 3, 1, 0, 1, 0, 0)
>>> metadata.last_time
datetime.datetime(2021, 3, 1, 0, 1, 2, 450000)
```

**class** resisticks.time.**TimeData**(*metadata*: [TimeMetadata](#), *data*: *ndarray*)

Bases: [ResisticksData](#)

Class for holding time data

The data values are stored in an numpy array attribute named *data*. This has shape:

*n\_chans* x *n\_samples*

### Parameters

- **metadata** ([TimeMetadata](#)) – Metadata for the TimeData
- **data** (*np.ndarray*) – Numpy array of the data

## Examples

```
>>> import numpy as np
>>> from resisticks.testing import time_metadata_2chan
>>> from resisticks.time import TimeData
>>> data = [[1, 2, 3, 4, 5, 6, 7, 8, 9, 10, 11], [11, 10, 9, 8, 7, 6, 5, 4, 3, 2,
↳ 1]]
>>> time_data = TimeData(time_metadata_2chan(), np.array(data))
>>> time_data.metadata.chans
['chan1', 'chan2']
>>> time_data.get_chan("chan1")
array([ 1,  2,  3,  4,  5,  6,  7,  8,  9, 10, 11])
>>> time_data["chan1"]
array([ 1,  2,  3,  4,  5,  6,  7,  8,  9, 10, 11])
```

**get\_chan\_index**(*chan*: *str*) → *int*

Get the channel index in the data

**Parameters**

**chan** (*str*) – The channel

**Returns**

The index

**Return type**

*int*

**get\_chan**(*chan*: *str*) → *ndarray*

Get the time data for a channel

**Parameters**

**chan** (*str*) – The channel for which to get the time data

**Returns**

pandas Series with channel data and datetime index

**Return type**

*np.ndarray*

**set\_chan**(*chan*: *str*, *chan\_data*: *ndarray*) → *None*

Set channel time data

**Parameters**

- **chan** (*str*) – The channel to set the data for
- **chan\_data** (*np.ndarray*) – The new channel data

**Raises**

- **ValueError** – If the data has incorrect size
- **ValueError** – If the data has incorrect dtype

**get\_timestamps**(*samples*: *ndarray* | *None* = *None*, *estimate*: *bool* = *True*) → *ndarray* | *DatetimeIndex*

Get an array of timestamps

**Parameters**

- **samples** (*Optional*[*np.ndarray*], *optional*) – If provided, timestamps are only returned for the specified samples, by default *None*
- **estimate** (*bool*, *optional*) – Flag for using estimates instead of high precision dates, by default *True*

**Returns**

The return dates. This will be a numpy array of *RSDatetime* objects if *estimate* is *False*, else it will be a pandas *DatetimeIndex*

**Return type**

*Union*[*np.ndarray*, *pd.DatetimeIndex*]

**subsection**(*from\_time*: *str* | *Timestamp* | *datetime*, *to\_time*: *str* | *Timestamp* | *datetime*) → *TimeData*

Get a subsection of the *TimeData*

Returns a new *TimeData* object

**Parameters**

- **from\_time** (*DateTimeLike*) – Start of subsection

- **to\_time** (*DateTimeLike*) – End of subsection

**Returns**

Subsection as new TimeData

**Return type**

*TimeData*

**subsamples**(*from\_sample: int | None = None, to\_sample: int | None = None*) → *TimeData*

Get a subsample range of the TimeData

Returns a new TimeData object

**Parameters**

- **from\_sample** (*Optional[int]*, *optional*) – The sample to go from, by default None. If not provided, this will be the first sample.
- **to\_sample** (*Optional[int]*, *optional*) – The sample to end at, by default None. If not provided, this will be the last sample

**Returns**

The subsamples as a new TimeData object

**Return type**

*TimeData*

**copy**() → *TimeData*

Get a deepcopy of the time data object

**plot**(*fig: Figure | None = None, chans: List[str] | None = None, color: str = 'blue', legend: str = 'TimeData', max\_pts: int | None = 10000*) → *Figure*

Plot time series data

**Parameters**

- **fig** (*Optional[go.Figure]*, *optional*) – A figure if appending the data to an existing plot, by default None
- **chans** (*Optional[List[str]]*, *optional*) – Explicit definition of channels to plot, by default None
- **color** (*str*, *optional*) – The color for the data, by default “blue”
- **legend** (*str*, *optional*) – The legend group to use, by default “TimeData”. This is more useful when plotting multiple TimeData
- **max\_pts** (*Optional[int]*, *optional*) – The maximum number of points for any channel plot before applying lttbc downsampling, by default 10\_000. If set to None, no downsampling will be applied.

**Returns**

Plotly Figure

**Return type**

*go.Figure*

**Raises**

**ValueError** – If a figure is provided and channels have not been explicitly defined

**to\_string**() → *str*

Class details as a string

**pydantic model** `resisticks.time.TimeReader`Bases: `ResisticksProcess`

```
{
  "title": "TimeReader",
  "description": "Base class for resisticks processes\n\nResisticks processes_\n↳perform operations on data (including read and write\noperations). Each time a_\n↳ResisticksProcess child class is run, it should add\na process record to the_\n↳dataset",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "apply_scalings": {
      "title": "Apply Scalings",
      "default": true,
      "type": "boolean"
    },
    "extension": {
      "title": "Extension",
      "type": "string"
    }
  }
}
```

**field** `apply_scalings`: `bool` = `True`**field** `extension`: `str` | `None` = `None`**run**(`dir_path`: `Path`, `metadata_only`: `bool` | `None` = `False`, `metadata`: `TimeMetadata` | `None` = `None`,  
`from_time`: `str` | `Timestamp` | `datetime` | `None` = `None`, `to_time`: `str` | `Timestamp` | `datetime` | `None` = `None`,  
`from_sample`: `int` | `None` = `None`, `to_sample`: `int` | `None` = `None`) → `TimeMetadata` | `TimeData`

Read time series data

**Parameters**

- **`dir_path`** (`Path`) – The directory path
- **`metadata_only`** (`Optional[bool]`, *optional*) – Read only the metadata, by default `False`
- **`metadata`** (`Optional[TimeMetadata]`, *optional*) – Pass the metadata if its already been read in, by default `None`.
- **`from_time`** (`Union[DateTimeLike, None]`, *optional*) – Timestamp to read from, by default `None`
- **`to_time`** (`Union[DateTimeLike, None]`, *optional*) – Timestamp to read to, by default `None`
- **`from_sample`** (`Union[int, None]`, *optional*) – Sample to read from, by default `None`
- **`to_sample`** (`Union[int, None]`, *optional*) – Sample to read to, by default `None`

**Returns**A `TimeData` instance

**Return type***TimeData***read\_metadata**(*dir\_path*: *Path*) → *TimeMetadata*

Read time series data metadata

**Parameters****dir\_path** (*Path*) – The directory path of the time series data**Raises****NotImplementedError** – To be implemented in child classes**read\_data**(*dir\_path*: *Path*, *metadata*: *TimeMetadata*, *read\_from*: *int*, *read\_to*: *int*) → *TimeData*

Read raw data with minimal scalings applied

**Parameters**

- **dir\_path** (*path*) – The directory path to read from
- **metadata** (*TimeMetadata*) – Time series data metadata
- **read\_from** (*int*) – Sample to read data from
- **read\_to** (*int*) – Sample to read data to

**Raises****NotImplementedError** – To be implemented in child TimeReader classes**scale\_data**(*time\_data*: *TimeData*) → *TimeData*

Scale data to physically meaningful units.

For magnetotelluric data, this is assumed to be mV/km for electric channels, mV for magnetic channels (or nT for certain sensors)

The base class assumes the data is already in the correct units and requires no scaling.

**Parameters****time\_data** (*TimeData*) – TimeData read in from file**Returns**

TimeData scaled to give physically meaningful units

**Return type***TimeData***pydantic model** `resistics.time.TimeReaderJSON`Bases: *TimeReader*

Base class for TimeReaders that use a resistics JSON header

```
{
  "title": "TimeReaderJSON",
  "description": "Base class for TimeReaders that use a resistics JSON header",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "apply_scalings": {
      "title": "Apply Scalings",
```

(continues on next page)

(continued from previous page)

```

        "default": true,
        "type": "boolean"
    },
    "extension": {
        "title": "Extension",
        "type": "string"
    }
}

```

**read\_metadata**(*dir\_path: Path*) → *TimeMetadata*

Read the time series data metadata and return

**Parameters**

**dir\_path** (*Path*) – Path to time series data directory

**Returns**

Metadata for time series data

**Return type**

*TimeMetadata*

**Raises**

- **MetadataReadError** – If the headers cannot be parsed
- **TimeDataReadError** – If the data files do not match the expected extension

**pydantic model** `resistics.time.TimeReaderAscii`

Bases: *TimeReaderJSON*

Class for reading Ascii data

Ascii data expected to be a single file with all the data. The delimiter can be set using the delimiter class attribute as can the number of header lines with the n\_header attribute.

```

{
  "title": "TimeReaderAscii",
  "description": "Class for reading Ascii data\n\nAscii data expected to be a_\n↪single file with all the data. The delimiter can\nbe set using the delimiter_\n↪class attribute as can the number of header\nlines with the n_header attribute.",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "apply_scalings": {
      "title": "Apply Scalings",
      "default": true,
      "type": "boolean"
    },
    "extension": {
      "title": "Extension",
      "default": ".txt",
      "type": "string"
    }
  }
}

```

(continues on next page)



(continued from previous page)

```

    },
    "delimiter": {
        "title": "Delimiter",
        "type": "string"
    },
    "n_header": {
        "title": "N Header",
        "default": 0,
        "type": "integer"
    }
}

```

field extension: `str = '.txt'`

field delimiter: `str | None = None`

field n\_header: `int = 0`

`read_data(dir_path: Path, metadata: TimeMetadata, read_from: int, read_to: int) → TimeData`

Read data from Ascii files

#### Parameters

- `dir_path` (*path*) – The directory path to read from
- `metadata` (*TimeMetadata*) – Time series data metadata
- `read_from` (*int*) – Sample to read data from
- `read_to` (*int*) – Sample to read data to

#### Returns

*TimeData*

#### Return type

*TimeData*

#### Raises

**ValueError** – If metadata is None

**pydantic model** `resisticks.time.TimeReaderNumpy`

Bases: *TimeReaderJSON*

Class for reading Numpy data

This is expected to be a single data file for all channels. The ordering is assumed to be the same as the channels definition in the metadata.

```

{
    "title": "TimeReaderNumpy",
    "description": "Class for reading Numpy data\n\nThis is expected to be a single_\n↪data file for all channels. The ordering is\nassumed to be the same as the_\n↪channels definition in the metadata.",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",

```

(continues on next page)

(continued from previous page)

```

        "type": "string"
    },
    "apply_scalings": {
        "title": "Apply Scalings",
        "default": true,
        "type": "boolean"
    },
    "extension": {
        "title": "Extension",
        "default": ".npy",
        "type": "string"
    }
}

```

**field extension:** `str = '.npy'`

**read\_data**(*dir\_path*: *Path*, *metadata*: *TimeMetadata*, *read\_from*: *int*, *read\_to*: *int*) → *TimeData*

Read raw data saved in numpy data

#### Parameters

- **dir\_path** (*path*) – The directory path to read from
- **metadata** (*TimeMetadata*) – Time series data metadata
- **read\_from** (*int*) – Sample to read data from
- **read\_to** (*int*) – Sample to read data to

#### Returns

*TimeData*

#### Return type

*TimeData*

#### Raises

**ValueError** – If metadata is None

**pydantic model** `resisticks.time.TimeWriterNumpy`

Bases: *ResisticksWriter*

Write out time data in numpy binary format

Data is written out as a single data file including all channels

```

{
    "title": "TimeWriterNumpy",
    "description": "Write out time data in numpy binary format\n\nData is written,\n→ out as a single data file including all channels",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        },
        "overwrite": {

```

(continues on next page)

(continued from previous page)

```

        "title": "Overwrite",
        "default": true,
        "type": "boolean"
    }
}

```

**run**(*dir\_path*: *Path*, *time\_data*: *TimeData*) → *None*

Write out TimeData

#### Parameters

- **dir\_path** (*Path*) – The directory path to write to
- **time\_data** (*TimeData*) – TimeData to write out

#### Raises

**WriteError** – If unable to write to the directory

**pydantic model** `resistics.time.TimeWriterAscii`

Bases: *ResisticsWriter*

Write out time data in ascii format

```

{
  "title": "TimeWriterAscii",
  "description": "Write out time data in ascii format",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "overwrite": {
      "title": "Overwrite",
      "default": true,
      "type": "boolean"
    }
  }
}

```

**run**(*dir\_path*: *Path*, *time\_data*: *TimeData*) → *None*

Write out TimeData

#### Parameters

- **dir\_path** (*Path*) – The directory path to write to
- **time\_data** (*TimeData*) – TimeData to write out

#### Raises

**WriteError** – If unable to write to the directory

`resistics.time.new_time_data`(*time\_data*: *TimeData*, *metadata*: *TimeMetadata* | *None* = *None*, *data*: *ndarray* | *None* = *None*, *record*: *Record* | *None* = *None*) → *TimeData*

Get a new TimeData

Values are taken from an existing `TimeData` where they are not explicitly specified. This is useful in a process where only some aspects of the `TimeData` have been changed

**Parameters**

- **time\_data** (`TimeData`) – The existing `TimeData`
- **metadata** (`Optional[TimeMetadata]`, `optional`) – A new `TimeMetadata`, by default `None`
- **data** (`Optional[np.ndarray]`, `optional`) – New data, by default `None`
- **record** (`Optional[Record]`, `optional`) – A new record to add, by default `None`

**Returns**

A new `TimeData` instance

**Return type**

*TimeData*

**pydantic model** `resistics.time.TimeProcess`

Bases: *ResisticsProcess*

Parent class for processing time data

```
{
  "title": "TimeProcess",
  "description": "Parent class for processing time data",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    }
  }
}
```

**run** (`time_data: TimeData`) → *TimeData*

Run the time processor

**pydantic model** `resistics.time.Subsection`

Bases: *TimeProcess*


Get a subsection of time data

**Parameters**

- **from\_time** (*DateTimeLike*) – Time to take subsection from
- **to\_time** (*DateTimeLike*) – Time to take subsection to

## Examples

```
>>> import matplotlib.pyplot as plt
>>> from resistics.testing import time_data_random
>>> from resistics.time import Subsection
>>> time_data = time_data_random(n_samples=1000)
>>> print(time_data.metadata.first_time, time_data.metadata.last_time)
2020-01-01 00:00:00 2020-01-01 00:01:39.9
>>> process = Subsection(from_time="2020-01-01 00:00:25", to_time="2020-01-01_
↪00:00:50.9")
>>> subsection = process.run(time_data)
>>> print(subsection.metadata.first_time, subsection.metadata.last_time)
2020-01-01 00:00:25 2020-01-01 00:00:50.9
>>> subsection.metadata.n_samples
260
>>> plt.plot(time_data.get_timestamps(), time_data["Ex"], label="full")
>>> plt.plot(subsection.get_timestamps(), subsection["Ex"], label="sub")
>>> plt.legend(loc=3)
>>> plt.tight_layout()
>>> plt.show()
```



See also:

### [Subsamples](#)

Getting a section of data using samples rather than dates

```

{
  "title": "Subsection",
  "description": "Get a subsection of time data\n\nParameters\n-----\nfrom_
↪time : DateTimeLike\n    Time to take subsection from\nto_time : DateTimeLike\n ↪
↪Time to take subsection to\n\nExamples\n-----\n.. plot::\n    :width: 90%\n↪
↪>>> import matplotlib.pyplot as plt\n    >>> from resistics.testing import_
↪time_data_random\n    >>> from resistics.time import Subsection\n    >>> time_
↪data = time_data_random(n_samples=1000)\n    >>> print(time_data.metadata.first_
↪time, time_data.metadata.last_time)\n    2020-01-01 00:00:00 2020-01-01 00:01:39.
↪9\n    >>> process = Subsection(from_time="2020-01-01 00:00:25", to_time="2020-
↪01-01 00:00:50.9")\n    >>> subsection = process.run(time_data)\n    >>>_
↪print(subsection.metadata.first_time, subsection.metadata.last_time)\n    2020-01-
↪01 00:00:25 2020-01-01 00:00:50.9\n    >>> subsection.metadata.n_samples\n    260\
↪n    >>> plt.plot(time_data.get_timestamps(), time_data["Ex"], label="full")
↪# doctest: +SKIP\n    >>> plt.plot(subsection.get_timestamps(), subsection["Ex\
↪"], label="sub") # doctest: +SKIP\n    >>> plt.legend(loc=3) # doctest: +SKIP\n_
↪>>> plt.tight_layout() # doctest: +SKIP\n    >>> plt.show() # doctest: +SKIP\n\
↪See Also\n-----\nSubsamples : Getting a section of data using samples rather_
↪than dates",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "from_time": {
      "title": "From Time",
      "anyOf": [
        {
          "type": "string"
        },
        {
          "type": "string",
          "format": "date-time"
        },
        {
          "type": "string",
          "format": "date-time"
        }
      ]
    },
    "to_time": {
      "title": "To Time",
      "anyOf": [
        {
          "type": "string"
        },
        {
          "type": "string",
          "format": "date-time"
        },
        {

```

(continues on next page)

(continued from previous page)

```

        "type": "string",
        "format": "date-time"
    }
]
},
"required": [
    "from_time",
    "to_time"
]
}

```

**field from\_time:** `str` | `Timestamp` | `datetime` [Required]

**field to\_time:** `str` | `Timestamp` | `datetime` [Required]

**run**(*time\_data*: `TimeData`) → `TimeData`

Take a subsection from TimeData

#### Parameters

**time\_data** (`TimeData`) – TimeData to take subsection from

#### Returns

Subsection TimeData

#### Return type

`TimeData`

**pydantic model** `resistics.time.Subsamples`

Bases: `TimeProcess`

Get a subsamples of time data, an alternative to getting a subsection by times

#### Parameters

- **from\_sample** (`int`) – Sample to begin from
- **to\_time** (`DateTimeLike`) – Sample to end at

### Examples

Taking subsample using positive sample numbers. Sample 0 is the first sample and sample -1 is the last sample.

```


>>> import matplotlib.pyplot as plt
>>> from resistics.testing import time_data_random
>>> from resistics.time import Subsamples
>>> time_data = time_data_random(n_samples=300)
>>> print(time_data.metadata.first_time, time_data.metadata.last_time)
2020-01-01 00:00:00 2020-01-01 00:00:29.9
>>> process = Subsamples(from_sample=10, to_sample=120)
>>> subsample = process.run(time_data)
>>> print(subsample.metadata.first_time, subsample.metadata.last_time)
2020-01-01 00:00:01 2020-01-01 00:00:12
>>> subsample.metadata.n_samples
111

```

(continues on next page)

(continued from previous page)


```
>>> plt.plot(time_data.get_timestamps(), time_data["Ex"], label="full")
>>> plt.plot(subsample.get_timestamps(), subsample["Ex"], label="sub")
>>> plt.legend(loc=3)
>>> plt.tight_layout()
>>> plt.show()
```



Another option is to use negative sample numbers which counts back from the end of the time data.

```
>>> import matplotlib.pyplot as plt
>>> from resistics.testing import time_data_random
>>> from resistics.time import Subsamples
>>> time_data = time_data_random(n_samples=300)
>>> print(time_data.metadata.first_time, time_data.metadata.last_time)
2020-01-01 00:00:00 2020-01-01 00:00:29.9
>>> process = Subsamples(from_sample=-100, to_sample=-50)
>>> subsample = process.run(time_data)
>>> print(subsample.metadata.first_time, subsample.metadata.last_time)
2020-01-01 00:00:20 2020-01-01 00:00:25
>>> subsample.metadata.n_samples
51
>>> plt.plot(time_data.get_timestamps(), time_data["Ex"], label="full")
>>> plt.plot(subsample.get_timestamps(), subsample["Ex"], label="sub")
>>> plt.legend(loc=3)
>>> plt.tight_layout()
>>> plt.show()
```






If from\_sample is not passed, it will be set to 0. If to\_sample is not passed this will default to the last sample.

```
>>> import matplotlib.pyplot as plt
>>> from resistics.testing import time_data_random
>>> from resistics.time import Subsamples
>>> time_data = time_data_random(n_samples=300)
>>> print(time_data.metadata.first_time, time_data.metadata.last_time)
2020-01-01 00:00:00 2020-01-01 00:00:29.9
>>> process = Subsamples(to_sample=100)
>>> subsample = process.run(time_data)
>>> print(subsample.metadata.first_time, subsample.metadata.last_time)
2020-01-01 00:00:00 2020-01-01 00:00:10
>>> subsample.metadata.n_samples
101
>>> plt.plot(time_data.get_timestamps(), time_data["Ex"], label="full")
>>> plt.plot(subsample.get_timestamps(), subsample["Ex"], label="sub")
>>> plt.legend(loc=3)
>>> plt.tight_layout()
>>> plt.show()
```

See also:

### Subsection

For taking a subsection using dates



```
{
    "title": "Subsamples",
    "description": "Get a subsamples of time data, an alternative to getting a
↳ subsection by\ntimes\n\nParameters\n-----\nfrom_sample : int\n    Sample to
↳ begin from\nto_time : DateTimeLike\n    Sample to end at\n\nExamples\n-----\
↳ nTaking subsample using positive sample numbers. Sample 0 is the first\nsample
↳ and sample -1 is the last sample.\n\n.. plot::\n    :width: 90%\n\n    >>> import
↳ matplotlib.pyplot as plt\n    >>> from resistics.testing import time_data_random\
↳ n    >>> from resistics.time import Subsamples\n    >>> time_data = time_data_
↳ random(n_samples=300)\n    >>> print(time_data.metadata.first_time, time_data.
↳ metadata.last_time)\n    2020-01-01 00:00:00 2020-01-01 00:00:29.9\n    >>>
↳ process = Subsamples(from_sample=10, to_sample=120)\n    >>> subsample = process.
↳ run(time_data)\n    >>> print(subsample.metadata.first_time, subsample.metadata.
↳ last_time)\n    2020-01-01 00:00:01 2020-01-01 00:00:12\n    >>> subsample.
↳ metadata.n_samples\n    111\n    >>> plt.plot(time_data.get_timestamps(), time_
↳ data[\"Ex\"], label=\"full\") # doctest: +SKIP\n    >>> plt.plot(subsample.get_
↳ timestamps(), subsample[\"Ex\"], label=\"sub\") # doctest: +SKIP\n    >>> plt.
↳ legend(loc=3) # doctest: +SKIP\n    >>> plt.tight_layout() # doctest: +SKIP\n    >
↳ >>> plt.show() # doctest: +SKIP\n\nAnother option is to use negative sample
↳ numbers which counts back from the\nend of the time data.\n\n.. plot::\n
↳ :width: 90%\n\n    >>> import matplotlib.pyplot as plt\n    >>> from resistics.
↳ testing import time_data_random\n    >>> from resistics.time import Subsamples\n
↳ >>> time_data = time_data_random(n_samples=300)\n    >>> print(time_data.
↳ metadata.first_time, time_data.metadata.last_time)\n    2020-01-01 00:00:00 2020-
```

(continues on next page)

(continued from previous page)

```

→01-01 00:00:29.9\n    >>> process = Subsamples(from_sample=-100, to_sample=-50)\n
→    >>> subsample = process.run(time_data)\n    >>> print(subsample.metadata.first_
→time, subsample.metadata.last_time)\n    2020-01-01 00:00:20 2020-01-01 00:00:25\
→n    >>> subsample.metadata.n_samples\n    51\n    >>> plt.plot(time_data.get_
→timestamps(), time_data["Ex"], label="full") # doctest: +SKIP\n    >>> plt.
→plot(subsample.get_timestamps(), subsample["Ex"], label="sub") # doctest:
→+SKIP\n    >>> plt.legend(loc=3) # doctest: +SKIP\n    >>> plt.tight_layout() #
→doctest: +SKIP\n    >>> plt.show() # doctest: +SKIP\n\nIf from_sample is not
→passed, it will be set to 0. If to_sample is not\npassed this will default to the
→last sample.\n\n.. plot::\n    :width: 90%\n\n    >>> import matplotlib.pyplot as
→plt\n    >>> from resistics.testing import time_data_random\n    >>> from
→resistics.time import Subsamples\n    >>> time_data = time_data_random(n_
→samples=300)\n    >>> print(time_data.metadata.first_time, time_data.metadata.
→last_time)\n    2020-01-01 00:00:00 2020-01-01 00:00:29.9\n    >>> process =
→Subsamples(to_sample=100)\n    >>> subsample = process.run(time_data)\n    >>>
→print(subsample.metadata.first_time, subsample.metadata.last_time)\n    2020-01-
→01 00:00:00 2020-01-01 00:00:10\n    >>> subsample.metadata.n_samples\n    101\n
→    >>> plt.plot(time_data.get_timestamps(), time_data["Ex"], label="full") #
→doctest: +SKIP\n    >>> plt.plot(subsample.get_timestamps(), subsample["Ex"],
→label="sub") # doctest: +SKIP\n    >>> plt.legend(loc=3) # doctest: +SKIP\n
→>>> plt.tight_layout() # doctest: +SKIP\n    >>> plt.show() # doctest: +SKIP\n\
→nSee Also\n-----\nSubsection : For taking a subsection using dates",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        },
        "from_sample": {
            "title": "From Sample",
            "type": "integer"
        },
        "to_sample": {
            "title": "To Sample",
            "type": "integer"
        }
    }
}

```

field **from\_sample**: `int` | `None` = `None`

field **to\_sample**: `int` | `None` = `None`

**run**(*time\_data*: `TimeData`) → `TimeData`

Take a subsection from `TimeData`

#### Parameters

**time\_data** (`TimeData`) – `TimeData` to take subsection from

#### Returns

Subsection `TimeData`

#### Return type

`TimeData`

**Raises**

- *ProcessRunError* – If from\_sample is not less than to\_sample
- *ProcessRunError* – If from\_sample is out of range
- *ProcessRunError* – If to\_sample is out of range

**pydantic model** `resisticks.time.InterpolateNans`Bases: *TimeProcess*

Interpolate nan values in the data

Preserve the data type of the input time data

**Examples**

```
>>> from resisticks.testing import time_data_with_nans
>>> from resisticks.time import InterpolateNans
>>> time_data = time_data_with_nans()
>>> time_data["Hx"]
array([nan,  2.,  3.,  5.,  1.,  2.,  3.,  4.,  2.,  6.,  7., nan, nan,
        4.,  3.,  2.], dtype=float32)
>>> process = InterpolateNans()
>>> time_data_new = process.run(time_data)
>>> time_data_new["Hx"]
array([2., 2., 3., 5., 1., 2., 3., 4., 2., 6., 7., 6., 5., 4., 3., 2.],
      dtype=float32)
```

```
{
  "title": "InterpolateNans",
  "description": "Interpolate nan values in the data\n\nPreserve the data type of_\n↪the input time data\n\nExamples\n-----\n>>> from resisticks.testing import time_\n↪data_with_nans\n>>> from resisticks.time import InterpolateNans\n>>> time_data =_\n↪time_data_with_nans()\n>>> time_data[\"Hx\"]\n↪\narray([nan,  2.,  3.,  5.,  1.,  2.,\n↪  3.,  4.,  2.,  6.,  7., nan, nan,\n↪  4.,  3.,  2.], dtype=float32)\n>>>_\n↪process = InterpolateNans()\n>>> time_data_new = process.run(time_data)\n>>> time_\n↪data_new[\"Hx\"]\n↪\narray([2., 2., 3., 5., 1., 2., 3., 4., 2., 6., 7., 6., 5., 4.,\n↪ 3., 2.],\n↪      dtype=float32)",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    }
  }
}
```

**run**(time\_data: *TimeData*) → *TimeData*

Interpolate nan values

**Parameters****time\_data** (*TimeData*) – TimeData to remove nan values from**Returns***TimeData* with no nan values

**Return type***TimeData***pydantic model** `resistics.time.RemoveMean`Bases: *TimeProcess*

Remove channel mean value from each channel

Preserve the data type of the input time data

**Examples**

```

>>> import numpy as np
>>> from resistics.testing import time_data_simple
>>> from resistics.time import RemoveMean
>>> time_data = time_data_simple()
>>> process = RemoveMean()
>>> time_data_new = process.run(time_data)
>>> time_data_new["Hx"]
array([-2.5, -1.5, -0.5,  1.5, -2.5, -1.5, -0.5,  0.5, -1.5,  2.5,  3.5,
        2.5,  1.5,  0.5, -0.5, -1.5], dtype=float32)
>>> hx_test = time_data["Hx"] - np.mean(time_data["Hx"])
>>> hx_test
array([-2.5, -1.5, -0.5,  1.5, -2.5, -1.5, -0.5,  0.5, -1.5,  2.5,  3.5,
        2.5,  1.5,  0.5, -0.5, -1.5], dtype=float32)
>>> np.all(hx_test == time_data_new["Hx"])
True

```

```

{
  "title": "RemoveMean",
  "description": "Remove channel mean value from each channel\n\nPreserve the data_
  ↪type of the input time data\n\nExamples\n-----\n>>> import numpy as np\n>>>_
  ↪from resistics.testing import time_data_simple\n>>> from resistics.time import_
  ↪RemoveMean\n>>> time_data = time_data_simple()\n>>> process = RemoveMean()\n>>>_
  ↪time_data_new = process.run(time_data)\n>>> time_data_new["Hx"]\nnarray([-2.5, -
  ↪1.5, -0.5,  1.5, -2.5, -1.5, -0.5,  0.5, -1.5,  2.5,  3.5,\n        2.5,  1.5,  0.
  ↪5, -0.5, -1.5], dtype=float32)\n>>> hx_test = time_data["Hx"] - np.mean(time_
  ↪data["Hx"])\n>>> hx_test\nnarray([-2.5, -1.5, -0.5,  1.5, -2.5, -1.5, -0.5,  0.5,
  ↪-1.5,  2.5,  3.5,\n        2.5,  1.5,  0.5, -0.5, -1.5], dtype=float32)\n>>> np.
  ↪all(hx_test == time_data_new["Hx"])\nTrue",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    }
  }
}

```

**run**(*time\_data*: *TimeData*) → *TimeData*

Remove mean from TimeData

**Parameters****time\_data** (*TimeData*) – TimeData input

**Returns**

TimeData with mean removed

**Return type***TimeData***pydantic model** resisticks.time.AddBases: *TimeProcess*

Add values to channels

Add can be used to add a constant value to all channels or values for specific channels can be provided.

Add preserves the data type of the original data

**Parameters****add** (*Union[float, Dict[str, float]]*) – Either a scalar to add to all channels or dictionary with values to add to each channel**Examples**

Using a constant value for all channels passed as a scalar

```
>>> from resisticks.testing import time_data_ones
>>> from resisticks.time import Add
>>> time_data = time_data_ones()
>>> process = Add(add=5)
>>> time_data_new = process.run(time_data)
>>> time_data_new["Ex"] - time_data["Ex"]
array([5., 5., 5., 5., 5., 5., 5., 5., 5., 5.], dtype=float32)
>>> time_data_new["Ey"] - time_data["Ey"]
array([5., 5., 5., 5., 5., 5., 5., 5., 5., 5.], dtype=float32)
```

Variable values for the channels provided as a dictionary

```
>>> time_data = time_data_ones()
>>> process = Add(add={"Ex": 3, "Hy": -7})
>>> time_data_new = process.run(time_data)
>>> time_data_new["Ex"] - time_data["Ex"]
array([3., 3., 3., 3., 3., 3., 3., 3., 3., 3.], dtype=float32)
>>> time_data_new["Hy"] - time_data["Hy"]
array([-7., -7., -7., -7., -7., -7., -7., -7., -7., -7.], dtype=float32)
>>> time_data_new["Ey"] - time_data["Ey"]
array([0., 0., 0., 0., 0., 0., 0., 0., 0., 0.], dtype=float32)
```

```
{
  "title": "Add",
  "description": "Add values to channels\n\nAdd can be used to add a constant_\n\value to all channels or values for\nspecific channels can be provided.\n\nAdd_\n\preserves the data type of the original data\n\nParameters\n-----\n\nadd :_\n\Union[float, Dict[str, float]]\n  Either a scalar to add to all channels or_\n\dictionary with values to\n  add to each channel\n\nExamples\n-----\n\nUsing a_\n\constant value for all channels passed as a scalar\n\n>>> from resisticks.testing_\n\import time_data_ones\n>>> from resisticks.time import Add\n>>> time_data = time_\n\data_ones()\n>>> process = Add(add=5)\n>>> time_data_new = process.run(time_data)\n\n(continues on next page)
```

(continued from previous page)

```

↪n>>> time_data_new["Ex"] - time_data["Ex"]\narray([5., 5., 5., 5., 5., 5., 5.,
↪ 5., 5., 5.], dtype=float32)\n>>> time_data_new["Ey"] - time_data["Ey"]\
↪narray([5., 5., 5., 5., 5., 5., 5., 5., 5., 5.], dtype=float32)\n\nVariable_
↪values for the channels provided as a dictionary\n\n>>> time_data = time_data_
↪ones()\n>>> process = Add(add={"Ex": 3, "Hy": -7})\n>>> time_data_new =
↪process.run(time_data)\n>>> time_data_new["Ex"] - time_data["Ex"]\narray([3.,
↪ 3., 3., 3., 3., 3., 3., 3., 3.], dtype=float32)\n>>> time_data_new["Hy"] -
↪time_data["Hy"]\narray([-7., -7., -7., -7., -7., -7., -7., -7., -7.],
↪dtype=float32)\n>>> time_data_new["Ey"] - time_data["Ey"]\narray([0., 0., 0.,
↪ 0., 0., 0., 0., 0.], dtype=float32)",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        },
        "add": {
            "title": "Add",
            "anyOf": [
                {
                    "type": "number"
                },
                {
                    "type": "object",
                    "additionalProperties": {
                        "type": "number"
                    }
                }
            ]
        }
    },
    "required": [
        "add"
    ]
}

```

field add: `float | Dict[str, float]` [Required]

**run**(time\_data: *TimeData*) → *TimeData*

Add values to the data

#### Parameters

**time\_data** (*TimeData*) – The input *TimeData*

#### Returns

*TimeData* with values added

#### Return type

*TimeData*

**pydantic model** `resistics.time.Multiply`

Bases: *TimeProcess*

Multiply channels by values

Multiply can be used to add a constant value to all channels or values for specific channels can be provided.

Multiply preserves the original type of the time data

#### Parameters

**multiplier** (`Union[Dict[str, float], float]`) – Either a float to multiply all channels with the same value or a dictionary to specify different values for each channel

#### Examples

Using a constant value for all channels passed as a scalar

```
>>> from resistics.testing import time_data_ones
>>> from resistics.time import Multiply
>>> time_data = time_data_ones()
>>> process = Multiply(multiplier=5)
>>> time_data_new = process.run(time_data)
>>> time_data_new["Ex"]/time_data["Ex"]
array([5., 5., 5., 5., 5., 5., 5., 5., 5., 5.], dtype=float32)
>>> time_data_new["Ey"]/time_data["Ey"]
array([5., 5., 5., 5., 5., 5., 5., 5., 5., 5.], dtype=float32)
```

Variable values for the channels provided as a dictionary

```
>>> time_data = time_data_ones()
>>> process = Multiply(multiplier={"Ex": 3, "Hy": -7})
>>> time_data_new = process.run(time_data)
>>> time_data_new["Ex"]/time_data["Ex"]
array([3., 3., 3., 3., 3., 3., 3., 3., 3., 3.], dtype=float32)
>>> time_data_new["Hy"]/time_data["Hy"]
array([-7., -7., -7., -7., -7., -7., -7., -7., -7., -7.], dtype=float32)
>>> time_data_new["Ey"]/time_data["Ey"]
array([1., 1., 1., 1., 1., 1., 1., 1., 1., 1.], dtype=float32)
```

```
{
  "title": "Multiply",
  "description": "Multiply channels by values\n\nMultiply can be used to add a
  ↳ constant value to all channels or values for\nspecific channels can be provided.\n
  ↳ \n\nMultiply preserves the original type of the time data\n\nParameters\n-----\n
  ↳ multiplier : Union[Dict[str, float], float]\n    Either a float to multiply all
  ↳ channels with the same value or a\n    dictionary to specify different values for
  ↳ each channel\n\nExamples\n-----\n\nUsing a constant value for all channels
  ↳ passed as a scalar\n\n>>> from resistics.testing import time_data_ones\n>>> from
  ↳ resistics.time import Multiply\n>>> time_data = time_data_ones()\n>>> process =
  ↳ Multiply(multiplier=5)\n>>> time_data_new = process.run(time_data)\n>>> time_data_
  ↳ new["Ex"]/time_data["Ex"]\narray([5., 5., 5., 5., 5., 5., 5., 5., 5., 5.],
  ↳ dtype=float32)\n>>> time_data_new["Ey"]/time_data["Ey"]\narray([5., 5., 5., 5.
  ↳ , 5., 5., 5., 5., 5., 5.], dtype=float32)\n\nVariable values for the channels
  ↳ provided as a dictionary\n\n>>> time_data = time_data_ones()\n>>> process =
  ↳ Multiply(multiplier={"Ex": 3, "Hy": -7})\n>>> time_data_new = process.
  ↳ run(time_data)\n>>> time_data_new["Ex"]/time_data["Ex"]\narray([3., 3., 3., 3.
  ↳ , 3., 3., 3., 3., 3., 3.], dtype=float32)\n>>> time_data_new["Hy"]/time_data[
  ↳ "Hy"]\narray([-7., -7., -7., -7., -7., -7., -7., -7., -7., -7.], dtype=float32)\n
  ↳ \n>>> time_data_new["Ey"]/time_data["Ey"]\narray([1., 1., 1., 1., 1., 1., 1.,
  ↳ 1., 1., 1.], dtype=float32)",
```

(continues on next page)



(continued from previous page)

```

    "type": "object",
    "properties": {
      "name": {
        "title": "Name",
        "type": "string"
      },
      "multiplier": {
        "title": "Multiplier",
        "anyOf": [
          {
            "type": "number"
          },
          {
            "type": "object",
            "additionalProperties": {
              "type": "number"
            }
          }
        ]
      }
    },
    "required": [
      "multiplier"
    ]
  }
}

```

**field multiplier:** `float | Dict[str, float]` [Required]

**run**(*time\_data*: *TimeData*) → *TimeData*

Multiply the channels

**Parameters**

**time\_data** (*TimeData*) – Input TimeData

**Returns**

TimeData with channels multiplied by the specified numbers

**Return type**

*TimeData*

**pydantic model** `resistics.time.LowPass`

Bases: *TimeProcess*

Apply low pass filter


**Parameters**

- **cutoff** (*float*) – The cutoff for the low pass
- **order** (*int*, *optional*) – Order of the filter, by default 10

## Examples

Low pass to remove 20 Hz from a time series sampled at 50 Hz

```
import matplotlib.pyplot as plt
from resistics.testing import time_data_periodic
from resistics.time import LowPass
time_data = time_data_periodic([10, 50], fs=250, n_samples=100)
process = LowPass(cutoff=30)
filtered = process.run(time_data)
plt.plot(time_data.get_timestamps(), time_data["chan1"], label="original")
plt.plot(filtered.get_timestamps(), filtered["chan1"], label="filtered")
plt.legend(loc=3)
plt.tight_layout()
plt.plot()
```



```
{
  "title": "LowPass",
  "description": "Apply low pass filter\n\nParameters\n-----\ncutoff : float\n  The cutoff for the low pass\norder : int, optional\n  Order of the filter,\n  by default 10\n\nExamples\n-----\nLow pass to remove 20 Hz from a time series_\nsampled at 50 Hz\n.. plot::\n  :width: 90%\n\n  import matplotlib.pyplot as_\n  plt\n  from resistics.testing import time_data_periodic\n  from resistics.\n  time import LowPass\n  time_data = time_data_periodic([10, 50], fs=250, n_\n  samples=100)\n  process = LowPass(cutoff=30)\n  filtered = process.run(time_
```

(continues on next page)

(continued from previous page)

```

→data)\n    plt.plot(time_data.get_timestamps(), time_data["chan1"], label=\
→"original")\n    plt.plot(filtered.get_timestamps(), filtered["chan1"], label=\
→"filtered")\n    plt.legend(loc=3)\n    plt.tight_layout()\n    plt.plot()",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        },
        "cutoff": {
            "title": "Cutoff",
            "type": "number"
        },
        "order": {
            "title": "Order",
            "default": 10,
            "type": "integer"
        }
    },
    "required": [
        "cutoff"
    ]
}

```

field cutoff: **float** [Required]

field order: **int** = 10

**run**(time\_data: *TimeData*) → *TimeData*

Apply the low pass filter

#### Parameters

**time\_data** (*TimeData*) – The input *TimeData*

#### Returns

The low pass filtered *TimeData*

#### Return type

*TimeData*

#### Raises

***ProcessRunError*** – If cutoff > nyquist

**pydantic model** `resistics.time.HighPass`

Bases: *TimeProcess*

High pass filter time data


#### Parameters

- **cutoff** (*float*) – Cutoff for the high pass filter
- **order** (*int*, *optional*) – Order of the filter, by default 10

## Examples

High pass to remove 3 Hz from signal sampled at 50 Hz

```
import matplotlib.pyplot as plt
from resistics.testing import time_data_periodic
from resistics.time import HighPass
time_data = time_data_periodic([10, 50], fs=250, n_samples=100)
process = HighPass(cutoff=30)
filtered = process.run(time_data)
plt.plot(time_data.get_timestamps(), time_data["chan1"], label="original")
plt.plot(filtered.get_timestamps(), filtered["chan1"], label="filtered")
plt.legend(loc=3)
plt.tight_layout()
plt.plot()
```



```
{
  "title": "HighPass",
  "description": "High pass filter time data\n\nParameters\n-----\ncutoff : float\n    Cutoff for the high pass filter\norder : int, optional\n    Order of the filter, by default 10\nExamples\n-----\nHigh pass to remove 3 Hz from signal sampled at 50 Hz\n\n.. plot::\n    :width: 90%\n\n    import matplotlib.pyplot as plt\n    from resistics.testing import time_data_periodic\n    from resistics.time import HighPass\n    time_data = time_data_periodic([10, 50], fs=250, n_samples=100)\n    process = HighPass(cutoff=30)\n    filtered = process.
```

(continues on next page)

(continued from previous page)

```

→run(time_data)\n    plt.plot(time_data.get_timestamps(), time_data["chan1"],\n
→label="original")\n    plt.plot(filtered.get_timestamps(), filtered["chan1"],\n
→label="filtered")\n    plt.legend(loc=3)\n    plt.tight_layout()\n    plt.plot()
→",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        },
        "cutoff": {
            "title": "Cutoff",
            "type": "number"
        },
        "order": {
            "title": "Order",
            "default": 10,
            "type": "integer"
        }
    },
    "required": [
        "cutoff"
    ]
}

```

field cutoff: float [Required]

field order: int = 10

**run**(time\_data: TimeData) → TimeData

Apply the high pass filter

#### Parameters

**time\_data** (TimeData) – The input TimeData

#### Returns

The high pass filtered TimeData

#### Return type

TimeData

#### Raises

**ProcessRunError** – If cutoff > nyquist

**pydantic model** resistics.time.BandPass

Bases: TimeProcess

Band pass filter time data


#### Parameters

- **cutoff\_low** (float) – The low cutoff for the band pass filter
- **cutoff\_high** (float) – The high cutoff for the band pass filter
- **order** (int, optional) – The order of the filter, by default 10

## Examples

Band pass to isolate 12 Hz signal

```
import matplotlib.pyplot as plt
from resistics.testing import time_data_periodic
from resistics.time import BandPass
time_data = time_data_periodic([10, 50], fs=250, n_samples=100)
process = BandPass(cutoff_low=45, cutoff_high=55)
filtered = process.run(time_data)
plt.plot(time_data.get_timestamps(), time_data["chan1"], label="original")
plt.plot(filtered.get_timestamps(), filtered["chan1"], label="filtered")
plt.legend(loc=3)
plt.tight_layout()
plt.plot()
```



```
{
  "title": "BandPass",
  "description": "Band pass filter time data\n\nParameters\n-----\ncutoff_low : float\n    The low cutoff for the band pass filter\ncutoff_high : float\n    The high cutoff for the band pass filter\norder : int, optional\n    The order of the filter, by default 10\n\nExamples\n-----\nBand pass to isolate 12 Hz signal\n\n.. plot::\n    :width: 90%\n\n    import matplotlib.pyplot as plt\n    from resistics.testing import time_data_periodic\n    from resistics.time import BandPass\n    time_data = time_data_periodic([10, 50], fs=250, n_samples=100)
```

(continues on next page)

(continued from previous page)

```

→ process = BandPass(cutoff_low=45, cutoff_high=55)\n    filtered = process.
→ run(time_data)\n    plt.plot(time_data.get_timestamps(), time_data["chan1"],\n
→ label="original")\n    plt.plot(filtered.get_timestamps(), filtered["chan1"],\n
→ label="filtered")\n    plt.legend(loc=3)\n    plt.tight_layout()\n    plt.plot()
→ ",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        },
        "cutoff_low": {
            "title": "Cutoff Low",
            "type": "number"
        },
        "cutoff_high": {
            "title": "Cutoff High",
            "type": "number"
        },
        "order": {
            "title": "Order",
            "default": 10,
            "type": "integer"
        }
    },
    "required": [
        "cutoff_low",
        "cutoff_high"
    ]
}

```

field cutoff\_low: float [Required]

field cutoff\_high: float [Required]

field order: int = 10

**run**(time\_data: TimeData) → TimeData

Apply the band pass filter

#### Parameters

**time\_data** (TimeData) – The input TimeData

#### Returns

The band pass filtered TimeData

#### Return type

TimeData

#### Raises

- **ProcessRunError** – If cutoff\_low > cutoff\_high
- **ProcessRunError** – If cutoff\_high > nyquist

**pydantic model** `resistics.time.Notch`Bases: `TimeProcess`

Notch filter time data


**Parameters**

- **notch** (`float`) – The frequency to notch
- **band** (`Optional[float]`, `optional`) – The bandwidth of the filter, by default `None`
- **order** (`int`, `optional`) – The order of the filter, by default `10`

**Examples**

Notch to remove a 50 Hz signal, for example powerline noise

```
import matplotlib.pyplot as plt
from resistics.testing import time_data_periodic
from resistics.time import Notch
time_data = time_data_periodic([10, 50], fs=250, n_samples=100)
process = Notch(notch=50, band=10)
filtered = process.run(time_data)
plt.plot(time_data.get_timestamps(), time_data["chan1"], label="original")
plt.plot(filtered.get_timestamps(), filtered["chan1"], label="filtered")
plt.legend(loc=3)
plt.tight_layout()
plt.plot()
```





```

{
  "title": "Notch",
  "description": "Notch filter time data\n\nParameters\n-----\nnotch : float\n↪n    The frequency to notch\nband : Optional[float], optional\n↪n    The bandwidth_
↪of the filter, by default None\norder : int, optional\n↪n    The order of the_
↪filter, by default 10\n\nExamples\n-----\nNotch to remove a 50 Hz signal, for_
↪example powerline noise\n\n.. plot::\n    :width: 90%\n\n    import matplotlib.
↪pyplot as plt\n    from resistics.testing import time_data_periodic\n    from_
↪resistics.time import Notch\n    time_data = time_data_periodic([10, 50], fs=250,_
↪n_samples=100)\n    process = Notch(notch=50, band=10)\n    filtered = process.
↪run(time_data)\n    plt.plot(time_data.get_timestamps(), time_data[\"chan1\"],_
↪label= \"original\")\n    plt.plot(filtered.get_timestamps(), filtered[\"chan1\"],_
↪label= \"filtered\")\n    plt.legend(loc=3)\n    plt.tight_layout()\n    plt.plot()
↪",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "notch": {
      "title": "Notch",
      "type": "number"
    },
    "band": {
      "title": "Band",
      "type": "number"
    },
    "order": {
      "title": "Order",
      "default": 10,
      "type": "integer"
    }
  },
  "required": [
    "notch"
  ]
}

```

**field notch:** `float` [Required]

**field band:** `float` | `None` = `None`

**field order:** `int` = `10`

**run**(*time\_data*: `TimeData`) → `TimeData`

Apply notch filter to `TimeData`

#### Parameters

**time\_data** (`TimeData`) – Input `TimeData`

#### Returns

Filtered `TimeData`

#### Return type

`TimeData`

**Raises***ProcessRunError* – If notch frequency > nyquist**pydantic model** `resistics.time.Resample`Bases: *TimeProcess*

Resample TimeData

Note that resampling is done on `np.float64` data and this will lead to a temporary increase in memory usage. Once resampling is complete, the data is converted back to its original data type.


**Parameters****new\_fs** (*int*) – The new sampling frequency**Examples**

Resample the data from 250 Hz to 50 Hz

```
>>> import matplotlib.pyplot as plt
>>> from resistics.testing import time_data_periodic
>>> from resistics.time import Resample
>>> time_data = time_data_periodic([10, 50], fs=250, n_samples=200)
>>> print(time_data.metadata.n_samples, time_data.metadata.first_time, time_data.
↳ metadata.last_time)
200 2020-01-01 00:00:00 2020-01-01 00:00:00.796
>>> process = Resample(new_fs=50)
>>> resampled = process.run(time_data)
>>> print(resampled.metadata.n_samples, resampled.metadata.first_time, resampled.
↳ metadata.last_time)
40 2020-01-01 00:00:00 2020-01-01 00:00:00.78
>>> plt.plot(time_data.get_timestamps(), time_data["chan1"], label="original")
>>> plt.plot(resampled.get_timestamps(), resampled["chan1"], label="resampled")
>>> plt.legend(loc=3)
>>> plt.tight_layout()
>>> plt.show()
```

```
{
  "title": "Resample",
  "description": "Resample TimeData\n\nNote that resampling is done on np.float64_\n
↳ data and this will lead to a\n\ttemporary increase in memory usage. Once resampling_\n
↳ is complete, the data is\n\tconverted back to its original data type.\n\nParameters_\n
↳ n-----\nnew_fs : int\n    The new sampling frequency\n\nExamples\n-----\n
↳ Resample the data from 250 Hz to 50 Hz\n\n.. plot::\n    :width: 90%\n\n    >>>_\n
↳ import matplotlib.pyplot as plt\n    >>> from resistics.testing import time_data_\n
↳ periodic\n    >>> from resistics.time import Resample\n    >>> time_data = time_\n
↳ data_periodic([10, 50], fs=250, n_samples=200)\n    >>> print(time_data.metadata.\n
↳ n_samples, time_data.metadata.first_time, time_data.metadata.last_time)\n    200_\n
↳ 2020-01-01 00:00:00 2020-01-01 00:00:00.796\n    >>> process = Resample(new_\n
↳ fs=50)\n    >>> resampled = process.run(time_data)\n    >>> print(resampled.\n
↳ metadata.n_samples, resampled.metadata.first_time, resampled.metadata.last_time)\n
↳ \n    40 2020-01-01 00:00:00 2020-01-01 00:00:00.78\n    >>> plt.plot(time_data.\n
↳ get_timestamps(), time_data[\"chan1\"], label=\"original\") # doctest: +SKIP\n
↳ >>> plt.plot(resampled.get_timestamps(), resampled[\"chan1\"], label=\"resampled_\n
↳ \") # doctest: +SKIP\n    >>> plt.legend(loc=3) # doctest: +SKIP\n    >>> plt.
```

(continues on next page)



(continued from previous page)

```

→tight_layout() # doctest: +SKIP\n    >>> plt.show() # doctest: +SKIP",
    "type": "object",
    "properties": {
      "name": {
        "title": "Name",
        "type": "string"
      },
      "new_fs": {
        "title": "New Fs",
        "type": "number"
      }
    },
    "required": [
      "new_fs"
    ]
  }

```

**field new\_fs:** `float` [Required]

**run**(*time\_data*: `TimeData`) → `TimeData`

Resample TimeData

Resampling uses the polyphase method which does not assume periodicity Calculate the upsample rate and

the downsampling rate and using polyphase filtering, the final sample rate is:

$$(up/down) * originalsampleRate$$

Therefore, to get a sampling frequency of `resampFreq`, want:

$$(resampFreq/sampleFreq) * sampleFreq$$

Use the fractions library to get up and down as integers which they are required to be.

#### Parameters

**time\_data** (`TimeData`) – Input `TimeData`

#### Returns

Resampled `TimeData`

#### Return type

`TimeData`

**pydantic model** `resistics.time.Decimate`

Bases: `TimeProcess`

Decimate `TimeData`

**Warning:** Data is converted to `np.float64` prior to decimation. This is going to cause a temporary increase in memory usage, but decimating `np.float64` delivers improved results.

The decimated data is converted back to its original data type prior to being returned.

The `max_factor` for a single decimation step is by default set as 3. When using `np.float64` data, it is possible to use a larger decimation factor, up to 13, but this does again have an impact on results.


For more information, see <https://docs.scipy.org/doc/scipy/reference/generated/scipy.signal.decimate.html>

#### Parameters

**factor** (`int`) – The decimation factor

### Examples

```
>>> import matplotlib.pyplot as plt
>>> from resistics.testing import time_data_periodic
>>> from resistics.time import Decimate
>>> time_data = time_data_periodic([10, 50], fs=250, n_samples=200)
>>> print(time_data.metadata.n_samples, time_data.metadata.first_time, time_data.
↳ metadata.last_time)
200 2020-01-01 00:00:00 2020-01-01 00:00:00.796
>>> process = Decimate(factor=5)
>>> decimated = process.run(time_data)
>>> print(decimated.metadata.n_samples, decimated.metadata.first_time, decimated.
↳ metadata.last_time)
40 2020-01-01 00:00:00 2020-01-01 00:00:00.78
>>> plt.plot(time_data.get_timestamps(), time_data["chan1"], label="original")
>>> plt.plot(decimated.get_timestamps(), decimated["chan1"], label="decimated")
>>> plt.legend(loc=3)
>>> plt.tight_layout()
>>> plt.show()
```



```
{
  "title": "Decimate",
  "description": "Decimate TimeData\n\n.. warning::\n\n    Data is converted to np.\n    ↳ float64 prior to decimation. This is going to\n    ↳ cause a temporary increase in\n    ↳ memory usage, but decimating np.float64\n    ↳ delivers improved results.\n    ↳ \n    ↳ The decimated data is converted back to its original data type prior\n    ↳ to\n    ↳ being returned.\n    ↳ \n    ↳ The max_factor for a single decimation step is by default\n    ↳ set as 3.\n    ↳ \n    ↳ When using np.float64 data, it is possible to use a larger\n    ↳ decimation\n    ↳ factor, up to 13, but this does again have an impact on results.\n    ↳ \n    ↳ For more information, see\n    ↳ https://docs.scipy.org/doc/scipy/reference/\n    ↳ generated/scipy.signal.decimate.html\nParameters\n-----\nfactor : int\n    ↳ The decimation factor\nExamples\n-----\n.. plot::\n    ↳ :width: 90%\n    >>> \n    ↳ import matplotlib.pyplot as plt\n    ↳ >>> from resistics.testing import time_data_\n    ↳ periodic\n    ↳ >>> from resistics.time import Decimate\n    ↳ >>> time_data = time_\n    ↳ data_periodic([10, 50], fs=250, n_samples=200)\n    ↳ >>> print(time_data.metadata.\n    ↳ n_samples, time_data.metadata.first_time, time_data.metadata.last_time)\n    ↳ 200_\n    ↳ 2020-01-01 00:00:00 2020-01-01 00:00:00.796\n    ↳ >>> process = Decimate(factor=5)\n    ↳ \n    ↳ >>> decimated = process.run(time_data)\n    ↳ >>> print(decimated.metadata.n_\n    ↳ samples, decimated.metadata.first_time, decimated.metadata.last_time)\n    ↳ 40_\n    ↳ 2020-01-01 00:00:00 2020-01-01 00:00:00.78\n    ↳ >>> plt.plot(time_data.get_\n    ↳ timestamps(), time_data[\"chan1\"], label=\"original\") # doctest: +SKIP\n    ↳ >>>\n    ↳ plt.plot(decimated.get_timestamps(), decimated[\"chan1\"], label=\"decimated\") #_\n    ↳ doctest: +SKIP\n    ↳ >>> plt.legend(loc=3) # doctest: +SKIP\n    ↳ >>> plt.tight_\n    ↳ layout() # doctest: +SKIP\n    ↳ >>> plt.show() # doctest: +SKIP",
}
```

(continues on next page)

(continued from previous page)

```

    "type": "object",
    "properties": {
      "name": {
        "title": "Name",
        "type": "string"
      },
      "factor": {
        "title": "Factor",
        "minimum": 1,
        "type": "integer"
      },
      "max_single_factor": {
        "title": "Max Single Factor",
        "default": 3,
        "minimum": 2,
        "type": "integer"
      }
    },
    "required": [
      "factor"
    ]
  }

```

**field factor:** `ConstrainedIntValue [Required]`

#### Constraints

- `minimum = 1`

**field max\_single\_factor:** `ConstrainedIntValue = 3`

#### Constraints

- `minimum = 2`

**run**(*time\_data*: `TimeData`) → `TimeData`

Decimate `TimeData`

#### Parameters

**time\_data** (`TimeData`) – Input `TimeData`

#### Returns

Decimated `TimeData`

#### Return type

`TimeData`

**pydantic model** `resistics.time.ShiftTimestamps`

Bases: `TimeProcess`

Shift timestamps. This method is usually used when there is an offset on the sampling, so that instead of coinciding with a second or an hour, they are offset from this.

The function interpolates the original data onto the shifted timestamps.


#### Parameters

**shift** (`float`) – The shift in seconds. This must be positive as data is never extrapolated

## Examples

An example shifting timestamps for TimeData with a sample period of 20 seconds ( $fs = 1/20 = 0.05$  Hz) but with an offset of 10 seconds on the timestamps

```
>>> from resistics.testing import time_data_with_offset
>>> from resistics.time import ShiftTimestamps
>>> time_data = time_data_with_offset(offset=10, fs=1/20, n_samples=5)
>>> [x.time().strftime('%H:%M:%S') for x in time_data.get_timestamps()]
['00:00:10', '00:00:30', '00:00:50', '00:01:10', '00:01:30']
>>> process = ShiftTimestamps(shift=10, style="linear")
>>> result = process.run(time_data)
>>> [x.time().strftime('%H:%M:%S') for x in result.get_timestamps()]
['00:00:20', '00:00:40', '00:01:00', '00:01:20']
>>> plt.plot(time_data.get_timestamps(), time_data["chan1"], "bo", label="original")
>>> plt.plot(result.get_timestamps(), result["chan1"], "rd", label="shifted")
>>> plt.legend(loc=4)
>>> plt.grid()
>>> plt.tight_layout()
>>> plt.show()
```



See also:

### [CropTimestamps](#)

Crop timestamps to a specified time unit

```

{
  "title": "ShiftTimestamps",
  "description": "Shift timestamps. This method is usually used when there is an
  ↳ offset on the\ nsampling, so that instead of coinciding with a second or an hour,
  ↳ they are\ noffset from this.\n\nThe function interpolates the original data onto\
  ↳ the shifted timestamps.\n\nParameters\n-----\nshift : float\n    The shift
  ↳ in seconds. This must be positive as data is never\n    extrapolated\n\nExamples\
  ↳ n-----\nAn example shifting timestamps for TimeData with a sample period of 20\
  ↳ nseconds (fs = 1/20 = 0.05 Hz) but with an offset of 10 seconds on the\
  ↳ ntimestamps\n\n.. plot::\n    :width: 90%\n\n    >>> from resistics.testing
  ↳ import time_data_with_offset\n    >>> from resistics.time import ShiftTimestamps\
  ↳ n    >>> time_data = time_data_with_offset(offset=10, fs=1/20, n_samples=5)\n    >
  ↳ >>> [x.time().strftime('%H:%M:%S') for x in time_data.get_timestamps()]\n    [
  ↳ '00:00:10', '00:00:30', '00:00:50', '00:01:10', '00:01:30']\n    >>> process =
  ↳ ShiftTimestamps(shift=10, style="linear")\n    >>> result = process.run(time_
  ↳ data)\n    >>> [x.time().strftime('%H:%M:%S') for x in result.get_timestamps()]\n
  ↳ ['00:00:20', '00:00:40', '00:01:00', '00:01:20']\n    >>> plt.plot(time_data.
  ↳ get_timestamps(), time_data["chan1"], "bo", label="original") # doctest:
  ↳ +SKIP\n    >>> plt.plot(result.get_timestamps(), result["chan1"], "rd",
  ↳ label="shifted") # doctest: +SKIP\n    >>> plt.legend(loc=4) # doctest: +SKIP\n
  ↳ >>> plt.grid() # doctest: +SKIP\n    >>> plt.tight_layout() # doctest: +SKIP\n
  ↳ >>> plt.show() # doctest: +SKIP\n\nSee Also\n-----\nCropTimestamps : Crop
  ↳ timestamps to a specified time unit",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "shift": {
      "title": "Shift",
      "exclusiveMinimum": 0,
      "type": "number"
    },
    "style": {
      "title": "Style",
      "default": "spline",
      "enum": [
        "spline",
        "linear"
      ],
      "type": "string"
    }
  },
  "required": [
    "shift"
  ]
}

```

field shift: PositiveFloat [Required]

#### Constraints

- exclusiveMinimum = 0



field style: `Literal['spline', 'linear'] = 'spline'`

**run**(time\_data: *TimeData*) → *TimeData*

Shift timestamps and interpolate data

**Parameters**

**time\_data** (*TimeData*) – Input TimeData

**Returns**

TimeData with shifted timestamps and data interpolated

**Return type**

*TimeData*

**Raises**

***ProcessRunError*** – If the shift is greater than the sampling frequency. This method is not supposed to be used for resampling, but simply for removing an offset from timestamps

**pydantic model** `resisticks.time.CropTimestamps`

Bases: *TimeProcess*

Crop timestamps to make them begin at the next second or minute or hour and end one sample before the nearest second, minute or hour.

Input timestamps should be sampled coincidentally with the time unit. This can be achieved with *ShiftTimestamps*.

Cropping works as follows:

- First times are cropped to the next time unit or maintained if they are a whole time unit already
- Last times are cropped to the previous time unit or maintained if they are a whole time unit already

**Parameters**


**time\_unit** (*str*) – The time unit to crop to given in pandas style time freq

## Examples

An example cropping timestamps to the nearest minute.

```
>>> from resisticks.testing import time_data_random
>>> from resisticks.time import CropTimestamps
>>> time_data = time_data_random(n_samples=1000)
>>> print(time_data.metadata.first_time, time_data.metadata.last_time)
2020-01-01 00:00:00 2020-01-01 00:01:39.9
>>> process = CropTimestamps(time_unit="T")
>>> result = process.run(time_data)
>>> print(result.metadata.first_time, result.metadata.last_time)
2020-01-01 00:00:00 2020-01-01 00:01:00
>>> plt.plot(time_data.get_timestamps(), time_data["Ex"], "bo-", label="original")
>>> plt.plot(result.get_timestamps(), result["Ex"], "rd-", label="cropped")
>>> plt.legend(loc=4)
>>> plt.grid()
>>> plt.tight_layout()
>>> plt.show()
```

See also:



### ShiftTimestamps

Calculate data values on shifted timestamps

```
{
  "title": "CropTimestamps",
  "description": "Crop timestamps to make them begin at the next second or minute,
  or hour and end one sample before the nearest second, minute or hour.\n\nInput
  timestamps should be sampled coincidentally with the time unit. This can be
  achieved with :class:`~ShiftTimestamps`.\n\nCropping works as follows:\n\n- First
  times are cropped to the next time unit or maintained if they are a whole time
  unit already\n- Last times are cropped to the previous time unit or maintained if
  they are a whole time unit already\n\nParameters\n-----\ntime_unit : str
  The time unit to crop to given in pandas style time freq\n\nExamples\n-----
  \n\nAn example cropping timestamps to the nearest minute.\n\n.. plot::
  width: 90%\n\n    >>> from resistics.testing import time_data_random\n    >>>
  from resistics.time import CropTimestamps\n    >>> time_data = time_data_random(n
  samples=10000)\n    >>> print(time_data.metadata.first_time, time_data.metadata.
  last_time)\n    2020-01-01 00:00:00 2020-01-01 00:01:39.9\n    >>> process =
  CropTimestamps(time_unit="T")\n    >>> result = process.run(time_data)\n    >>>
  print(result.metadata.first_time, result.metadata.last_time)\n    2020-01-01
  00:00:00 2020-01-01 00:01:00\n    >>> plt.plot(time_data.get_timestamps(), time_
  data[\"Ex\"], \"bo-\", label=\"original\") # doctest: +SKIP\n    >>> plt.
  plot(result.get_timestamps(), result[\"Ex\"], \"rd-\", label=\"cropped\") #
  doctest: +SKIP\n    >>> plt.legend(loc=4) # doctest: +SKIP\n    >>> plt.grid() #
  doctest: +SKIP\n    >>> plt.tight_layout() # doctest: +SKIP\n    >>> plt.show() #
```

(continues on next page)

(continued from previous page)

```

↪doctest: +SKIP\n\nSee Also\n-----\nShiftTimestamps : Calculate data values on_
↪shifted timestamps",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        },
        "time_unit": {
            "title": "Time Unit",
            "default": "s",
            "type": "string"
        }
    }
}

```

**field time\_unit:** `str = 's'`

**run**(*time\_data*: `TimeData`) → `TimeData`

Crop timestamps to the next time unit

**Parameters**

**time\_data** (`TimeData`) – The `TimeData` to crop

**Returns**

The cropped `TimeData`

**Return type**

`TimeData`

**resistics.time.serialize\_custom\_fnc**(*fnc*: `Callable`) → `str`

Serialize the custom functions

This is not really reversible and recovering parameters from `ApplyFunction` is not supported

**Parameters**

**fnc** (`Callable`) – Function to serialize

**Returns**

serialized output

**Return type**

`str`

**pydantic model** **resistics.time.ApplyFunction**

Bases: `TimeProcess`

Apply a generic functions to the time data

To be used with single argument functions that take the channel data array and a perform transformation on the data.

**Parameters**

**fncs** (`Dict[str, Callable]`) – Dictionary of channel to callable

## Examples

```
>>> import numpy as np
>>> from resistics.testing import time_data_ones
>>> from resistics.time import ApplyFunction
>>> time_data = time_data_ones()
>>> process = ApplyFunction(fncs={"Ex": lambda x: 2*x, "Hy": lambda x: 3*x*x - 5*x_
↪+ 1})
>>> result = process.run(time_data)
>>> time_data["Ex"]
array([1., 1., 1., 1., 1., 1., 1., 1., 1.], dtype=float32)
>>> result["Ex"]
array([2., 2., 2., 2., 2., 2., 2., 2., 2.])
>>> time_data["Hy"]
array([1., 1., 1., 1., 1., 1., 1., 1., 1.], dtype=float32)
>>> result["Hy"]
array([-1., -1., -1., -1., -1., -1., -1., -1., -1.])
```

```
{
  "title": "ApplyFunction",
  "description": "Apply a generic functions to the time data\n\nTo be used with_
↪single argument functions that take the channel data array\nand a perform_
↪transformation on the data.\n\nParameters\n-----\nfncs : Dict[str, Callable]\n↪n Dictionary of channel to callable\n\nExamples\n-----\n>>> import numpy as_
↪np\n>>> from resistics.testing import time_data_ones\n>>> from resistics.time_
↪import ApplyFunction\n>>> time_data = time_data_ones()\n>>> process =_
↪ApplyFunction(fncs={"Ex": lambda x: 2*x, "Hy": lambda x: 3*x*x - 5*x + 1})\n>>
↪> result = process.run(time_data)\n>>> time_data["Ex"]\narray([1., 1., 1., 1.,_
↪1., 1., 1., 1., 1.], dtype=float32)\n>>> result["Ex"]\narray([2., 2., 2., 2._
↪2., 2., 2., 2., 2.])\n>>> time_data["Hy"]\narray([1., 1., 1., 1., 1., 1.,_
↪1., 1., 1.], dtype=float32)\n>>> result["Hy"]\narray([-1., -1., -1., -1., -_
↪1., -1., -1., -1., -1.])",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    }
  }
}
```

**field fncs:** `Dict[str, Callable]` [Required]

**run**(*time\_data*: `TimeData`) → `TimeData`

Apply functions to channel data

### Parameters

**time\_data** (`TimeData`) – Input `TimeData`

### Returns

Transformed `TimeData`

### Return type

`TimeData`

## resisticks.transfunc module

Module defining transfer functions

**pydantic model** resisticks.transfunc.Component

Bases: *Metadata*

Data class for a single component in a Transfer function

### Example

```
>>> from resisticks.transfunc import Component
>>> component = Component(real=[1, 2, 3, 4, 5], imag=[-5, -4, -3, -2, -1])
>>> component.get_value(0)
(1-5j)
>>> component.to_numpy()
array([1.-5.j, 2.-4.j, 3.-3.j, 4.-2.j, 5.-1.j])
```

```
{
  "title": "Component",
  "description": "Data class for a single component in a Transfer function\n\
  ↳Example\n-----\n>>> from resisticks.transfunc import Component\n>>> component = \
  ↳Component(real=[1, 2, 3, 4, 5], imag=[-5, -4, -3, -2, -1])\n>>> component.get_ \
  ↳value(0)\n(1-5j)\n>>> component.to_numpy()\nnarray([1.-5.j, 2.-4.j, 3.-3.j, 4.-2.j, \
  ↳5.-1.j])",
  "type": "object",
  "properties": {
    "real": {
      "title": "Real",
      "type": "array",
      "items": {
        "type": "number"
      }
    },
    "imag": {
      "title": "Imag",
      "type": "array",
      "items": {
        "type": "number"
      }
    }
  },
  "required": [
    "real",
    "imag"
  ]
}
```

**field real:** `List[float]` [Required]

The real part of the component

**field imag:** `List[float]` [Required]

The complex part of the component

**get\_value**(*eval\_idx: int*) → complex

Get the value for an evaluation frequency

**to\_numpy**() → ndarray

Get the component as a numpy complex array

resistics.transfunc.**get\_component\_key**(*out\_chan: str, in\_chan: str*) → str

Get key for out channel and in channel combination in the solution

#### Parameters

- **out\_chan** (*str*) – The output channel
- **in\_chan** (*str*) – The input channel

#### Returns

The component key

#### Return type

str

### Examples

```
>>> from resistics.regression import get_component_key
>>> get_component_key("Ex", "Hy")
'ExHy'
```

**pydantic model** resistics.transfunc.**TransferFunction**

Bases: [Metadata](#)

Define a generic transfer function

This class is a describes generic transfer function, including:

- The output channels for the transfer function
- The input channels for the transfer function
- The cross channels for the transfer function

The cross channels are the channels that will be used to calculate out the cross powers for the regression.

This generic parent class has no implemented plotting function. However, child classes may have a plotting function as different transfer functions may need different types of plots.

---

**Note:** Users interested in writing a custom transfer function should inherit from this generic Transfer function

---

**See also:**

#### **ImpedanceTensor**

Transfer function for the MT impedance tensor

#### **Tipper**

Transfer function for the MT tipper

## Examples

A generic example

```
>>> from resistics.transfunc import TransferFunction
>>> tf = TransferFunction(variation="example", out_chans=["bye", "see you", "ciao"],
↳ in_chans=["hello", "hi_there"])
>>> print(tf.to_string())
| bye      | | bye_hello      bye_hi_there      | | hello      |
| see you  | = | see you_hello  see you_hi_there  | | hi_there  |
| ciao     | | ciao_hello     ciao_hi_there     |
```

Combining the impedance tensor and the tipper into one TransferFunction

```
>>> tf = TransferFunction(variation="combined", out_chans=["Ex", "Ey"], in_chans=[
↳ "Hx", "Hy", "Hz"])
>>> print(tf.to_string())
| Ex |   | Ex_Hx Ex_Hy Ex_Hz | | Hx |
| Ey | = | Ey_Hx Ey_Hy Ey_Hz | | Hy |
| Hz |
```

```
{
  "title": "TransferFunction",
  "description": "Define a generic transfer function\n\nThis class is a describes_
↳ generic transfer function, including:\n\n- The output channels for the transfer_
↳ function\n- The input channels for the transfer function\n- The cross channels_
↳ for the transfer function\n\nThe cross channels are the channels that will be_
↳ used to calculate out the\ncross powers for the regression.\n\nThis generic_
↳ parent class has no implemented plotting function. However,\nchild classes may_
↳ have a plotting function as different transfer functions\nmay need different_
↳ types of plots.\n\n.. note::\n\n    Users interested in writing a custom transfer_
↳ function should inherit\n    from this generic Transfer function\n\nSee Also\n----
↳ ----\nImpandanceTensor : Transfer function for the MT impedance tensor\nTipper :_
↳ Transfer function for the MT tipper\n\nExamples\n-----\nA generic example\n\n>>
↳ from resistics.transfunc import TransferFunction\n>>> tf =_
↳ TransferFunction(variation="\example", out_chans=["bye", "see you", "ciao\
↳ "], in_chans=["hello", "hi_there"])\n>>> print(tf.to_string())\n| bye      |
↳ | bye_hello      bye_hi_there      | | hello      |\n| see you  | = | see you_
↳ hello      see you_hi_there  | | hi_there |\n| ciao     | | ciao_hello
↳ ciao_hi_there      |\n\nCombining the impedance tensor and the tipper into one_
↳ TransferFunction\n\n>>> tf = TransferFunction(variation="\combined", out_chans=[\
↳ "Ex", "Ey"], in_chans=["Hx", "Hy", "Hz"])\n>>> print(tf.to_string())\n|
↳ Ex |   | Ex_Hx Ex_Hy Ex_Hz | | Hx |\n| Ey | = | Ey_Hx Ey_Hy Ey_Hz | | Hy |\n
↳ | Hz |",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "variation": {
      "title": "Variation",
      "default": "generic",
```

(continues on next page)

(continued from previous page)

```

        "maxLength": 16,
        "type": "string"
    },
    "out_chans": {
        "title": "Out Chans",
        "type": "array",
        "items": {
            "type": "string"
        }
    },
    "in_chans": {
        "title": "In Chans",
        "type": "array",
        "items": {
            "type": "string"
        }
    },
    "cross_chans": {
        "title": "Cross Chans",
        "type": "array",
        "items": {
            "type": "string"
        }
    },
    "n_out": {
        "title": "N Out",
        "type": "integer"
    },
    "n_in": {
        "title": "N In",
        "type": "integer"
    },
    "n_cross": {
        "title": "N Cross",
        "type": "integer"
    }
},
"required": [
    "out_chans",
    "in_chans"
]
}

```

**field name:** `str | None = None`

The name of the transfer function, this will be set automatically

**Validated by**

- `validate_name`

**field variation:** `ConstrainedStrValue = 'generic'`

A short additional bit of information about this variation

**Constraints**



- **maxLength** = 16

**field out\_chans:** `List[str]` [Required]

The output channels

**field in\_chans:** `List[str]` [Required]

The input channels

**field cross\_chans:** `List[str] | None = None`

The channels to use for calculating the cross spectra

**Validated by**

- `validate_cross_chans`

**field n\_out:** `int | None = None`

The number of output channels

**Validated by**

- `validate_n_out`

**field n\_in:** `int | None = None`

The number of input channels

**Validated by**

- `validate_n_in`

**field n\_cross:** `int | None = None`

The number of cross power channels

**Validated by**

- `validate_n_cross`

**classmethod validate**(*value*: `TransferFunction | Dict[str, Any]`) → *TransferFunction*

Validate a TransferFunction

**Parameters**

**value** (`Union[TransferFunction, Dict[str, Any]]`) – A TransferFunction child class or a dictionary

**Returns**

A TransferFunction or TransferFunction child class

**Return type**

*TransferFunction*

**Raises**

- **ValueError** – If the value is neither a TransferFunction or a dictionary
- **KeyError** – If name is not in the dictionary
- **ValueError** – If initialising from dictionary fails

## Examples

The following example will show how a child TransferFunction class can be instantiated using a dictionary and the parent TransferFunction (but only as long as that child class has been imported).

```
>>> from resistics.transfunc import TransferFunction
```

Show known TransferFunction types in built into resistics

```
>>> for entry in TransferFunction._types.items():
...     print(entry)
('ImpedanceTensor', <class 'resistics.transfunc.ImpedanceTensor'>)
('Tipper', <class 'resistics.transfunc.Tipper'>)
```

Now let's initialise an ImpedanceTensor from the base TransferFunction and a dictionary.

```
>>> mytf = {"name": "ImpedanceTensor", "variation": "ecross", "cross_chans": [
↳ "Ex", "Ey"]}
>>> test = TransferFunction(**mytf)
Traceback (most recent call last):
...
KeyError: 'out_chans'
```

This is not quite what we were expecting. The generic TransferFunction requires out\_chans to be defined, but they are not in the dictionary as the ImpedanceTensor child class defaults these. To get this to work, instead use the validate class method. This is the class method used by pydantic when instantiating.

```
>>> mytf = {"name": "ImpedanceTensor", "variation": "ecross", "cross_chans": [
↳ "Ex", "Ey"]}
>>> test = TransferFunction.validate(mytf)
>>> test.summary()
{
  'name': 'ImpedanceTensor',
  'variation': 'ecross',
  'out_chans': ['Ex', 'Ey'],
  'in_chans': ['Hx', 'Hy'],
  'cross_chans': ['Ex', 'Ey'],
  'n_out': 2,
  'n_in': 2,
  'n_cross': 2
}
```

That's more like it. This will raise errors if an unknown type of TransferFunction is received.

```
>>> mytf = {"name": "NewTF", "cross_chans": ["Ex", "Ey"]}
>>> test = TransferFunction.validate(mytf)
Traceback (most recent call last):
...
ValueError: Unable to initialise NewTF from dictionary
```

Or if the dictionary does not have a name key

```
>>> mytf = {"cross_chans": ["Ex", "Ey"]}
>>> test = TransferFunction.validate(mytf)
```

(continues on next page)

(continued from previous page)

```
Traceback (most recent call last):
...
KeyError: 'No name provided for initialisation of TransferFunction'
```

Unexpected inputs will also raise an error

```
>>> test = TransferFunction.validate(5)
Traceback (most recent call last):
...
ValueError: TransferFunction unable to initialise from <class 'int'>
```

**n\_eqns\_per\_output()** → int

Get the number of equations per output

**n\_regressors()** → int

Get the number of regressors

**solution\_components()** → List[str]

Get the components of the solution based on the input and output channels

**Returns**

The solution components

**Return type**

List[str]

## Examples

```
>>> from resisticks.transfunc import TransferFunction
>>> tf = TransferFunction(
...     name="example",
...     variation="a",
...     in_chans=["a", "b", "c"],
...     out_chans=["x", "y"]
... )
>>> tf.solution_components()
['xa', 'xb', 'xc', 'ya', 'yb', 'yc']
```

**to\_string()**

Get the transfer function as as string

**pydantic model** resisticks.transfunc.ImpedanceTensor

Bases: *TransferFunction*

Standard magnetotelluric impedance tensor

## Notes

Information about data units

- Magnetic permeability in  $\text{nT} \cdot \text{m} / \text{A}$
- Electric (E) data is in  $\text{mV}/\text{m}$
- Magnetic (H) data is in  $\text{nT}$
- $Z = E/H$  is in  $\text{mV} / \text{m} \cdot \text{nT}$
- Units of resistance = Ohm =  $\text{V} / \text{A}$

## Examples

```
>>> from resisticks.transfunc import ImpedanceTensor
>>> tf = ImpedanceTensor()
>>> print(tf.to_string())
| Ex | = | Ex_Hx Ex_Hy | | Hx |
| Ey |   | Ey_Hx Ey_Hy | | Hy |
```

```
{
  "title": "ImpedanceTensor",
  "description": "Standard magnetotelluric impedance tensor\n\nNotes\n-----\n
  ↳nInformation about data units\n\n- Magnetic permeability in nT . m / A\n-
  ↳Electric (E) data is in mV/m\n- Magnetic (H) data is in nT\n- Z = E/H is in mV /
  ↳m . nT\n- Units of resistance = Ohm = V / A\n\nExamples\n-----\n>>> from
  ↳resisticks.transfunc import ImpedanceTensor\n>>> tf = ImpedanceTensor()\n>>>
  ↳print(tf.to_string())\n| Ex | = | Ex_Hx Ex_Hy | | Hx |\n| Ey |   | Ey_Hx Ey_Hy |
  ↳| Hy |",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "variation": {
      "title": "Variation",
      "default": "default",
      "maxLength": 16,
      "type": "string"
    },
    "out_chans": {
      "title": "Out Chans",
      "default": [
        "Ex",
        "Ey"
      ],
      "type": "array",
      "items": {
        "type": "string"
      }
    }
  },
}
```

(continues on next page)

(continued from previous page)

```

    "in_chans": {
        "title": "In Chans",
        "default": [
            "Hx",
            "Hy"
        ],
        "type": "array",
        "items": {
            "type": "string"
        }
    },
    "cross_chans": {
        "title": "Cross Chans",
        "type": "array",
        "items": {
            "type": "string"
        }
    },
    "n_out": {
        "title": "N Out",
        "type": "integer"
    },
    "n_in": {
        "title": "N In",
        "type": "integer"
    },
    "n_cross": {
        "title": "N Cross",
        "type": "integer"
    }
}

```

**field variation:** `ConstrainedStrValue = 'default'`

A short additional bit of information about this variation

#### Constraints

- `maxLength = 16`

**field out\_chans:** `List[str] = ['Ex', 'Ey']`

The output channels

**field in\_chans:** `List[str] = ['Hx', 'Hy']`

The input channels

**static get\_resistivity**(*periods*: `ndarray`, *component*: `Component`) → `ndarray`

Get apparent resistivity for a component

#### Parameters

- **periods** (`np.ndarray`) – The periods of the component
- **component** (`Component`) – The component values

**Returns**

Apparent resistivity

**Return type**

np.ndarray

**static** `get_phase(key: str, component: Component) → ndarray`

Get the phase for the component

---

**Note:** Components ExHx and ExHy are wrapped around in [0,90]

---

**Parameters**

- **key** (*str*) – The component name
- **component** (*Component*) – The component values

**Returns**

The phase values

**Return type**

np.ndarray

**static** `get_fig(x_lim: List[float] | None = None, res_lim: List[float] | None = None, phs_lim: List[float] | None = None) → Figure`

Get a figure for plotting the ImpedanceTensor

**Parameters**

- **x\_lim** (*Optional[List[float]]*, *optional*) – The x limits, to be provided as powers of 10, by default None. For example, for 0.001, use -3
- **res\_lim** (*Optional[List[float]]*, *optional*) – The y limits for resistivity, to be provided as powers of 10, by default None. For example, for 1000, use 3
- **phs\_lim** (*Optional[List[float]]*, *optional*) – The phase limits, by default None

**Returns**

Plotly figure

**Return type**

go.Figure

**static** `plot(freqs: List[float], components: Dict[str, Component], fig: Figure | None = None, to_plot: List[str] | None = None, legend: str = 'Impedance tensor', x_lim: List[float] | None = None, res_lim: List[float] | None = None, phs_lim: List[float] | None = None, symbol: str | None = 'circle') → Figure`

Plot the Impedance tensor

**Parameters**

- **freqs** (*List[float]*) – The frequencies where the impedance tensor components have been calculated
- **components** (*Dict[str, Component]*) – The component data
- **fig** (*Optional[go.Figure]*, *optional*) – Figure to add to, by default None
- **to\_plot** (*Optional[List[str]]*, *optional*) – The components to plot, by default all of the components of the impedance tensor

- **legend** (*str*, *optional*) – Legend prefix for the components, by default “Impedance tensor”
- **x\_lim** (*Optional[List[float]]*, *optional*) – The x limits, to be provided as powers of 10, by default None. For example, for 0.001, use -3. Only used when a figure is not provided.
- **res\_lim** (*Optional[List[float]]*, *optional*) – The y limits for resistivity, to be provided as powers of 10, by default None. For example, for 1000, use 3. Only used when a figure is not provided.
- **phs\_lim** (*Optional[List[float]]*, *optional*) – The phase limits, by default None. Only used when a figure is not provided.
- **symbol** (*Optional[str]*, *optional*) – The marker symbol to use, by default “circle”

**Returns**

[description]

**Return type**

go.Figure

**pydantic model** resisticks.transfunc.TipperBases: *TransferFunction*

Magnetotelluric tipper

The tipper components are  $T_x = H_z H_x$  and  $T_y = H_z H_y$ The tipper length is  $\sqrt{\text{Re}(T_x)^2 + \text{Re}(T_y)^2}$ The tipper angle is  $\arctan(\text{Re}(T_y)/\text{Re}(T_x))$ **Notes**

Information about units

- Tipper  $T = H/H$  is dimensionless

**Examples**

```
>>> from resisticks.transfunc import Tipper
>>> tf = Tipper()
>>> print(tf.to_string())
| Hz | = | Hz_Hx Hz_Hy | | Hx |
                        | Hy |
```

```
{
  "title": "Tipper",
  "description": "Magnetotelluric tipper\n\nThe tipper components are  $T_x = H_z H_x$ ,  

  and  $T_y = H_z H_y$ \n\nThe tipper length is  $\sqrt{\text{Re}(T_x)^2 + \text{Re}(T_y)^2}$ \n\nThe tipper  

  angle is  $\arctan(\text{Re}(T_y)/\text{Re}(T_x))$ \n\nNotes\n-----\nInformation about units\n\n-  

  Tipper  $T = H/H$  is dimensionless\n\nExamples\n-----\n>>> from resisticks.  

  transfunc import Tipper\n>>> tf = Tipper()\n>>> print(tf.to_string())\n| Hz | = |  

  Hz_Hx Hz_Hy | | Hx | \n                        | Hy |",
  "type": "object",
  "properties": {
```

(continues on next page)

(continued from previous page)

```
"name": {
  "title": "Name",
  "type": "string"
},
"variation": {
  "title": "Variation",
  "default": "default",
  "maxLength": 16,
  "type": "string"
},
"out_chans": {
  "title": "Out Chans",
  "default": [
    "Hz"
  ],
  "type": "array",
  "items": {
    "type": "string"
  }
},
"in_chans": {
  "title": "In Chans",
  "default": [
    "Hx",
    "Hy"
  ],
  "type": "array",
  "items": {
    "type": "string"
  }
},
"cross_chans": {
  "title": "Cross Chans",
  "type": "array",
  "items": {
    "type": "string"
  }
},
"n_out": {
  "title": "N Out",
  "type": "integer"
},
"n_in": {
  "title": "N In",
  "type": "integer"
},
"n_cross": {
  "title": "N Cross",
  "type": "integer"
}
}
```



**field variation:** `ConstrainedStrValue = 'default'`

A short additional bit of information about this variation

#### Constraints

- **maxLength** = 16

**field out\_chans:** `List[str] = ['Hz']`

The output channels

**field in\_chans:** `List[str] = ['Hx', 'Hy']`

The input channels

**get\_length**(*components: Dict[str, Component]*) → ndarray

Get the tipper length

**get\_real\_angle**(*components: Dict[str, Component]*) → ndarray

Get the real angle

**get\_imag\_angle**(*components: Dict[str, Component]*) → ndarray

Get the imaginary angle

**plot**(*freqs: List[float], components: Dict[str, Component], x\_lim: List[float] | None = None, len\_lim: List[float] | None = None, ang\_lim: List[float] | None = None*) → Figure

Plot the impedance tensor

**Warning:** This probably needs further checking and verification

#### Parameters

- **freqs** (*List[float]*) – The x axis frequencies
- **components** (*Dict[str, Component]*) – The component data
- **x\_lim** (*Optional[List[float]], optional*) – The x limits, to be provided as powers of 10, by default None. For example, for 0.001, use -3
- **len\_lim** (*Optional[List[float]], optional*) – The y limits for tipper length, to be provided as powers of 10, by default None. For example, for 1000, use 3
- **ang\_lim** (*Optional[List[float]], optional*) – The angle limits, by default None

#### Returns

Plotly figure

#### Return type

go.Figure

### resisticks.window module

Module for calculating window related data. Windows can be indexed relative to two starting indices.

- Local window index
  - Window index relative to the TimeData is called “local\_win”
  - Local window indices always start at 0
- Global window index

- The global window index is relative to the project reference time
- The 0 index window begins at the reference time
- This window indexing is to synchronise data across sites

The global window index is considered the default and sometimes referred to as the window. Local windows should be explicitly referred to as `local_win` in all cases.

The window module includes functionality to do the following:

- Windowing utility functions to calculate window and overlap sizes
- Functions to map windows to samples in `TimeData`
- Converting a global index array to datetime

Usually with windowing, there is a window size and windows overlap with each other for a set number of samples. As an illustrative examples, consider a signal sampled at 10 Hz ( $dt=0.1$  seconds) with 24 samples. This will be windowed using a window size of 8 samples per window and a 2 sample overlap.

```
>>> import numpy as np
>>> import matplotlib.pyplot as plt
>>> fs = 10
>>> n_samples = 24
>>> win_size = 8
>>> olap_size = 2
>>> times = np.arange(0, n_samples) * (1/fs)
```

The first window

```
>>> start_win1 = 0
>>> end_win1 = win_size
>>> win1_times = times[start_win1:end_win1]
```

The second window

```
>>> start_win2 = end_win1 - olap_size
>>> end_win2 = start_win2 + win_size
>>> win2_times = times[start_win2:end_win2]
```

The third window

```
>>> start_win3 = end_win2 - olap_size
>>> end_win3 = start_win3 + win_size
>>> win3_times = times[start_win3:end_win3]
```

The fourth window

```
>>> start_win4 = end_win3 - olap_size
>>> end_win4 = start_win4 + win_size
>>> win4_times = times[start_win4:end_win4]
```

Let's look at the actual window times for each window

```
>>> win1_times
array([0. , 0.1, 0.2, 0.3, 0.4, 0.5, 0.6, 0.7])
>>> win2_times
```

(continues on next page)

(continued from previous page)

```
array([0.6, 0.7, 0.8, 0.9, 1. , 1.1, 1.2, 1.3])
>>> win3_times
array([1.2, 1.3, 1.4, 1.5, 1.6, 1.7, 1.8, 1.9])
>>> win4_times
array([1.8, 1.9, 2. , 2.1, 2.2, 2.3])
```

The duration and increments of windows can be calculated using provided methods

```
>>> from resistics.window import win_duration, inc_duration
>>> print(win_duration(win_size, fs))
0:00:00.7
>>> print(inc_duration(win_size, olap_size, fs))
0:00:00.6
```

Plot the windows to give an illustration of how it works

```
>>> plt.plot(win1_times, np.ones_like(win1_times), "bo", label="window1")
>>> plt.plot(win2_times, np.ones_like(win2_times)*2, "ro", label="window2")
>>> plt.plot(win3_times, np.ones_like(win3_times)*3, "go", label="window3")
>>> plt.plot(win4_times, np.ones_like(win4_times)*4, "co", label="window4")
>>> plt.xlabel("Time [s]")
>>> plt.legend()
>>> plt.grid()
>>> plt.tight_layout()
>>> plt.show()
```

`resistics.window.win_duration(win_size: int, fs: float) → timedelta`

Get the window duration

#### Parameters

- **win\_size** (*int*) – Window size in samples
- **fs** (*float*) – Sampling frequency Hz

#### Returns

Duration

#### Return type


RSTimeDelta

### Examples

A few examples with different sampling frequencies and window sizes

```
>>> from resistics.window import win_duration
>>> duration = win_duration(512, 512)
>>> print(duration)
0:00:00.998046875
>>> duration = win_duration(520, 512)
>>> print(duration)
0:00:01.013671875
>>> duration = win_duration(4096, 16_384)
>>> print(duration)
```

(continues on next page)



(continued from previous page)

```
0:00:00.24993896484375
>>> duration = win_duration(200, 0.05)
>>> print(duration)
1:06:20
```

`resistics.window.inc_duration(win_size: int, olap_size: int, fs: float)` → `attotimedelta`

Get the increment between window start times

If the overlap size = 0, then the time increment between windows is simply the window duration. However, when there is an overlap, the increment between window start times has to be adjusted by the overlap size

#### Parameters

- **win\_size** (*int*) – The window size in samples
- **olap\_size** (*int*) – The overlap size in samples
- **fs** (*float*) – The sample frequency Hz

#### Returns

The duration of the window

#### Return type

`RSTimeDelta`

### Examples

```
>>> from resistics.window import inc_duration
>>> increment = inc_duration(128, 32, 128)
>>> print(increment)
0:00:00.75
>>> increment = inc_duration(128*3600, 128*60, 128)
>>> print(increment)
0:59:00
```

`resistics.window.win_to_datetime(ref_time: attodatetime, global_win: int, increment: attotimedelta)` → `attodatetime`

Convert reference window index to start time of window

#### Parameters

- **ref\_time** (`RSDatetime`) – Reference time
- **global\_win** (*int*) – Window index relative to reference time
- **increment** (`RSTimeDelta`) – The increment duration

#### Returns

Start time of window

#### Return type

`RSDatetime`

## Examples

An example with sampling at 1 Hz, a window size of 100 and an overlap size of 25.

```
>>> from resistics.sampling import to_datetime
>>> from resistics.window import inc_duration, win_to_datetime
>>> ref_time = to_datetime("2021-01-01 00:00:00")
>>> fs = 1
>>> win_size = 60
>>> olap_size = 15
>>> increment = inc_duration(win_size, olap_size, fs)
>>> print(increment)
0:00:45
```

The increment is the time increment between the start of time one window and the succeeding window.

```
>>> print(win_to_datetime(ref_time, 0, increment))
2021-01-01 00:00:00
>>> print(win_to_datetime(ref_time, 1, increment))
2021-01-01 00:00:45
>>> print(win_to_datetime(ref_time, 2, increment))
2021-01-01 00:01:30
>>> print(win_to_datetime(ref_time, 3, increment))
2021-01-01 00:02:15
```

`resistics.window.datetime_to_win(ref_time: attodatetime, time: attodatetime, increment: attotimedelta, method: str = 'round') → int`

Convert a datetime to a global window index

### Parameters

- **ref\_time** (*RSDatetime*) – Reference time
- **time** (*RSDatetime*) – Datetime to convert
- **increment** (*RSTimeDelta*) – The increment duration
- **method** (*str*, *optional*) – Method for dealing with float results, by default “round”

### Returns

The global window index i.e. the window index relative to the reference time

### Return type

*int*

### Raises

**ValueError** – If time < ref\_time

## Examples

A simple example to show the logic

```
>>> from resistics.sampling import to_datetime, to_timedelta
>>> from resistics.window import datetime_to_win, win_to_datetime, inc_duration
>>> ref_time = to_datetime("2021-01-01 00:00:00")
>>> time = to_datetime("2021-01-01 00:01:00")
>>> increment = to_timedelta(60)
>>> global_win = datetime_to_win(ref_time, time, increment)
>>> global_win
1
>>> print(win_to_datetime(ref_time, global_win, increment))
2021-01-01 00:01:00
```

A more complex logic with window sizes, overlap sizes and sampling frequencies

```
>>> fs = 128
>>> win_size = 256
>>> olap_size = 64
>>> ref_time = to_datetime("2021-03-15 00:00:00")
>>> time = to_datetime("2021-04-17 18:00:00")
>>> increment = inc_duration(win_size, olap_size, fs)
>>> print(increment)
0:00:01.5
>>> global_win = datetime_to_win(ref_time, time, increment)
>>> global_win
1944000
>>> print(win_to_datetime(ref_time, global_win, increment))
2021-04-17 18:00:00
```

In this scenario, explore the use of rounding

```
>>> time = to_datetime("2021-04-17 18:00:00.50")
>>> global_win = datetime_to_win(ref_time, time, increment, method = "floor")
>>> global_win
1944000
>>> print(win_to_datetime(ref_time, global_win, increment))
2021-04-17 18:00:00
>>> global_win = datetime_to_win(ref_time, time, increment, method = "ceil")
>>> global_win
1944001
>>> print(win_to_datetime(ref_time, global_win, increment))
2021-04-17 18:00:01.5
>>> global_win = datetime_to_win(ref_time, time, increment, method = "round")
>>> global_win
1944000
>>> print(win_to_datetime(ref_time, global_win, increment))
2021-04-17 18:00:00
```

Another example with a window duration of greater than a day

```
>>> fs = 4.8828125e-05
>>> win_size = 64
```

(continues on next page)

(continued from previous page)

```
>>> olap_size = 16
>>> ref_time = to_datetime("1985-07-18 01:00:20")
>>> time = to_datetime("1985-09-22 23:00:00")
>>> increment = inc_duration(win_size, olap_size, fs)
>>> print(increment)
11 days, 9:04:00
>>> global_win = datetime_to_win(ref_time, time, increment)
>>> global_win
6
>>> print(win_to_datetime(ref_time, global_win, increment))
1985-09-24 07:24:20
```

This time is greater than the time that was transformed to global window, 1985-09-22 23:00:00. Try again, this time with the floor option.

```
>>> global_win = datetime_to_win(ref_time, time, increment, method="floor")
>>> global_win
5
>>> print(win_to_datetime(ref_time, global_win, increment))
1985-09-12 22:20:20
```

`resistics.window.get_first_and_last_win(ref_time: attodatetime, metadata: DecimatedLevelMetadata, win_size: int, olap_size: int) → Tuple[int, int]`

Get first and last window for a decimated data level

---

**Note:** For the last window, on initial calculation this may be one or a maximum of two windows beyond the last time. The last window is adjusted in this function.

Two windows may occur when the time of the last sample is in the overlap of the final two windows.

---

### Parameters

- **ref\_time** (*RSDateTime*) – The reference time
- **metadata** (*DecimatedLevelMetadata*) – Metadata for the decimation level
- **win\_size** (*int*) – Window size in samples
- **olap\_size** (*int*) – Overlap size in samples

### Returns

First and last global windows. This is window indices relative to the reference time

### Return type

`Tuple[int, int]`

### Raises

**ValueError** – If unable to calculate the last window correctly as this will result in an incorrect number of windows



## Examples

Get the first and last window for the first decimation level in a decimated data instance.

```
>>> from resisticks.testing import decimated_data_random
>>> from resisticks.sampling import to_datetime
>>> from resisticks.window import get_first_and_last_win, win_to_datetime
>>> from resisticks.window import win_duration, inc_duration
>>> ref_time = to_datetime("2021-01-01 00:00:00")
>>> dec_data = decimated_data_random(fs=0.1, first_time="2021-01-01 00:05:10", n_
↳ samples=100, factor=10)
```

Get the metadata for decimation level 0

```
>>> level_metadata = dec_data.metadata.levels_metadata[0]
>>> level_metadata.summary()
{
  'fs': 10.0,
  'n_samples': 10000,
  'first_time': '2021-01-01 00:05:10.000000_000000_000000_000000',
  'last_time': '2021-01-01 00:21:49.899999_999999_977300_000000'
}
```

**Note:** As a point of interest, note how the last time is actually slightly incorrect. This is due to machine precision issues described in more detail here <https://docs.python.org/3/tutorial/floatingpoint.html>. Whilst there is value in using the high resolution datetime format for high sampling rates, there is a tradeoff. Such are the perils of floating point arithmetic.

The next step is to calculate the first and last window, relative to the reference time

```
>>> win_size = 100
>>> olap_size = 25
>>> first_win, last_win = get_first_and_last_win(ref_time, level_metadata, win_size,
↳ olap_size)
>>> print(first_win, last_win)
42 173
```

These window indices can be converted to start times of the windows. The last window is checked to make sure it does not extend past the end of the time data. First get the window duration and increments.

```
>>> duration = win_duration(win_size, level_metadata.fs)
>>> print(duration)
0:00:09.9
>>> increment = inc_duration(win_size, olap_size, level_metadata.fs)
>>> print(increment)
0:00:07.5
```

Now calculate the times of the windows

```
>>> first_win_start_time = win_to_datetime(ref_time, 42, increment)
>>> last_win_start_time = win_to_datetime(ref_time, 173, increment)
>>> print(first_win_start_time, last_win_start_time)
```

(continues on next page)

(continued from previous page)

```

2021-01-01 00:05:15 2021-01-01 00:21:37.5
>>> print(last_win_start_time + duration)
2021-01-01 00:21:47.4
>>> print(level_metadata.last_time)
2021-01-01 00:21:49.89999999999999773
>>> level_metadata.last_time > last_win_start_time + increment
True

```

`resistics.window.get_win_starts(ref_time: attodatetime, win_size: int, olap_size: int, fs: float, n_wins: int, index_offset: int)` → `DatetimeIndex`

Get window start times

This is a useful for getting the timestamps for the windows in a dataset

#### Parameters

- **ref\_time** (*RSDatetime*) – The reference time
- **win\_size** (*int*) – The window size
- **olap\_size** (*int*) – The overlap size
- **fs** (*float*) – The sampling frequency
- **n\_wins** (*int*) – The number of windows
- **index\_offset** (*int*) – The index offset from the reference time

#### Returns

The start times of the windows

#### Return type

`pd.DatetimeIndex`

### Examples

```

>>> import pandas as pd
>>> from resistics.sampling import to_datetime
>>> from resistics.window import get_win_starts
>>> ref_time = to_datetime("2021-01-01 00:00:00")
>>> win_size = 100
>>> olap_size = 25
>>> fs = 10
>>> n_wins = 3
>>> index_offset = 480
>>> starts = get_win_starts(ref_time, win_size, olap_size, fs, n_wins, index_offset)
>>> pd.Series(starts)
0    2021-01-01 01:00:00.000
1    2021-01-01 01:00:07.500
2    2021-01-01 01:00:15.000
dtype: datetime64[ns]

```

`resistics.window.get_win_ends(starts: DatetimeIndex, win_size: int, fs: float)` → `DatetimeIndex`

Get window end times

#### Parameters

- **starts** (*RSDatetime*) – The start times of the windows
- **win\_size** (*int*) – The window size
- **fs** (*float*) – The sampling frequency

**Returns**

The end times of the windows

**Return type**

pd.DatetimeIndex

**Examples**

```
>>> import pandas as pd
>>> from resisticks.sampling import to_datetime
>>> from resisticks.window import get_win_starts, get_win_ends
>>> ref_time = to_datetime("2021-01-01 00:00:00")
>>> win_size = 100
>>> olap_size = 25
>>> fs = 10
>>> n_wins = 3
>>> index_offset = 480
>>> starts = get_win_starts(ref_time, win_size, olap_size, fs, n_wins, index_offset)
>>> pd.Series(starts)
0    2021-01-01 01:00:00.000
1    2021-01-01 01:00:07.500
2    2021-01-01 01:00:15.000
dtype: datetime64[ns]
>>> ends = get_win_ends(starts, win_size, fs)
>>> pd.Series(ends)
0    2021-01-01 01:00:09.900
1    2021-01-01 01:00:17.400
2    2021-01-01 01:00:24.900
dtype: datetime64[ns]
```

`resisticks.window.get_win_table(ref_time: attodatetime, metadata: DecimatedLevelMetadata, win_size: int, olap_size: int) → DataFrame`

Get a DataFrame with

**Parameters**

- **ref\_time** (*RSDatetime*) – Reference
- **metadata** (*DecimatedLevelMetadata*) – Metadata for the decimation level
- **win\_size** (*int*) – The window size
- **olap\_size** (*int*) – The overlap size

**Returns**

A pandas DataFrame with details about each window

**Return type**

pd.DataFrame

## Examples

```

>>> import matplotlib.pyplot as plt
>>> from resistics.decimate import DecimatedLevelMetadata
>>> from resistics.sampling import to_datetime, to_timedelta
>>> from resistics.window import get_win_table
>>> ref_time = to_datetime("2021-01-01 00:00:00")
>>> fs = 10
>>> n_samples = 1000
>>> first_time = to_datetime("2021-01-01 01:00:00")
>>> last_time = first_time + to_timedelta((n_samples-1)/fs)
>>> metadata = DecimatedLevelMetadata(fs=10, n_samples=1000, first_time=first_time,
↳ last_time=last_time)
>>> print(metadata.fs, metadata.first_time, metadata.last_time)
10.0 2021-01-01 01:00:00 2021-01-01 01:01:39.9
>>> win_size = 100
>>> olap_size = 25
>>> df = get_win_table(ref_time, metadata, win_size, olap_size)
>>> print(df.to_string())
   global  local  from_sample  to_sample          win_start      ↵
↳ win_end
0         480         0         0         99 2021-01-01 01:00:00.000 2021-01-01
↳ 01:00:09.900
1         481         1        75        174 2021-01-01 01:00:07.500 2021-01-01
↳ 01:00:17.400
2         482         2       150       249 2021-01-01 01:00:15.000 2021-01-01
↳ 01:00:24.900
3         483         3       225       324 2021-01-01 01:00:22.500 2021-01-01
↳ 01:00:32.400
4         484         4       300       399 2021-01-01 01:00:30.000 2021-01-01
↳ 01:00:39.900
5         485         5       375       474 2021-01-01 01:00:37.500 2021-01-01
↳ 01:00:47.400
6         486         6       450       549 2021-01-01 01:00:45.000 2021-01-01
↳ 01:00:54.900
7         487         7       525       624 2021-01-01 01:00:52.500 2021-01-01
↳ 01:01:02.400
8         488         8       600       699 2021-01-01 01:01:00.000 2021-01-01
↳ 01:01:09.900
9         489         9       675       774 2021-01-01 01:01:07.500 2021-01-01
↳ 01:01:17.400
10        490        10       750       849 2021-01-01 01:01:15.000 2021-01-01
↳ 01:01:24.900
11        491        11       825       924 2021-01-01 01:01:22.500 2021-01-01
↳ 01:01:32.400
12        492        12       900       999 2021-01-01 01:01:30.000 2021-01-01
↳ 01:01:39.900

```

Plot six windows to illustrate the overlap

```

>>> plt.figure(figsize=(8, 3))
>>> for idx, row in df.iterrows():
...     color = "red" if idx%2 == 0 else "blue"

```


(continues on next page)

(continued from previous page)

```

...     plt.axvspan(row.loc["win_start"], row.loc["win_end"], alpha=0.5,
    ↪color=color)
...     if idx > 5:
...         break
>>> plt.tight_layout()
>>> plt.show()

```



### pydantic model `resistics.window.WindowParameters`

Bases: `ResisticsModel`

Windowing parameters per decimation level

Windowing parameters are the window and overlap size for each decimation level.

#### Parameters

- **n\_levels** (`int`) – The number of decimation levels
- **min\_n\_wins** (`int`) – Minimum number of windows
- **win\_sizes** (`List[int]`) – The window sizes per decimation level
- **olap\_sizes** (`List[int]`) – The overlap sizes per decimation level

### Examples

Generate decimation and windowing parameters for data sampled at 4096 Hz. Note that requesting window sizes or overlap sizes for decimation levels that do not exist will raise a `ValueError`.

```

>>> from resistics.decimate import DecimationSetup
>>> from resistics.window import WindowSetup
>>> dec_setup = DecimationSetup(n_levels=3, per_level=3)
>>> dec_params = dec_setup.run(4096)
>>> dec_params.summary()
{
  'fs': 4096.0,
  'n_levels': 3,
  'per_level': 3,
  'min_samples': 256,
  'eval_freqs': [

```

(continues on next page)

(continued from previous page)

```

        1024.0,
        724.0773439350246,
        512.0,
        362.0386719675123,
        256.0,
        181.01933598375615,
        128.0,
        90.50966799187808,
        64.0
    ],
    'dec_factors': [1, 2, 8],
    'dec_increments': [1, 2, 4],
    'dec_fs': [4096.0, 2048.0, 512.0]
}
>>> win_params = WindowSetup().run(dec_params.n_levels, dec_params.dec_fs)
>>> win_params.summary()
{
    'n_levels': 3,
    'min_n_wins': 5,
    'win_sizes': [1024, 512, 128],
    'olap_sizes': [256, 128, 32]
}
>>> win_params.get_win_size(0)
1024
>>> win_params.get_olap_size(0)
256
>>> win_params.get_olap_size(3)
Traceback (most recent call last):
...
ValueError: Level 3 must be 0 <= level < 3

```

```

{
    "title": "WindowParameters",
    "description": "Windowing parameters per decimation level\n\nWindowing_
    ↳ parameters are the window and overlap size for each decimation\nlevel.\n
    ↳ nParameters\n-----\nn_levels : int\n    The number of decimation levels\nmin_
    ↳ n_wins : int\n    Minimum number of windows\nwin_sizes : List[int]\n    The_
    ↳ window sizes per decimation level\nolap_sizes : List[int]\n    The overlap sizes_
    ↳ per decimation level\n\nExamples\n-----\nGenerate decimation and windowing_
    ↳ parameters for data sampled at 4096 Hz.\nNote that requesting window sizes or_
    ↳ overlap sizes for decimation levels\nthat do not exist will raise a ValueError.\n
    ↳ \n>>> from resistics.decimate import DecimationSetup\n>>> from resistics.window_
    ↳ import WindowSetup\n>>> dec_setup = DecimationSetup(n_levels=3, per_level=3)\n>>>_
    ↳ dec_params = dec_setup.run(4096)\n>>> dec_params.summary()\n{\n    'fs': 4096.0,\n
    ↳ \n    'n_levels': 3,\n    'per_level': 3,\n    'min_samples': 256,\n    'eval_freqs_
    ↳ ': [\n        1024.0,\n        724.0773439350246,\n        512.0,\n        362.
    ↳ 0386719675123,\n        256.0,\n        181.01933598375615,\n        128.0,\n    _
    ↳ \n        90.50966799187808,\n        64.0\n    ],\n    'dec_factors': [1, 2, 8],\n
    ↳ \n    'dec_increments': [1, 2, 4],\n    'dec_fs': [4096.0, 2048.0, 512.0]\n}\n>>> win_
    ↳ \n    params = WindowSetup().run(dec_params.n_levels, dec_params.dec_fs)\n>>> win_
    ↳ \n    params.summary()\n{\n    'n_levels': 3,\n    'min_n_wins': 5,\n    'win_sizes':_

```

(continues on next page)

(continued from previous page)

```

↪[1024, 512, 128],\n      'olap_sizes': [256, 128, 32]\n}\n>>> win_params.get_win_
↪size(0)\n1024\n>>> win_params.get_olap_size(0)\n256\n>>> win_params.get_olap_
↪size(3)\nTraceback (most recent call last):\n...\nValueError: Level 3 must be 0
↪<= level < 3",
  "type": "object",
  "properties": {
    "n_levels": {
      "title": "N Levels",
      "type": "integer"
    },
    "min_n_wins": {
      "title": "Min N Wins",
      "type": "integer"
    },
    "win_sizes": {
      "title": "Win Sizes",
      "type": "array",
      "items": {
        "type": "integer"
      }
    },
    "olap_sizes": {
      "title": "Olap Sizes",
      "type": "array",
      "items": {
        "type": "integer"
      }
    }
  },
  "required": [
    "n_levels",
    "min_n_wins",
    "win_sizes",
    "olap_sizes"
  ]
}

```

**field** `n_levels`: `int` [Required]

**field** `min_n_wins`: `int` [Required]

**field** `win_sizes`: `List[int]` [Required]

**field** `olap_sizes`: `List[int]` [Required]

**check\_level**(*level*: `int`)

Check the decimation level is within range

**get\_win\_size**(*level*: `int`) → `int`

Get window size for a decimation level

**get\_olap\_size**(*level*: `int`) → `int`

Get overlap size for a decimation level

**pydantic model** `resisticks.window.WindowSetup`Bases: `ResisticksProcess`

Setup WindowParameters

WindowSetup outputs the WindowParameters to use for windowing decimated time data.

Window parameters are simply the window and overlap sizes for each decimation level.

**Parameters**

- **min\_size** (*int*, *optional*) – Minimum window size, by default 128
- **min\_olap** (*int*, *optional*) – Minimum overlap size, by default 32
- **win\_factor** (*int*, *optional*) – Window factor, by default 4. Window sizes are calculated by sampling frequency / 4 to ensure sufficient frequency resolution. If the sampling frequency is small, window size will be adjusted to min\_size
- **olap\_proportion** (*float*, *optional*) – The proportion of the window size to use as the overlap, by default 0.25. For example, for a window size of 128, the overlap would be  $0.25 * 128 = 32$
- **min\_n\_wins** (*int*, *optional*) – The minimum number of windows needed in a decimation level, by default 5
- **win\_sizes** (*Optional[List[int]]*, *optional*) – Explicit define window sizes, by default None. Must have the same length as number of decimation levels
- **olap\_sizes** (*Optional[List[int]]*, *optional*) – Explicitly define overlap sizes, by default None. Must have the same length as number of decimation levels

**Examples**

Generate decimation and windowing parameters for data sampled at 0.05 Hz or 20 seconds sampling period

```
>>> from resisticks.decimate import DecimationSetup
>>> from resisticks.window import WindowSetup
>>> dec_params = DecimationSetup(n_levels=3, per_level=3).run(0.05)
>>> dec_params.summary()
{
  'fs': 0.05,
  'n_levels': 3,
  'per_level': 3,
  'min_samples': 256,
  'eval_freqs': [
    0.0125,
    0.008838834764831844,
    0.00625,
    0.004419417382415922,
    0.003125,
    0.002209708691207961,
    0.0015625,
    0.0011048543456039805,
    0.00078125
  ],
  'dec_factors': [1, 2, 8],
  'dec_increments': [1, 2, 4],
```

(continues on next page)



(continued from previous page)

```

    'dec_fs': [0.05, 0.025, 0.00625]
}
>>> win_params = WindowSetup().run(dec_params.n_levels, dec_params.dec_fs)
>>> win_params.summary()
{
    'n_levels': 3,
    'min_n_wins': 5,
    'win_sizes': [128, 128, 128],
    'olap_sizes': [32, 32, 32]
}

```

Window parameters can also be explicitly defined

```

>>> from resisticks.decimate import DecimationSetup
>>> from resisticks.window import WindowSetup
>>> dec_setup = DecimationSetup(n_levels=3, per_level=3)
>>> dec_params = dec_setup.run(0.05)
>>> win_setup = WindowSetup(win_sizes=[1000, 578, 104])
>>> win_params = win_setup.run(dec_params.n_levels, dec_params.dec_fs)
>>> win_params.summary()
{
    'n_levels': 3,
    'min_n_wins': 5,
    'win_sizes': [1000, 578, 104],
    'olap_sizes': [250, 144, 32]
}

```

When providing explicit window and overlap sizes, the size of the overlap is expected to be less than the size of the window

```

>>> from resisticks.decimate import DecimationSetup
>>> from resisticks.window import WindowSetup
>>> dec_setup = DecimationSetup(n_levels=3, per_level=3)
>>> dec_params = dec_setup.run(0.05)
>>> win_setup = WindowSetup(win_sizes=[1000, 578, 104], olap_sizes=[1001, 600, 25])
>>> win_params = win_setup.run(dec_params.n_levels, dec_params.dec_fs)
Traceback (most recent call last):
...
ValueError: Invalid overlaps found [ True  True False]

```

```

{
    "title": "WindowSetup",
    "description": "Setup WindowParameters\n\nWindowSetup outputs the_
↪WindowParameters to use for windowing decimated\ntime data.\n\nWindow parameters_
↪are simply the window and overlap sizes for each\ndecimation level.\n\nParameters\
↪n-----\nmin_size : int, optional\n    Minimum window size, by default 128\
↪nmin_olap : int, optional\n    Minimum overlap size, by default 32\nwin_factor :_
↪int, optional\n    Window factor, by default 4. Window sizes are calculated by_
↪sampling\n    frequency / 4 to ensure sufficient frequency resolution. If the\n _
↪ sampling frequency is small, window size will be adjusted to\n    min_size\nolap_
↪proportion : float, optional\n    The proportion of the window size to use as the_
↪overlap, by default\n    0.25. For example, for a window size of 128, the overlap_

```

(continues on next page)

(continued from previous page)

```

→would be\n    0.25 * 128 = 32\nmin_n_wins : int, optional\n    The minimum number_
→of windows needed in a decimation level, by\n    default 5\nwin_sizes :_
→Optional[List[int]], optional\n    Explicit define window sizes, by default None._
→Must have the same\n    length as number of decimation levels\nolap_sizes :_
→Optional[List[int]], optional\n    Explicitly define overlap sizes, by default_
→None. Must have the same\n    length as number of decimation levels\n\nExamples\n
→-----\nGenerate decimation and windowing parameters for data sampled at 0.05 Hz_
→or\n20 seconds sampling period\n\n>>> from resistics.decimate import_
→DecimationSetup\n>>> from resistics.window import WindowSetup\n>>> dec_params =_
→DecimationSetup(n_levels=3, per_level=3).run(0.05)\n>>> dec_params.summary()\n{\n
→  'fs': 0.05,\n    'n_levels': 3,\n    'per_level': 3,\n    'min_samples': 256,\n
→  'eval_freqs': [\n        0.0125,\n        0.008838834764831844,\n        0.
→00625,\n        0.004419417382415922,\n        0.003125,\n        0.
→002209708691207961,\n        0.0015625,\n        0.0011048543456039805,\n
→0.00078125\n    ],\n    'dec_factors': [1, 2, 8],\n    'dec_increments': [1, 2,_
→4],\n    'dec_fs': [0.05, 0.025, 0.00625]\n}\n>>> win_params = WindowSetup().
→run(dec_params.n_levels, dec_params.dec_fs)\n>>> win_params.summary()\n{\n    'n_
→levels': 3,\n    'min_n_wins': 5,\n    'win_sizes': [128, 128, 128],\n    'olap_
→sizes': [32, 32, 32]\n}\n\nWindow parameters can also be explicitly defined\n\n>>>
→ from resistics.decimate import DecimationSetup\n>>> from resistics.window import_
→WindowSetup\n>>> dec_setup = DecimationSetup(n_levels=3, per_level=3)\n>>> dec_
→params = dec_setup.run(0.05)\n>>> win_setup = WindowSetup(win_sizes=[1000, 578,_
→104])\n>>> win_params = win_setup.run(dec_params.n_levels, dec_params.dec_fs)\n>>>
→ win_params.summary()\n{\n    'n_levels': 3,\n    'min_n_wins': 5,\n    'win_sizes
→': [1000, 578, 104],\n    'olap_sizes': [250, 144, 32]\n}\n\nWhen providing_
→explicit window and overlap sizes, the size of the overlap\nis expected to be_
→less than the size of the window\n\n>>> from resistics.decimate import_
→DecimationSetup\n>>> from resistics.window import WindowSetup\n>>> dec_setup =_
→DecimationSetup(n_levels=3, per_level=3)\n>>> dec_params = dec_setup.run(0.05)\n>>
→ win_setup = WindowSetup(win_sizes=[1000, 578, 104], olap_sizes=[1001, 600, 25])\n
→\n>>> win_params = win_setup.run(dec_params.n_levels, dec_params.dec_fs)\n
→nTraceback (most recent call last):\n...\nValueError: Invalid overlaps found [_
→True True False]",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        },
        "min_size": {
            "title": "Min Size",
            "default": 128,
            "type": "integer"
        },
        "min_olap": {
            "title": "Min Olap",
            "default": 32,
            "type": "integer"
        },
        "win_factor": {
            "title": "Win Factor",
            "default": 4,

```

(continues on next page)

(continued from previous page)

```

        "type": "integer"
    },
    "olap_proportion": {
        "title": "Olap Proportion",
        "default": 0.25,
        "type": "number"
    },
    "min_n_wins": {
        "title": "Min N Wins",
        "default": 5,
        "type": "integer"
    },
    "win_sizes": {
        "title": "Win Sizes",
        "type": "array",
        "items": {
            "type": "integer"
        }
    },
    "olap_sizes": {
        "title": "Olap Sizes",
        "type": "array",
        "items": {
            "type": "integer"
        }
    }
}

```

**field min\_size:** `int` = 128

**field min\_olap:** `int` = 32

**field win\_factor:** `int` = 4

**field olap\_proportion:** `float` = 0.25

**field min\_n\_wins:** `int` = 5

**field win\_sizes:** `List[int] | None` = None

**field olap\_sizes:** `List[int] | None` = None

**run**(*n\_levels*: `int`, *dec\_fs*: `List[float]`) → *WindowParameters*

Calculate window and overlap sizes for each decimation level based on decimation level sampling frequency and minimum allowable parameters

The window and overlap sizes (number of samples) are calculated based in the following way:

- window size = frequency at decimation level / window factor
- overlap size = window size \* overlap proportion

This is to ensure good frequency resolution at high frequencies. At low sampling frequencies, this would result in very small window sizes, therefore, there a minimum allowable sizes for both windows and overlap defined by `min_size` and `min_olap` in the initialiser. If window sizes or overlaps size are calculated below these respectively, they will be set to the minimum values.

**Parameters**

- **n\_levels** (*int*) – The number of decimation levels
- **dec\_fs** (*List[float]*) – The sampling frequencies for each decimation level

**Returns**

The window parameters, the window sizes and overlaps for each decimation level

**Return type**

*WindowParameters*

**Raises**

- **ValueError** – If the number of windows does not match the number of levels
- **ValueError** – If the number of overlaps does not match the number of levels
- **ValueError** – If any of the overlaps are bigger than the window sizes

**pydantic model** `resistics.window.WindowedLevelMetadata`

Bases: *Metadata*

Metadata for a windowed level

```
{
  "title": "WindowedLevelMetadata",
  "description": "Metadata for a windowed level",
  "type": "object",
  "properties": {
    "fs": {
      "title": "Fs",
      "type": "number"
    },
    "n_wins": {
      "title": "N Wins",
      "type": "integer"
    },
    "win_size": {
      "title": "Win Size",
      "exclusiveMinimum": 0,
      "type": "integer"
    },
    "olap_size": {
      "title": "Olap Size",
      "exclusiveMinimum": 0,
      "type": "integer"
    },
    "index_offset": {
      "title": "Index Offset",
      "type": "integer"
    }
  },
  "required": [
    "fs",
    "n_wins",
    "win_size",
    "olap_size",
```

(continues on next page)

(continued from previous page)

```

    "index_offset"
]
}

```

**field fs:** `float` [Required]

The sampling frequency for the decimation level

**field n\_wins:** `int` [Required]

The number of windows

**field win\_size:** `PositiveInt` [Required]

The window size in samples

#### Constraints

- `exclusiveMinimum` = 0

**field olap\_size:** `PositiveInt` [Required]

The overlap size in samples

#### Constraints

- `exclusiveMinimum` = 0

**field index\_offset:** `int` [Required]

The global window offset for local window 0

**property dt**

**pydantic model** `resistics.window.WindowedMetadata`

Bases: `WriteableMetadata`

Metadata for windowed data

```

{
  "title": "WindowedMetadata",
  "description": "Metadata for windowed data",
  "type": "object",
  "properties": {
    "file_info": {
      "$ref": "#/definitions/ResisticsFile"
    },
    "fs": {
      "title": "Fs",
      "type": "array",
      "items": {
        "type": "number"
      }
    },
    "chans": {
      "title": "Chans",
      "type": "array",
      "items": {
        "type": "string"
      }
    }
  },
}

```

(continues on next page)

(continued from previous page)

```

    "n_chans": {
      "title": "N Chans",
      "type": "integer"
    },
    "n_levels": {
      "title": "N Levels",
      "type": "integer"
    },
    "first_time": {
      "title": "First Time",
      "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
      "examples": [
        "2021-01-01 00:00:00.000061_035156_250000_000000"
      ]
    },
    "last_time": {
      "title": "Last Time",
      "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
      "examples": [
        "2021-01-01 00:00:00.000061_035156_250000_000000"
      ]
    },
    "system": {
      "title": "System",
      "default": "",
      "type": "string"
    },
    "serial": {
      "title": "Serial",
      "default": "",
      "type": "string"
    },
    "wgs84_latitude": {
      "title": "Wgs84 Latitude",
      "default": -999.0,
      "type": "number"
    },
    "wgs84_longitude": {
      "title": "Wgs84 Longitude",
      "default": -999.0,
      "type": "number"
    },
    "easting": {
      "title": "Easting",
      "default": -999.0,
      "type": "number"
    },
    "northing": {
      "title": "Northing",
      "default": -999.0,
      "type": "number"
    },
  },

```

(continues on next page)

(continued from previous page)

```

    "elevation": {
      "title": "Elevation",
      "default": -999.0,
      "type": "number"
    },
    "chans_metadata": {
      "title": "Chans Metadata",
      "type": "object",
      "additionalProperties": {
        "$ref": "#/definitions/ChanMetadata"
      }
    },
    "levels_metadata": {
      "title": "Levels Metadata",
      "type": "array",
      "items": {
        "$ref": "#/definitions/WindowedLevelMetadata"
      }
    },
    "ref_time": {
      "title": "Ref Time",
      "pattern": "%Y-%m-%d %H:%M:%S.%f_%o_%q_%v",
      "examples": [
        "2021-01-01 00:00:00.000061_035156_250000_000000"
      ]
    },
    "history": {
      "title": "History",
      "default": {
        "records": []
      },
      "allOf": [
        {
          "$ref": "#/definitions/History"
        }
      ]
    }
  },
  "required": [
    "fs",
    "chans",
    "n_levels",
    "first_time",
    "last_time",
    "chans_metadata",
    "levels_metadata",
    "ref_time"
  ],
  "definitions": {
    "ResisticsFile": {
      "title": "ResisticsFile",
      "description": "Required information for writing out a resistics file",

```

(continues on next page)

(continued from previous page)

```
"type": "object",
"properties": {
  "created_on_local": {
    "title": "Created On Local",
    "type": "string",
    "format": "date-time"
  },
  "created_on_utc": {
    "title": "Created On Utc",
    "type": "string",
    "format": "date-time"
  },
  "version": {
    "title": "Version",
    "type": "string"
  }
},
"ChanMetadata": {
  "title": "ChanMetadata",
  "description": "Channel metadata",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "data_files": {
      "title": "Data Files",
      "type": "array",
      "items": {
        "type": "string"
      }
    },
    "chan_type": {
      "title": "Chan Type",
      "type": "string"
    },
    "chan_source": {
      "title": "Chan Source",
      "type": "string"
    },
    "sensor": {
      "title": "Sensor",
      "default": "",
      "type": "string"
    },
    "serial": {
      "title": "Serial",
      "default": "",
      "type": "string"
    }
  },

```

(continues on next page)



(continued from previous page)

```

    "gain1": {
      "title": "Gain1",
      "default": 1,
      "type": "number"
    },
    "gain2": {
      "title": "Gain2",
      "default": 1,
      "type": "number"
    },
    "scaling": {
      "title": "Scaling",
      "default": 1,
      "type": "number"
    },
    "chopper": {
      "title": "Chopper",
      "default": false,
      "type": "boolean"
    },
    "dipole_dist": {
      "title": "Dipole Dist",
      "default": 1,
      "type": "number"
    },
    "sensor_calibration_file": {
      "title": "Sensor Calibration File",
      "default": "",
      "type": "string"
    },
    "instrument_calibration_file": {
      "title": "Instrument Calibration File",
      "default": "",
      "type": "string"
    }
  },
  "required": [
    "name"
  ]
},
"WindowedLevelMetadata": {
  "title": "WindowedLevelMetadata",
  "description": "Metadata for a windowed level",
  "type": "object",
  "properties": {
    "fs": {
      "title": "Fs",
      "type": "number"
    },
    "n_wins": {
      "title": "N Wins",
      "type": "integer"
    }
  }
}

```

(continues on next page)

(continued from previous page)

```

    },
    "win_size": {
        "title": "Win Size",
        "exclusiveMinimum": 0,
        "type": "integer"
    },
    "olap_size": {
        "title": "Olap Size",
        "exclusiveMinimum": 0,
        "type": "integer"
    },
    "index_offset": {
        "title": "Index Offset",
        "type": "integer"
    }
},
"required": [
    "fs",
    "n_wins",
    "win_size",
    "olap_size",
    "index_offset"
]
},
"Record": {
    "title": "Record",
    "description": "Class to hold a record\n\nA record holds information about,
↪ a process that was run. It is intended to\ntrack processes applied to data,
↪ allowing a process history to be saved\nalong with any datasets.\n\nExamples\n----
↪ ----\nA simple example of creating a process record\n\n>>> from resistics.common
↪ import Record\n>>> messages = ["message 1", "message 2"]\n>>> record =
↪ Record(\n...     creator={"name": "example", "parameter1": 15},\n...     _
↪ messages=messages,\n...     record_type="example"\n... )\n>>> record.summary()\n
↪ {\n    'time_local': '...',\n    'time_utc': '...',\n    'creator': {'name':
↪ 'example', 'parameter1': 15},\n    'messages': ['message 1', 'message 2'],\n
↪ 'record_type': 'example'\n}",
    "type": "object",
    "properties": {
        "time_local": {
            "title": "Time Local",
            "type": "string",
            "format": "date-time"
        },
        "time_utc": {
            "title": "Time Utc",
            "type": "string",
            "format": "date-time"
        },
        "creator": {
            "title": "Creator",
            "type": "object"
        }
    }
},

```

(continues on next page)

(continued from previous page)

```

        "messages": {
            "title": "Messages",
            "type": "array",
            "items": {
                "type": "string"
            }
        },
        "record_type": {
            "title": "Record Type",
            "type": "string"
        }
    },
    "required": [
        "creator",
        "messages",
        "record_type"
    ]
},
"History": {
    "title": "History",
    "description": "Class for storing processing history\n\nParameters\n-----
↪----\nrecords : List[Record], optional\n    List of records, by default []\n\
↪nExamples\n-----\n>>> from resistics.testing import record_example1, record_
↪example2\n>>> from resistics.common import History\n>>> record1 = record_
↪example1()\n>>> record2 = record_example2()\n>>> history =
↪History(records=[record1, record2])\n>>> history.summary()\n{\n    'records': [\n
↪    {\n        'time_local': '...',\n        'time_utc': '...',\n
↪    'creator': {\n        'name': 'example1',\n        'a': 5,\n
↪    'b': -7.0\n    },\n        'messages': ['Message 1',
↪'Message 2'],\n        'record_type': 'process'\n    },\n    {\n
↪    'time_local': '...',\n        'time_utc': '...',\n        'creator
↪': {\n        'name': 'example2',\n        'a': 'parzen',\n
↪    'b': -21\n    },\n        'messages': ['Message 5', 'Message
↪6'],\n        'record_type': 'process'\n    }\n    ]\n}",
    "type": "object",
    "properties": {
        "records": {
            "title": "Records",
            "default": [],
            "type": "array",
            "items": {
                "$ref": "#/definitions/Record"
            }
        }
    }
}
}
}
}
}

```

field fs: List[float] [Required]

field chans: List[str] [Required]

field `n_chans`: `int` | `None` = `None`

Validated by

- `validate_n_chans`

field `n_levels`: `int` [Required]

field `first_time`: `HighResDateTime` [Required]

Constraints

- `pattern` = `%Y-%m-%d %H:%M:%S.%f_%o_%q_%v`
- `examples` = [`'2021-01-01 00:00:00.000061_035156_250000_000000'`]

field `last_time`: `HighResDateTime` [Required]

Constraints

- `pattern` = `%Y-%m-%d %H:%M:%S.%f_%o_%q_%v`
- `examples` = [`'2021-01-01 00:00:00.000061_035156_250000_000000'`]

field `system`: `str` = `''`

field `serial`: `str` = `''`

field `wgs84_latitude`: `float` = `-999.0`

field `wgs84_longitude`: `float` = `-999.0`

field `easting`: `float` = `-999.0`

field `northing`: `float` = `-999.0`

field `elevation`: `float` = `-999.0`

field `chans_metadata`: `Dict[str, ChanMetadata]` [Required]

field `levels_metadata`: `List[WindowedLevelMetadata]` [Required]

field `ref_time`: `HighResDateTime` [Required]

Constraints

- `pattern` = `%Y-%m-%d %H:%M:%S.%f_%o_%q_%v`
- `examples` = [`'2021-01-01 00:00:00.000061_035156_250000_000000'`]

field `history`: `History` = `History(records=[])`

**class** `resisticks.window.WindowedData(metadata: WindowedMetadata, data: Dict[int, ndarray])`

Bases: `ResisticksData`

Windows of a `DecimatedData` object

The windowed data is stored in a dictionary attribute named `data`. This is a dictionary with an entry for each decimation level. The shape for a single decimation level is as follows:

`n_wins x n_chans x n_samples`

**get\_level**(*level: int*) → ndarray

Get windows for a decimation level

**Parameters**

**level** (*int*) – The decimation level

**Returns**

The window array

**Return type**

np.ndarray

**Raises**

**ValueError** – If decimation level is not within range

**get\_local**(*level: int, local\_win: int*) → ndarray

Get window using local index

**Parameters**

- **level** (*int*) – The decimation level
- **local\_win** (*int*) – Local window index

**Returns**

Window data

**Return type**

np.ndarray

**Raises**

**ValueError** – If local window index is out of range

**get\_global**(*level: int, global\_win: int*) → ndarray

Get window using global index

**Parameters**

- **level** (*int*) – The decimation level
- **global\_win** (*int*) – Global window index

**Returns**

Window data

**Return type**

np.ndarray

**get\_chan**(*level: int, chan: str*) → ndarray

Get all the windows for a channel

**Parameters**

- **level** (*int*) – The decimation level
- **chan** (*str*) – The channel

**Returns**

The data for the channels

**Return type**

np.ndarray

**Raises**

**ChannelNotFoundError** – If the channel is not found in the data

`to_string()` → `str`

Class information as a string

**pydantic model** `resisticks.window.Windower`

Bases: `ResisticksProcess`

Windows DecimatedData

This is the primary window making process for resisticks and should be used when alignment of windows with a site or across sites is required.

This method uses numpy striding to produce window views into the decimated data.

**See also:**

**`WindowerTarget`**

A windower to make a target number of windows

## Examples

The Windower windows a DecimatedData object given a reference time and some window parameters.

There's quite a few imports needed for this example. Begin by doing the imports, defining a reference time and generating random decimated data.

```
>>> from resisticks.sampling import to_datetime
>>> from resisticks.testing import decimated_data_linear
>>> from resisticks.window import WindowSetup, Windower
>>> dec_data = decimated_data_linear(fs=128)
>>> ref_time = dec_data.metadata.first_time
>>> print(dec_data.to_string())
<class 'resisticks.decimate.DecimatedData'>
           fs           dt  n_samples           first_time           last_
↪time
level
0      2048.0  0.000488      16384  2021-01-01 00:00:00  2021-01-01 00:00:07.
↪99951171875
1       512.0  0.001953       4096  2021-01-01 00:00:00  2021-01-01 00:00:07.
↪998046875
2       128.0  0.007812       1024  2021-01-01 00:00:00  2021-01-01 00:00:07.
↪9921875
```

Next, initialise the window parameters. For this example, use small windows, which will make inspecting them easier.

```
>>> win_params = WindowSetup(win_sizes=[16,16,16], min_olap=4).run(dec_data.
↪metadata.n_levels, dec_data.metadata.fs)
>>> win_params.summary()
{
  'n_levels': 3,
  'min_n_wins': 5,
  'win_sizes': [16, 16, 16],
  'olap_sizes': [4, 4, 4]
}
```

Perform the windowing. This actually creates views into the decimated data using the `numpy.lib.stride_tricks.sliding_window_view` function. The shape for a data array at a decimation level is: `n_wins x n_chans x win_size`. The information about each level is also in the `levels_metadata` attribute of `WindowedMetadata`.

```
>>> win_data = Windower().run(ref_time, win_params, dec_data)
>>> win_data.data[0].shape
(1365, 2, 16)
>>> for level_metadata in win_data.metadata.levels_metadata:
...     level_metadata.summary()
{
  'fs': 2048.0,
  'n_wins': 1365,
  'win_size': 16,
  'olap_size': 4,
  'index_offset': 0
}
{
  'fs': 512.0,
  'n_wins': 341,
  'win_size': 16,
  'olap_size': 4,
  'index_offset': 0
}
{
  'fs': 128.0,
  'n_wins': 85,
  'win_size': 16,
  'olap_size': 4,
  'index_offset': 0
}
```

Let's look at an example of data from the first decimation level for the first channel. This is simply a linear set of data ranging from 0...16\_383.

```
>>> dec_data.data[0][0]
array([ 0, 1, 2, ..., 16381, 16382, 16383])
```

Inspecting the first few windows shows they are as expected including the overlap.

```
>>> win_data.data[0][0, 0]
array([ 0, 1, 2, 3, 4, 5, 6, 7, 8, 9, 10, 11, 12, 13, 14, 15])
>>> win_data.data[0][1, 0]
array([12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27])
>>> win_data.data[0][2, 0]
array([24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37, 38, 39])
```

```
{
  "title": "Windower",
  "description": "Windows DecimatedData\n\nThis is the primary window making_
↳ process for resistics and should be used\nwhen alignment of windows with a site_
↳ or across sites is required.\n\nThis method uses numpy striding to produce window_
↳ views into the decimated\ndata.\n\nSee Also\n-----\nWindowerTarget : A_
```

(continues on next page)

(continued from previous page)

```

→windower to make a target number of windows\n\nExamples\n-----\n\nThe Windower.
→windows a DecimatedData object given a reference time and some\nwindow parameters.
→\n\nThere's quite a few imports needed for this example. Begin by doing the\
→\n\nfrom resistics.sampling import to_datetime\n>>> from resistics.testing import
→decimated_data_linear\n>>> from resistics.window import WindowSetup, Windower\n>>>
→ dec_data = decimated_data_linear(fs=128)\n>>> ref_time = dec_data.metadata.first_
→time\n>>> print(dec_data.to_string())\n<class 'resistics.decimate.DecimatedData'\n
→n      fs      dt  n_samples      first_time
→last_time\nlevel\n0      2048.0  0.000488      16384  2021-01-01 00:00:00  2021-
→01-01 00:00:07.99951171875\n1      512.0  0.001953      4096  2021-01-01
→00:00:00      2021-01-01 00:00:07.998046875\n2      128.0  0.007812      1024
→2021-01-01 00:00:00      2021-01-01 00:00:07.9921875\n\nNext, initialise the
→window parameters. For this example, use small windows,\nwhich will make
→inspecting them easier.\n>>> win_params = WindowSetup(win_sizes=[16,16,16], min_
→olap=4).run(dec_data.metadata.n_levels, dec_data.metadata.fs)\n>>> win_params.
→summary()\n{\n  'n_levels': 3,\n  'min_n_wins': 5,\n  'win_sizes': [16, 16,
→16],\n  'olap_sizes': [4, 4, 4]\n}\n\nPerform the windowing. This actually
→creates views into the decimated data\nusing the numpy.lib.stride_tricks.sliding_
→window_view function. The shape\nfor a data array at a decimation level is: n_
→wins x n_chans x win_size. The\ninformation about each level is also in the
→levels_metadata attribute of\nWindowedMetadata.\n>>> win_data = Windower().
→run(ref_time, win_params, dec_data)\n>>> win_data.data[0].shape\n(1365, 2, 16)\n>>
→> for level_metadata in win_data.metadata.levels_metadata:\n...   level_
→metadata.summary()\n{\n  'fs': 2048.0,\n  'n_wins': 1365,\n  'win_size': 16,
→\n  'olap_size': 4,\n  'index_offset': 0\n}\n{\n  'fs': 512.0,\n  'n_wins
→': 341,\n  'win_size': 16,\n  'olap_size': 4,\n  'index_offset': 0\n}\n{\n
→'fs': 128.0,\n  'n_wins': 85,\n  'win_size': 16,\n  'olap_size': 4,\n
→'index_offset': 0\n}\n\nLet's look at an example of data from the first
→decimation level for the\nfirst channel. This is simply a linear set of data
→ranging from 0...16_383.\n>>> dec_data.data[0][0]\narray([  0,   1,   2, .
→..., 16381, 16382, 16383])\n\nInspecting the first few windows shows they are as
→expected including the\noverlap.\n>>> win_data.data[0][0, 0]\narray([ 0,  1,  2,
→  3,  4,  5,  6,  7,  8,  9, 10, 11, 12, 13, 14, 15])\n>>> win_data.data[0][1, 0]\
→narray([12, 13, 14, 15, 16, 17, 18, 19, 20, 21, 22, 23, 24, 25, 26, 27])\n>>> win_
→data.data[0][2, 0]\narray([24, 25, 26, 27, 28, 29, 30, 31, 32, 33, 34, 35, 36, 37,
→38, 39])",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    }
  }
}

```

**run**(*ref\_time*: *attodatetime*, *win\_params*: *WindowParameters*, *dec\_data*: *DecimatedData*) → *WindowedData*  
 Perform windowing of DecimatedData

#### Parameters

- **ref\_time** (*RSDateTime*) – The reference time
- **win\_params** (*WindowParameters*) – The window parameters



- **dec\_data** ([DecimatedData](#)) – The decimated data

**Returns**

Windows for decimated data

**Return type**

[WindowedData](#)

**Raises**

[ProcessRunError](#) – If the number of windows calculated in the window table does not match the size of the array views

**pydantic model** `resistics.window.WindowerTarget`

Bases: [Windower](#)

Windower that selects window sizes to meet a target number of windows

The minimum window size in window parameters will be respected even if the generated number of windows is below the target. This is to avoid situations where excessively small windows sizes are selected.

**Warning:** This process is primarily useful for quick processing of a single measurement and should not be used when any alignment of windows is required within a site or across sites.

**Parameters**

- **target** ([int](#)) – The target number of windows for each decimation level
- **olap\_proportion** ([float](#)) – The overlap proportion of the window size

See also:

[Windower](#)

The window making process to use when alignment is required

```
{
  "title": "WindowerTarget",
  "description": "Windower that selects window sizes to meet a target number of_
↪ windows\n\nThe minimum window size in window parameters will be respected even if_
↪ the\ngenerated number of windows is below the target. This is to avoid situations\
↪ nwhere excessively small windows sizes are selected.\n\n.. warning::\n\n    This_
↪ process is primarily useful for quick processing of a single\n    measurement and_
↪ should not be used when any alignment of windows is\n    required within a site_
↪ or across sites.\n\nParameters\n-----\nntarget : int\n    The target number_
↪ of windows for each decimation level\nolap_proportion : float\n    The overlap_
↪ proportion of the window size\n\nSee Also\n-----\nWindower : The window making_
↪ process to use when alignment is required",
  "type": "object",
  "properties": {
    "name": {
      "title": "Name",
      "type": "string"
    },
    "target": {
      "title": "Target",
      "default": 1000,
```

(continues on next page)

(continued from previous page)

```

        "type": "integer"
    },
    "min_size": {
        "title": "Min Size",
        "default": 64,
        "type": "integer"
    },
    "olap_proportion": {
        "title": "Olap Proportion",
        "default": 0.25,
        "type": "number"
    }
}

```

**field target:** `int = 1000`

**field min\_size:** `int = 64`

**field olap\_proportion:** `float = 0.25`

**run**(*ref\_time*: *attodatetime*, *win\_params*: *WindowParameters*, *dec\_data*: *DecimatedData*) → *WindowedData*

Perform windowing of DecimatedData

#### Parameters

- **ref\_time** (*RSDatetime*) – The reference time
- **win\_params** (*WindowParameters*) – The window parameters
- **dec\_data** (*DecimatedData*) – The decimated data

#### Returns

Windows for decimated data

#### Return type

*WindowedData*

#### Raises

***ProcessRunError*** – If the number of windows calculated in the window table does not match the size of the array views

**pydantic model** `resistics.window.WindowedDataWriter`

Bases: *ResisticsWriter*

Writer of resistics windowed data

```

{
    "title": "WindowedDataWriter",
    "description": "Writer of resistics windowed data",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        },
    },
    "overwrite": {

```

(continues on next page)

(continued from previous page)

```

        "title": "Overwrite",
        "default": true,
        "type": "boolean"
    }
}

```

**run**(*dir\_path*: *Path*, *win\_data*: *WindowedData*) → *None*

Write out *WindowedData*

#### Parameters

- **dir\_path** (*Path*) – The directory path to write to
- **win\_data** (*WindowedData*) – *Windowed data* to write out

#### Raises

**WriteError** – If unable to write to the directory

**pydantic model** *resistics.window.WindowedReader*

Bases: *ResisticsProcess*

Reader of *resistics windowed data*

```

{
    "title": "WindowedReader",
    "description": "Reader of resistics windowed data",
    "type": "object",
    "properties": {
        "name": {
            "title": "Name",
            "type": "string"
        }
    }
}

```

**run**(*dir\_path*: *Path*, *metadata\_only*: *bool* = *False*) → *WindowedMetadata* | *WindowedData*

Read *WindowedData*

#### Parameters

- **dir\_path** (*Path*) – The directory path to read from
- **metadata\_only** (*bool*, *optional*) – Flag for getting metadata only, by default *False*

#### Returns

The *WindowedData* or *WindowedMetadata* if *metadata\_only* is *True*

#### Return type

Union[*WindowedMetadata*, *WindowedData*]

#### Raises

**ReadError** – If the directory does not exist

### **4.3.2 Module contents**

A package for the processing of magnetotelluric data

Resistics is a package for the robust processing of magnetotelluric data. It includes several features focussed on traceability and data investigation. For more information, visit the package website at: [www.resistics.io](http://www.resistics.io)

## **4.4 Literature references**

**INDEX**

- genindex
- modindex
- search



## BIBLIOGRAPHY

- [Jones2009] Area selection for diamonds using magnetotellurics: Examples from southern Africa. Jones et al. (2009). *Lithos*, 112S, 83-92. doi: 10.1016/j.lithos.2009.06.011





## PYTHON MODULE INDEX

### r

- `resisticks`, [408](#)
- `resisticks.calibrate`, [90](#)
- `resisticks.common`, [101](#)
- `resisticks.config`, [117](#)
- `resisticks.decimate`, [135](#)
- `resisticks.errors`, [155](#)
- `resisticks.gather`, [157](#)
- `resisticks.letsgo`, [168](#)
- `resisticks.plot`, [201](#)
- `resisticks.project`, [203](#)
- `resisticks.regression`, [230](#)
- `resisticks.sampling`, [262](#)
- `resisticks.spectra`, [275](#)
- `resisticks.testing`, [297](#)
- `resisticks.time`, [306](#)
- `resisticks.transfunc`, [361](#)
- `resisticks.window`, [373](#)



## A

add (*resisticks.time.Add* attribute), 339  
 add\_record() (*resisticks.common.History* method), 112  
 adjust\_time\_metadata() (in module *resisticks.time*), 318  
 any\_electric() (*resisticks.time.TimeMetadata* method), 316  
 any\_magnetic() (*resisticks.time.TimeMetadata* method), 316  
 apply\_lttb() (in module *resisticks.plot*), 201  
 apply\_scalings (*resisticks.time.TimeReader* attribute), 322  
 array\_to\_string() (in module *resisticks.common*), 105  
 assert\_dir() (in module *resisticks.common*), 102  
 assert\_file() (in module *resisticks.common*), 102  
 assert\_soln\_equal() (in module *resisticks.testing*), 306  
 assert\_time\_data\_equal() (in module *resisticks.testing*), 305

## B

band (*resisticks.time.Notch* attribute), 349  
 begin\_time (*resisticks.project.Project* attribute), 229  
 begin\_time (*resisticks.project.Site* attribute), 217  
 bisquare() (*resisticks.regression.SolverScikitWLS* method), 261

## C

CalibrationFileNotFound, 157  
 CalibrationFileReadError, 157  
 chan\_source (*resisticks.time.ChanMetadata* attribute), 308  
 chan\_type (*resisticks.time.ChanMetadata* attribute), 308  
 ChannelNotFoundError, 156  
 chans (*resisticks.calibrate.Calibrator* attribute), 99  
 chans (*resisticks.decimate.DecimatedMetadata* attribute), 150  
 chans (*resisticks.gather.SiteCombinedMetadata* attribute), 165  
 chans (*resisticks.spectra.SpectraMetadata* attribute), 283  
 chans (*resisticks.time.TimeMetadata* attribute), 314  
 chans (*resisticks.window.WindowedMetadata* attribute), 399

chans\_metadata (*resisticks.decimate.DecimatedMetadata* attribute), 151  
 chans\_metadata (*resisticks.spectra.SpectraMetadata* attribute), 284  
 chans\_metadata (*resisticks.time.TimeMetadata* attribute), 315  
 chans\_metadata (*resisticks.window.WindowedMetadata* attribute), 400  
 check\_chan() (in module *resisticks.common*), 105  
 check\_eval\_idx() (*resisticks.decimate.DecimationParameters* method), 139  
 check\_from\_time() (in module *resisticks.sampling*), 269  
 check\_level() (*resisticks.decimate.DecimationParameters* method), 139  
 check\_level() (*resisticks.window.WindowParameters* method), 387  
 check\_sample() (in module *resisticks.sampling*), 267  
 check\_to\_time() (in module *resisticks.sampling*), 270  
 chopper (*resisticks.time.ChanMetadata* attribute), 308  
 components (*resisticks.regression.Solution* attribute), 255  
 components\_mt() (in module *resisticks.testing*), 304  
 config (*resisticks.letsgo.ResisticksEnvironment* attribute), 195  
 contributors (*resisticks.project.ProjectMetadata* attribute), 220  
 contributors (*resisticks.regression.RegressionInputMetadata* attribute), 240  
 contributors (*resisticks.regression.Solution* attribute), 255  
 copy() (*resisticks.time.TimeData* method), 321  
 country (*resisticks.project.ProjectMetadata* attribute), 220  
 created\_on\_local (*resisticks.common.ResisticksFile* attribute), 107  
 created\_on\_utc (*resisticks.common.ResisticksFile* attribute), 107  
 creator (*resisticks.common.Record* attribute), 109  
 cross\_chans (*resisticks.transfunc.TransferFunction* attribute), 365

cutoff (*resisticks.time.HighPass* attribute), 345  
cutoff (*resisticks.time.LowPass* attribute), 343  
cutoff\_high (*resisticks.time.BandPass* attribute), 347  
cutoff\_low (*resisticks.time.BandPass* attribute), 347

## D

data\_files (*resisticks.time.ChanMetadata* attribute), 308  
datetime\_array() (in module *resisticks.sampling*), 273  
datetime\_array\_estimate() (in module *resisticks.sampling*), 274  
datetime\_from\_string() (in module *resisticks.sampling*), 263  
datetime\_to\_string() (in module *resisticks.sampling*), 262  
datetime\_to\_win() (in module *resisticks.window*), 378  
datetimes\_to\_samples() (in module *resisticks.sampling*), 272  
dec\_factors (*resisticks.decimate.DecimationParameters* attribute), 139  
dec\_fs (*resisticks.decimate.DecimationParameters* attribute), 139  
dec\_increments (*resisticks.decimate.DecimationParameters* attribute), 139  
dec\_setup (*resisticks.config.Configuration* attribute), 134  
decimated\_data\_linear() (in module *resisticks.testing*), 301  
decimated\_data\_periodic() (in module *resisticks.testing*), 302  
decimated\_data\_random() (in module *resisticks.testing*), 301  
decimated\_metadata() (in module *resisticks.testing*), 300  
DecimatedData (class in *resisticks.decimate*), 151  
decimator (*resisticks.config.Configuration* attribute), 134  
delimiter (*resisticks.time.TimeReaderAscii* attribute), 325  
description (*resisticks.project.ProjectMetadata* attribute), 220  
detrend (*resisticks.spectra.FourierTransform* attribute), 289  
dipole\_dist (*resisticks.time.ChanMetadata* attribute), 308  
dir\_contents() (in module *resisticks.common*), 102  
dir\_files() (in module *resisticks.common*), 102  
dir\_path (*resisticks.letsgo.ProjectCreator* attribute), 170  
dir\_path (*resisticks.letsgo.ProjectLoader* attribute), 171  
dir\_path (*resisticks.project.Measurement* attribute), 210  
dir\_path (*resisticks.project.Project* attribute), 229  
dir\_path (*resisticks.project.Site* attribute), 217  
dir\_subdirs() (in module *resisticks.common*), 103  
div\_factor (*resisticks.decimate.DecimationSetup* attribute), 142

dt (*resisticks.decimate.DecimatedLevelMetadata* property), 144  
dt (*resisticks.time.TimeMetadata* property), 315  
dt (*resisticks.window.WindowedLevelMetadata* property), 393  
duration (*resisticks.time.TimeMetadata* property), 315

## E

easting (*resisticks.decimate.DecimatedMetadata* attribute), 150  
easting (*resisticks.gather.SiteCombinedMetadata* attribute), 165  
easting (*resisticks.spectra.SpectraMetadata* attribute), 283  
easting (*resisticks.time.TimeMetadata* attribute), 315  
easting (*resisticks.window.WindowedMetadata* attribute), 400  
electric() (*resisticks.time.ChanMetadata* method), 308  
elevation (*resisticks.decimate.DecimatedMetadata* attribute), 151  
elevation (*resisticks.gather.SiteCombinedMetadata* attribute), 165  
elevation (*resisticks.spectra.SpectraMetadata* attribute), 283  
elevation (*resisticks.time.TimeMetadata* attribute), 315  
elevation (*resisticks.window.WindowedMetadata* attribute), 400  
end\_time (*resisticks.project.Project* attribute), 229  
end\_time (*resisticks.project.Site* attribute), 217  
epsilon (*resisticks.regression.SolverScikitHuber* attribute), 258  
eval\_freqs (*resisticks.decimate.DecimationParameters* attribute), 139  
eval\_freqs (*resisticks.decimate.DecimationSetup* attribute), 142  
eval\_freqs (*resisticks.gather.SiteCombinedMetadata* attribute), 166  
evals (*resisticks.config.Configuration* attribute), 135  
evaluation\_data() (in module *resisticks.testing*), 303  
extension (*resisticks.calibrate.CalibrationReader* attribute), 94  
extension (*resisticks.calibrate.SensorCalibration.JSON* attribute), 97  
extension (*resisticks.time.TimeReader* attribute), 322  
extension (*resisticks.time.TimeReaderAscii* attribute), 325  
extension (*resisticks.time.TimeReaderNumpy* attribute), 326

## F

factor (*resisticks.time.Decimate* attribute), 354  
file\_info (*resisticks.common.WritableMetadata* attribute), 108

- file\_path (*resistics.calibrate.CalibrationData* attribute), 93  
 file\_str (*resistics.calibrate.SensorCalibrationReader* attribute), 96  
 first\_time (*resistics.decimate.DecimatedLevelMetadata* attribute), 143  
 first\_time (*resistics.decimate.DecimatedMetadata* attribute), 150  
 first\_time (*resistics.spectra.SpectraMetadata* attribute), 283  
 first\_time (*resistics.time.TimeMetadata* attribute), 314  
 first\_time (*resistics.window.WindowedMetadata* attribute), 400  
 fit\_intercept (*resistics.regression.SolverScikit* attribute), 256  
 fncs (*resistics.time.ApplyFunction* attribute), 360  
 fourier (*resistics.config.Configuration* attribute), 135  
 freqs (*resistics.regression.Solution* attribute), 255  
 freqs (*resistics.spectra.SpectraLevelMetadata* attribute), 276  
 frequency (*resistics.calibrate.CalibrationData* attribute), 93  
 from\_sample (*resistics.time.Subsamples* attribute), 335  
 from\_time (*resistics.time.Subsection* attribute), 331  
 from\_time\_to\_sample() (in module *resistics.sampling*), 271  
 fs (*resistics.decimate.DecimatedLevelMetadata* attribute), 143  
 fs (*resistics.decimate.DecimatedMetadata* attribute), 150  
 fs (*resistics.decimate.DecimationParameters* attribute), 139  
 fs (*resistics.gather.SiteCombinedMetadata* attribute), 165  
 fs (*resistics.spectra.SpectraLevelMetadata* attribute), 276  
 fs (*resistics.spectra.SpectraMetadata* attribute), 283  
 fs (*resistics.time.TimeMetadata* attribute), 314  
 fs (*resistics.window.WindowedLevelMetadata* attribute), 393  
 fs (*resistics.window.WindowedMetadata* attribute), 399  
 fs() (*resistics.project.Project* method), 229  
 fs() (*resistics.project.Site* method), 218  
 fs\_to\_string() (in module *resistics.common*), 105
- ## G
- gain1 (*resistics.time.ChanMetadata* attribute), 308  
 gain2 (*resistics.time.ChanMetadata* attribute), 308  
 GatheredData (class in *resistics.gather*), 166  
 generate\_evaluation\_data() (in module *resistics.testing*), 303  
 get\_calibration\_fig() (in module *resistics.plot*), 202  
 get\_calibration\_path() (in module *resistics.project*), 203  
 get\_chan() (*resistics.spectra.SpectraData* method), 284  
 get\_chan() (*resistics.time.TimeData* method), 320  
 get\_chan() (*resistics.window.WindowedData* method), 401  
 get\_chan\_index() (*resistics.time.TimeData* method), 319  
 get\_chan\_type() (in module *resistics.common*), 104  
 get\_chan\_types() (*resistics.time.TimeMetadata* method), 315  
 get\_chans() (*resistics.spectra.SpectraData* method), 284  
 get\_chans\_with\_type() (*resistics.time.TimeMetadata* method), 315  
 get\_component() (*resistics.regression.Solution* method), 255  
 get\_component\_key() (in module *resistics.transfunc*), 362  
 get\_concurrent() (*resistics.project.Project* method), 230  
 get\_default\_configuration() (in module *resistics.config*), 135  
 get\_electric\_chans() (*resistics.time.TimeMetadata* method), 316  
 get\_eval\_freq() (*resistics.decimate.DecimationParameters* method), 140  
 get\_eval\_freqs() (in module *resistics.decimate*), 136  
 get\_eval\_freqs() (*resistics.decimate.DecimationParameters* method), 139  
 get\_eval\_freqs() (*resistics.gather.Selection* method), 160  
 get\_eval\_freqs\_min() (in module *resistics.decimate*), 135  
 get\_eval\_freqs\_size() (in module *resistics.decimate*), 136  
 get\_eval\_wins() (*resistics.gather.Selection* method), 160  
 get\_fig() (*resistics.transfunc.ImpedanceTensor* static method), 370  
 get\_first\_and\_last\_win() (in module *resistics.window*), 380  
 get\_freq() (*resistics.spectra.SpectraData* method), 284  
 get\_fs() (*resistics.decimate.DecimationParameters* method), 140  
 get\_global() (*resistics.window.WindowedData* method), 401  
 get\_history() (in module *resistics.common*), 113  
 get\_imag\_angle() (*resistics.transfunc.Tipper* method), 373  
 get\_incremental\_factor() (*resistics.decimate.DecimationParameters* method), 140  
 get\_inputs() (*resistics.regression.RegressionInputData* method), 241

- [get\\_length\(\)](#) (*resisticks.transfunc.Tipper* method), 373  
[get\\_level\(\)](#) (*resisticks.decimate.DecimatedData* method), 152  
[get\\_level\(\)](#) (*resisticks.spectra.SpectraData* method), 284  
[get\\_level\(\)](#) (*resisticks.window.WindowedData* method), 400  
[get\\_local\(\)](#) (*resisticks.window.WindowedData* method), 401  
[get\\_mag\\_phs\(\)](#) (*resisticks.spectra.SpectraData* method), 284  
[get\\_magnetic\\_chans\(\)](#) (*resisticks.time.TimeMetadata* method), 316  
[get\\_mask\\_name\(\)](#) (in module *resisticks.project*), 203  
[get\\_mask\\_path\(\)](#) (in module *resisticks.project*), 203  
[get\\_meas\\_evals\\_path\(\)](#) (in module *resisticks.project*), 203  
[get\\_meas\\_features\\_path\(\)](#) (in module *resisticks.project*), 203  
[get\\_meas\\_spectra\\_path\(\)](#) (in module *resisticks.project*), 203  
[get\\_meas\\_time\\_path\(\)](#) (in module *resisticks.project*), 203  
[get\\_measurement\(\)](#) (*resisticks.project.Site* method), 218  
[get\\_measurements\(\)](#) (*resisticks.gather.Selection* method), 160  
[get\\_measurements\(\)](#) (*resisticks.project.Site* method), 218  
[get\\_n\\_evals\(\)](#) (*resisticks.gather.Selection* method), 159  
[get\\_n\\_wins\(\)](#) (*resisticks.gather.Selection* method), 159  
[get\\_olap\\_size\(\)](#) (*resisticks.window.WindowParameters* method), 387  
[get\\_phase\(\)](#) (*resisticks.transfunc.ImpedanceTensor* static method), 370  
[get\\_real\\_angle\(\)](#) (*resisticks.transfunc.Tipper* method), 373  
[get\\_record\(\)](#) (in module *resisticks.common*), 112  
[get\\_resistivity\(\)](#) (*resisticks.transfunc.ImpedanceTensor* static method), 369  
[get\\_results\\_path\(\)](#) (in module *resisticks.project*), 203  
[get\\_site\(\)](#) (*resisticks.project.Project* method), 229  
[get\\_site\\_evals\\_metadata\(\)](#) (in module *resisticks.gather*), 157  
[get\\_site\\_level\\_wins\(\)](#) (in module *resisticks.gather*), 158  
[get\\_site\\_wins\(\)](#) (in module *resisticks.gather*), 159  
[get\\_sites\(\)](#) (*resisticks.project.Project* method), 230  
[get\\_solution\(\)](#) (in module *resisticks.letsgo*), 201  
[get\\_solution\\_name\(\)](#) (in module *resisticks.project*), 203  
[get\\_spectra\\_section\\_fig\(\)](#) (in module *resisticks.plot*), 202  
[get\\_spectra\\_stack\\_fig\(\)](#) (in module *resisticks.plot*), 202  
[get\\_tensor\(\)](#) (*resisticks.regression.Solution* method), 255  
[get\\_time\\_fig\(\)](#) (in module *resisticks.plot*), 202  
[get\\_time\\_metadata\(\)](#) (in module *resisticks.time*), 316  
[get\\_timestamps\(\)](#) (*resisticks.decimate.DecimatedData* method), 152  
[get\\_timestamps\(\)](#) (*resisticks.spectra.SpectraData* method), 284  
[get\\_timestamps\(\)](#) (*resisticks.time.TimeData* method), 320  
[get\\_total\\_factor\(\)](#) (*resisticks.decimate.DecimationParameters* method), 140  
[get\\_value\(\)](#) (*resisticks.transfunc.Component* method), 361  
[get\\_version\(\)](#) (in module *resisticks.common*), 101  
[get\\_win\\_ends\(\)](#) (in module *resisticks.window*), 382  
[get\\_win\\_size\(\)](#) (*resisticks.window.WindowParameters* method), 387  
[get\\_win\\_starts\(\)](#) (in module *resisticks.window*), 382  
[get\\_win\\_table\(\)](#) (in module *resisticks.window*), 383
- ## H
- [HighResDateTime](#) (class in *resisticks.sampling*), 262  
[histories](#) (*resisticks.gather.SiteCombinedMetadata* attribute), 166  
[history](#) (*resisticks.decimate.DecimatedMetadata* attribute), 151  
[history](#) (*resisticks.regression.RegressionInputMetadata* attribute), 240  
[history](#) (*resisticks.regression.Solution* attribute), 255  
[history](#) (*resisticks.spectra.SpectraMetadata* attribute), 284  
[history](#) (*resisticks.time.TimeMetadata* attribute), 315  
[history](#) (*resisticks.window.WindowedMetadata* attribute), 400  
[history\\_example\(\)](#) (in module *resisticks.testing*), 297  
[huber\(\)](#) (*resisticks.regression.SolverScikitWLS* method), 261
- ## I
- [imag](#) (*resisticks.transfunc.Component* attribute), 361  
[in\\_chans](#) (*resisticks.transfunc.ImpedanceTensor* attribute), 369  
[in\\_chans](#) (*resisticks.transfunc.Tipper* attribute), 373  
[in\\_chans](#) (*resisticks.transfunc.TransferFunction* attribute), 365  
[inc\\_duration\(\)](#) (in module *resisticks.window*), 377  
[index\\_offset](#) (*resisticks.spectra.SpectraLevelMetadata* attribute), 276  
[index\\_offset](#) (*resisticks.window.WindowedLevelMetadata* attribute), 393



- instrument\_calibration\_file (resistics.time.ChanMetadata attribute), 308
- is\_dir() (in module resistics.common), 102
- is\_electric() (in module resistics.common), 103
- is\_file() (in module resistics.common), 101
- is\_magnetic() (in module resistics.common), 104
- ## K
- known\_chan() (in module resistics.common), 103
- ## L
- last\_time (resistics.decimate.DecimatedLevelMetadata attribute), 143
- last\_time (resistics.decimate.DecimatedMetadata attribute), 150
- last\_time (resistics.spectra.SpectraMetadata attribute), 283
- last\_time (resistics.time.TimeMetadata attribute), 314
- last\_time (resistics.window.WindowedMetadata attribute), 400
- length\_proportion (resistics.spectra.SpectraSmootherUniform attribute), 295
- levels\_metadata (resistics.decimate.DecimatedMetadata attribute), 151
- levels\_metadata (resistics.spectra.SpectraMetadata attribute), 284
- levels\_metadata (resistics.window.WindowedMetadata attribute), 400
- load() (in module resistics.letsgo), 195
- location (resistics.project.ProjectMetadata attribute), 220
- ltnb\_downsample() (in module resistics.plot), 201
- ## M
- magnetic() (resistics.time.ChanMetadata method), 308
- magnitude (resistics.calibrate.CalibrationData attribute), 93
- magnitude\_unit (resistics.calibrate.CalibrationData attribute), 93
- max\_single\_factor (resistics.decimate.Decimator attribute), 154
- max\_single\_factor (resistics.time.Decimate attribute), 354
- max\_subpopulation (resistics.regression.SolverScikitTheilSen attribute), 259
- max\_trials (resistics.regression.SolverScikitRANSAC attribute), 260
- MeasurementNotFoundError, 156
- measurements (resistics.gather.SiteCombinedMetadata attribute), 165
- measurements (resistics.project.Site attribute), 217
- messages (resistics.common.Record attribute), 110
- metadata (resistics.letsgo.ProjectCreator attribute), 170
- metadata (resistics.project.Measurement attribute), 210
- metadata (resistics.project.Project attribute), 229
- MetadataReadError, 156
- min\_n\_wins (resistics.window.WindowParameters attribute), 387
- min\_n\_wins (resistics.window.WindowSetup attribute), 391
- min\_olap (resistics.window.WindowSetup attribute), 391
- min\_samples (resistics.decimate.DecimationParameters attribute), 139
- min\_samples (resistics.decimate.DecimationSetup attribute), 142
- min\_samples (resistics.regression.SolverScikitRANSAC attribute), 260
- min\_size (resistics.window.WindowerTarget attribute), 406
- min\_size (resistics.window.WindowSetup attribute), 391
- module
- resistics, 408
  - resistics.calibrate, 90
  - resistics.common, 101
  - resistics.config, 117
  - resistics.decimate, 135
  - resistics.errors, 155
  - resistics.gather, 157
  - resistics.letsgo, 168
  - resistics.plot, 201
  - resistics.project, 203
  - resistics.regression, 230
  - resistics.sampling, 262
  - resistics.spectra, 275
  - resistics.testing, 297
  - resistics.time, 306
  - resistics.transfunc, 361
  - resistics.window, 373
- multiplier (resistics.time.Multiply attribute), 341
- ## N
- n\_chans (resistics.decimate.DecimatedMetadata attribute), 150
- n\_chans (resistics.spectra.SpectraMetadata attribute), 283
- n\_chans (resistics.time.TimeMetadata attribute), 314
- n\_chans (resistics.window.WindowedMetadata attribute), 399
- n\_cross (resistics.transfunc.TransferFunction attribute), 365
- n\_eqns\_per\_output() (resistics.transfunc.TransferFunction method), 367

- `n_evals` (*resisticks.gather.SiteCombinedMetadata* attribute), 165
  - `n_freqs` (*resisticks.regression.RegressionInputData* property), 241
  - `n_freqs` (*resisticks.regression.Solution* property), 255
  - `n_freqs` (*resisticks.spectra.SpectraLevelMetadata* attribute), 276
  - `n_header` (*resisticks.time.TimeReaderAscii* attribute), 325
  - `n_in` (*resisticks.transfunc.TransferFunction* attribute), 365
  - `n_iter` (*resisticks.regression.SolverScikitWLS* attribute), 261
  - `n_jobs` (*resisticks.regression.SolverScikitOLS* attribute), 257
  - `n_jobs` (*resisticks.regression.SolverScikitTheilSen* attribute), 259
  - `n_jobs` (*resisticks.regression.SolverScikitWLS* attribute), 261
  - `n_levels` (*resisticks.decimate.DecimatedMetadata* attribute), 150
  - `n_levels` (*resisticks.decimate.DecimationParameters* attribute), 139
  - `n_levels` (*resisticks.decimate.DecimationSetup* attribute), 142
  - `n_levels` (*resisticks.spectra.SpectraMetadata* attribute), 283
  - `n_levels` (*resisticks.window.WindowedMetadata* attribute), 400
  - `n_levels` (*resisticks.window.WindowParameters* attribute), 387
  - `n_meas` (*resisticks.project.Site* property), 218
  - `n_out` (*resisticks.transfunc.TransferFunction* attribute), 365
  - `n_regressors()` (*resisticks.transfunc.TransferFunction* method), 367
  - `n_samples` (*resisticks.calibrate.CalibrationData* attribute), 93
  - `n_samples` (*resisticks.decimate.DecimatedLevelMetadata* attribute), 143
  - `n_samples` (*resisticks.time.TimeMetadata* attribute), 314
  - `n_sites` (*resisticks.project.Project* property), 229
  - `n_subsamples` (*resisticks.regression.SolverScikitTheilSen* attribute), 259
  - `n_wins` (*resisticks.spectra.SpectraLevelMetadata* attribute), 276
  - `n_wins` (*resisticks.window.WindowedLevelMetadata* attribute), 393
  - `name` (*resisticks.common.ResisticksProcess* attribute), 115
  - `name` (*resisticks.config.Configuration* attribute), 134
  - `name` (*resisticks.project.Measurement* property), 210
  - `name` (*resisticks.project.Site* property), 218
  - `name` (*resisticks.time.ChanMetadata* attribute), 307
  - `name` (*resisticks.transfunc.TransferFunction* attribute), 364
  - `new()` (in module *resisticks.letsgo*), 170
  - `new_fs` (*resisticks.time.Resample* attribute), 351
  - `new_time_data()` (in module *resisticks.time*), 327
  - `normalize` (*resisticks.regression.SolverScikit* attribute), 256
  - `northing` (*resisticks.decimate.DecimatedMetadata* attribute), 151
  - `northing` (*resisticks.gather.SiteCombinedMetadata* attribute), 165
  - `northing` (*resisticks.spectra.SpectraMetadata* attribute), 283
  - `northing` (*resisticks.time.TimeMetadata* attribute), 315
  - `northing` (*resisticks.window.WindowedMetadata* attribute), 400
  - `notch` (*resisticks.time.Notch* attribute), 349
  - `NotDirectoryError`, 156
  - `NotFileError`, 156
  - `nyquist` (*resisticks.spectra.SpectraLevelMetadata* property), 276
  - `nyquist` (*resisticks.time.TimeMetadata* property), 315
- ## O
- `olap_proportion` (*resisticks.window.WindowerTarget* attribute), 406
  - `olap_proportion` (*resisticks.window.WindowSetup* attribute), 391
  - `olap_size` (*resisticks.spectra.SpectraLevelMetadata* attribute), 276
  - `olap_size` (*resisticks.window.WindowedLevelMetadata* attribute), 393
  - `olap_sizes` (*resisticks.window.WindowParameters* attribute), 387
  - `olap_sizes` (*resisticks.window.WindowSetup* attribute), 391
  - `order` (*resisticks.time.BandPass* attribute), 347
  - `order` (*resisticks.time.HighPass* attribute), 345
  - `order` (*resisticks.time.LowPass* attribute), 343
  - `order` (*resisticks.time.Notch* attribute), 349
  - `out_chans` (*resisticks.transfunc.ImpedanceTensor* attribute), 369
  - `out_chans` (*resisticks.transfunc.Tipper* attribute), 373
  - `out_chans` (*resisticks.transfunc.TransferFunction* attribute), 365
  - `overwrite` (*resisticks.common.ResisticksWriter* attribute), 117
- ## P
- `parameters()` (*resisticks.common.ResisticksProcess* method), 116
  - `path_to_string()` (in module *resisticks.errors*), 155
  - `PathError`, 156
  - `PathNotFoundError`, 156
  - `per_level` (*resisticks.decimate.DecimationParameters* attribute), 139
  - `per_level` (*resisticks.decimate.DecimationSetup* attribute), 142



- periods (*resisticks.regression.Solution* property), 255  
 phase (*resisticks.calibrate.CalibrationData* attribute), 93  
 plot() (*resisticks.calibrate.CalibrationData* method), 93  
 plot() (*resisticks.decimate.DecimatedData* method), 153  
 plot() (*resisticks.project.Project* method), 230  
 plot() (*resisticks.project.Site* method), 218  
 plot() (*resisticks.spectra.SpectraData* method), 284  
 plot() (*resisticks.time.TimeData* method), 321  
 plot() (*resisticks.transfunc.ImpedanceTensor* static method), 370  
 plot() (*resisticks.transfunc.Tipper* method), 373  
 plot\_level\_section() (*resisticks.spectra.SpectraData* method), 285  
 plot\_level\_stack() (*resisticks.spectra.SpectraData* method), 285  
 plot\_timeline() (in module *resisticks.plot*), 202  
 process\_evals\_to\_tf() (in module *resisticks.letsgo*), 200  
 process\_time() (in module *resisticks.letsgo*), 199  
 process\_time\_to\_evals() (in module *resisticks.letsgo*), 200  
 ProcessRunError, 157  
 profile\_windowing() (in module *resisticks.letsgo*), 199  
 proj (*resisticks.letsgo.ResisticksEnvironment* attribute), 195  
 ProjectCreateError, 156  
 ProjectLoadError, 156  
 ProjectPathError, 156
- ## Q
- quick\_read() (in module *resisticks.letsgo*), 198  
 quick\_spectra() (in module *resisticks.letsgo*), 198  
 quick\_tf() (in module *resisticks.letsgo*), 199  
 quick\_view() (in module *resisticks.letsgo*), 198
- ## R
- read\_calibration\_data() (*resisticks.calibrate.SensorCalibrationJSON* method), 97  
 read\_calibration\_data() (*resisticks.calibrate.SensorCalibrationReader* method), 96  
 read\_calibration\_data() (*resisticks.calibrate.SensorCalibrationTXT* method), 98  
 read\_data() (*resisticks.time.TimeReader* method), 323  
 read\_data() (*resisticks.time.TimeReaderAscii* method), 325  
 read\_data() (*resisticks.time.TimeReaderNumpy* method), 326  
 read\_metadata() (*resisticks.time.TimeReader* method), 323  
 read\_metadata() (*resisticks.time.TimeReaderJSON* method), 324  
 reader (*resisticks.project.Measurement* attribute), 210  
 ReadError, 156  
 readers (*resisticks.calibrate.InstrumentCalibrator* attribute), 100  
 readers (*resisticks.calibrate.SensorCalibrator* attribute), 101  
 real (*resisticks.transfunc.Component* attribute), 361  
 record\_example1() (in module *resisticks.testing*), 297  
 record\_example2() (in module *resisticks.testing*), 297  
 record\_type (*resisticks.common.Record* attribute), 110  
 records (*resisticks.common.History* attribute), 112  
 ref\_time (*resisticks.project.ProjectMetadata* attribute), 220  
 ref\_time (*resisticks.spectra.SpectraMetadata* attribute), 284  
 ref\_time (*resisticks.window.WindowedMetadata* attribute), 400  
 regression\_input\_metadata\_single\_site() (in module *resisticks.testing*), 304  
 regression\_preparer (*resisticks.config.Configuration* attribute), 135  
 RegressionInputData (class in *resisticks.regression*), 240  
 reload() (in module *resisticks.letsgo*), 195  
 remove\_record\_times() (in module *resisticks.testing*), 305  
 resample (*resisticks.decimate.Decimator* attribute), 154  
 resisticks  
     module, 408  
 resisticks.calibrate  
     module, 90  
 resisticks.common  
     module, 101  
 resisticks.config  
     module, 117  
 resisticks.decimate  
     module, 135  
 resisticks.errors  
     module, 155  
 resisticks.gather  
     module, 157  
 resisticks.letsgo  
     module, 168  
 resisticks.plot  
     module, 201  
 resisticks.project  
     module, 203  
 resisticks.regression  
     module, 230  
 resisticks.sampling  
     module, 262  
 resisticks.spectra  
     module, 275  
 resisticks.testing

- module, 297
  - resisticks.time
    - module, 306
  - resisticks.transfunc
    - module, 361
  - resisticks.window
    - module, 373
  - ResisticksBase (class in resisticks.common), 116
  - ResisticksData (class in resisticks.common), 117
  - run() (resisticks.calibrate.Calibrator method), 99
  - run() (resisticks.calibrate.InstrumentCalibrationReader method), 94
  - run() (resisticks.calibrate.SensorCalibrationReader method), 96
  - run() (resisticks.calibrate.SensorCalibrator method), 101
  - run() (resisticks.common.ResisticksWriter method), 117
  - run() (resisticks.decimate.DecimatedDataReader method), 155
  - run() (resisticks.decimate.DecimatedDataWriter method), 154
  - run() (resisticks.decimate.DecimationSetup method), 142
  - run() (resisticks.decimate.Decimator method), 154
  - run() (resisticks.gather.ProjectGather method), 166
  - run() (resisticks.gather.QuickGather method), 167
  - run() (resisticks.gather.Selector method), 161
  - run() (resisticks.letsgo.ProjectCreator method), 170
  - run() (resisticks.letsgo.ProjectLoader method), 171
  - run() (resisticks.regression.RegressionPreparerGathered method), 242
  - run() (resisticks.regression.RegressionPreparerSpectra method), 241
  - run() (resisticks.regression.Solver method), 256
  - run() (resisticks.regression.SolverScikitHuber method), 258
  - run() (resisticks.regression.SolverScikitOLS method), 257
  - run() (resisticks.regression.SolverScikitRANSAC method), 260
  - run() (resisticks.regression.SolverScikitTheilSen method), 259
  - run() (resisticks.spectra.EvaluationFreqs method), 292
  - run() (resisticks.spectra.FourierTransform method), 289
  - run() (resisticks.spectra.SpectraDataReader method), 293
  - run() (resisticks.spectra.SpectraDataWriter method), 293
  - run() (resisticks.spectra.SpectraProcess method), 294
  - run() (resisticks.spectra.SpectraSmootherGaussian method), 296
  - run() (resisticks.spectra.SpectraSmootherUniform method), 295
  - run() (resisticks.time.Add method), 339
  - run() (resisticks.time.ApplyFunction method), 360
  - run() (resisticks.time.BandPass method), 347
  - run() (resisticks.time.CropTimestamps method), 359
  - run() (resisticks.time.Decimate method), 354
  - run() (resisticks.time.HighPass method), 345
  - run() (resisticks.time.InterpolateNans method), 336
  - run() (resisticks.time.LowPass method), 343
  - run() (resisticks.time.Multiply method), 341
  - run() (resisticks.time.Notch method), 349
  - run() (resisticks.time.RemoveMean method), 337
  - run() (resisticks.time.Resample method), 351
  - run() (resisticks.time.ShiftTimestamps method), 357
  - run() (resisticks.time.Subsamples method), 335
  - run() (resisticks.time.Subsection method), 331
  - run() (resisticks.time.TimeProcess method), 328
  - run() (resisticks.time.TimeReader method), 322
  - run() (resisticks.time.TimeWriterAscii method), 327
  - run() (resisticks.time.TimeWriterNumpy method), 327
  - run() (resisticks.window.WindowedDataReader method), 407
  - run() (resisticks.window.WindowedDataWriter method), 407
  - run() (resisticks.window.Windower method), 404
  - run() (resisticks.window.WindowerTarget method), 406
  - run() (resisticks.window.WindowSetup method), 391
  - run\_decimation() (in module resisticks.letsgo), 195
  - run\_evals() (in module resisticks.letsgo), 196
  - run\_fft() (in module resisticks.letsgo), 196
  - run\_regression\_preparer() (in module resisticks.letsgo), 197
  - run\_sensor\_calibration() (in module resisticks.letsgo), 197
  - run\_solver() (in module resisticks.letsgo), 197
  - run\_spectra\_processors() (in module resisticks.letsgo), 196
  - run\_time\_processors() (in module resisticks.letsgo), 195
  - run\_windowing() (in module resisticks.letsgo), 196
- ## S
- sample\_to\_datetime() (in module resisticks.sampling), 268
  - samples\_to\_datetimes() (in module resisticks.sampling), 268
  - scale\_data() (resisticks.time.TimeReader method), 323
  - scaling (resisticks.time.ChanMetadata attribute), 308
  - Selection (class in resisticks.gather), 159
  - sensor (resisticks.calibrate.CalibrationData attribute), 93
  - sensor (resisticks.time.ChanMetadata attribute), 308
  - sensor\_calibration\_file (resisticks.time.ChanMetadata attribute), 308
  - sensor\_calibrator (resisticks.config.Configuration attribute), 135
  - serial (resisticks.calibrate.CalibrationData attribute), 93
  - serial (resisticks.decimate.DecimatedMetadata attribute), 150
  - serial (resisticks.gather.SiteCombinedMetadata attribute), 165

- serial (*resisticks.spectra.SpectraMetadata* attribute), 283  
 serial (*resisticks.time.ChanMetadata* attribute), 308  
 serial (*resisticks.time.TimeMetadata* attribute), 314  
 serial (*resisticks.window.WindowedMetadata* attribute), 400  
 serialize\_custom\_fnc() (in module *resisticks.time*), 359  
 set\_chan() (*resisticks.time.TimeData* method), 320  
 shift (*resisticks.time.ShiftTimestamps* attribute), 356  
 sigma (*resisticks.spectra.SpectraSmootherGaussian* attribute), 296  
 site\_name (*resisticks.gather.SiteCombinedMetadata* attribute), 165  
 site\_name (*resisticks.project.Measurement* attribute), 210  
 SiteCombinedData (class in *resisticks.gather*), 166  
 SiteNotFoundError, 156  
 sites (*resisticks.project.Project* attribute), 229  
 solution\_components() (*resisticks.transfunc.TransferFunction* method), 367  
 solution\_general() (in module *resisticks.testing*), 304  
 solution\_mt() (in module *resisticks.testing*), 304  
 solution\_random\_float() (in module *resisticks.testing*), 305  
 solution\_random\_int() (in module *resisticks.testing*), 305  
 solver (*resisticks.config.Configuration* attribute), 135  
 spectra\_data\_basic() (in module *resisticks.testing*), 302  
 spectra\_metadata\_multilevel() (in module *resisticks.testing*), 302  
 spectra\_processors (*resisticks.config.Configuration* attribute), 135  
 SpectraData (class in *resisticks.spectra*), 284  
 static\_gain (*resisticks.calibrate.CalibrationData* attribute), 93  
 style (*resisticks.time.ShiftTimestamps* attribute), 356  
 subsamples() (*resisticks.time.TimeData* method), 321  
 subsection() (*resisticks.time.TimeData* method), 320  
 summary() (*resisticks.common.ResisticksBase* method), 116  
 summary() (*resisticks.common.ResisticksModel* method), 106  
 system (*resisticks.decimate.DecimatedMetadata* attribute), 150  
 system (*resisticks.gather.SiteCombinedMetadata* attribute), 165  
 system (*resisticks.spectra.SpectraMetadata* attribute), 283  
 system (*resisticks.time.TimeMetadata* attribute), 314  
 system (*resisticks.window.WindowedMetadata* attribute), 400
- ## T
- target (*resisticks.window.WindowerTarget* attribute), 406  
 tf (*resisticks.config.Configuration* attribute), 135  
 tf (*resisticks.regression.Solution* attribute), 255  
 time\_data\_linear() (in module *resisticks.testing*), 299  
 time\_data\_ones() (in module *resisticks.testing*), 298  
 time\_data\_periodic() (in module *resisticks.testing*), 300  
 time\_data\_random() (in module *resisticks.testing*), 299  
 time\_data\_simple() (in module *resisticks.testing*), 298  
 time\_data\_with\_nans() (in module *resisticks.testing*), 299  
 time\_data\_with\_offset() (in module *resisticks.testing*), 300  
 time\_local (*resisticks.common.Record* attribute), 109  
 time\_metadata\_1chan() (in module *resisticks.testing*), 297  
 time\_metadata\_2chan() (in module *resisticks.testing*), 297  
 time\_metadata\_general() (in module *resisticks.testing*), 298  
 time\_metadata\_mt() (in module *resisticks.testing*), 298  
 time\_processors (*resisticks.config.Configuration* attribute), 134  
 time\_readers (*resisticks.config.Configuration* attribute), 134  
 time\_unit (*resisticks.time.CropTimestamps* attribute), 359  
 time\_utc (*resisticks.common.Record* attribute), 109  
 TimeData (class in *resisticks.time*), 319  
 TimeDataReadError, 156  
 to\_dataframe() (*resisticks.calibrate.CalibrationData* method), 93  
 to\_dataframe() (*resisticks.decimate.DecimationParameters* method), 141  
 to\_dataframe() (*resisticks.project.Project* method), 230  
 to\_dataframe() (*resisticks.project.Site* method), 218  
 to\_dataframe() (*resisticks.regression.Solution* method), 255  
 to\_datetime() (in module *resisticks.sampling*), 263  
 to\_n\_samples() (in module *resisticks.sampling*), 266  
 to\_numpy() (*resisticks.decimate.DecimationParameters* method), 140  
 to\_numpy() (*resisticks.transfunc.Component* method), 362  
 to\_sample (*resisticks.time.Subsamples* attribute), 335  
 to\_seconds() (in module *resisticks.sampling*), 265  
 to\_string() (*resisticks.common.ResisticksBase* method), 116  
 to\_string() (*resisticks.common.ResisticksModel* method), 106  
 to\_string() (*resisticks.decimate.DecimatedData* method), 153

`to_string()` (*resisticks.time.TimeData* method), 321  
`to_string()` (*resisticks.transfunc.TransferFunction* method), 367  
`to_string()` (*resisticks.window.WindowedData* method), 401  
`to_time` (*resisticks.time.Subsection* attribute), 331  
`to_time_to_sample()` (in module *resisticks.sampling*), 271  
`to_timedelta()` (in module *resisticks.sampling*), 264  
`to_timestamp()` (in module *resisticks.sampling*), 264  
`transfer_function_random()` (in module *resisticks.testing*), 303  
`trimmed_mean()` (*resisticks.regression.SolverScikitWLS* method), 261  
`type_to_string()` (*resisticks.common.ResisticksBase* method), 116

## V

`validate()` (*resisticks.common.ResisticksProcess* class method), 115  
`validate()` (*resisticks.sampling.HighResDateTime* class method), 262  
`validate()` (*resisticks.transfunc.TransferFunction* class method), 365  
`variation` (*resisticks.transfunc.ImpedanceTensor* attribute), 369  
`variation` (*resisticks.transfunc.Tipper* attribute), 372  
`variation` (*resisticks.transfunc.TransferFunction* attribute), 364  
`version` (*resisticks.common.ResisticksFile* attribute), 107

## W

`wgs84_latitude` (*resisticks.decimate.DecimatedMetadata* attribute), 150  
`wgs84_latitude` (*resisticks.gather.SiteCombinedMetadata* attribute), 165  
`wgs84_latitude` (*resisticks.spectra.SpectraMetadata* attribute), 283  
`wgs84_latitude` (*resisticks.time.TimeMetadata* attribute), 314  
`wgs84_latitude` (*resisticks.window.WindowedMetadata* attribute), 400  
`wgs84_longitude` (*resisticks.decimate.DecimatedMetadata* attribute), 150  
`wgs84_longitude` (*resisticks.gather.SiteCombinedMetadata* attribute), 165  
`wgs84_longitude` (*resisticks.spectra.SpectraMetadata* attribute), 283  
`wgs84_longitude` (*resisticks.time.TimeMetadata* attribute), 314

`wgs84_longitude` (*resisticks.window.WindowedMetadata* attribute), 400  
`win_duration()` (in module *resisticks.window*), 375  
`win_factor` (*resisticks.window.WindowSetup* attribute), 391  
`win_fnc` (*resisticks.spectra.FourierTransform* attribute), 289  
`win_setup` (*resisticks.config.Configuration* attribute), 134  
`win_size` (*resisticks.spectra.SpectraLevelMetadata* attribute), 276  
`win_size` (*resisticks.window.WindowedLevelMetadata* attribute), 393  
`win_sizes` (*resisticks.window.WindowParameters* attribute), 387  
`win_sizes` (*resisticks.window.WindowSetup* attribute), 391  
`win_to_datetime()` (in module *resisticks.window*), 377  
`WindowedData` (class in *resisticks.window*), 400  
`windower` (*resisticks.config.Configuration* attribute), 134  
`workers` (*resisticks.spectra.FourierTransform* attribute), 289  
`write()` (*resisticks.common.WriteableMetadata* method), 108  
`WriteError`, 156

## Y

`year` (*resisticks.project.ProjectMetadata* attribute), 220